

MultiNet for OpenVMS Administrator's Reference

Part Number: N-5011-44-NN-A

December 2001

This guide provides information to configure and manage MultiNet for the experienced system manager. Before using this guide, install and start MultiNet as described in the *MultiNet for OpenVMS Installation and Introduction*.

Revision/Update: This guide supersedes the *MultiNet Administrator's Reference*, V4.3.

Operating System/Version: VAX/VMS V5.5-2 or later, OpenVMS VAX V6.0 or later, or OpenVMS Alpha V6.1 or later

Software Version: MultiNet V4.4

**Process Software
Framingham, Massachusetts
USA**

The material in this document is for informational purposes only and is subject to change without notice. It should not be construed as a commitment by Process Software. Process Software assumes no responsibility for any errors that may appear in this document.

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013.

The following third-party software may be included with your product and will be subject to the software license agreement.

Network Time Protocol (NTP). Copyright © 1992 by David L. Mills. The University of Delaware makes no representations about the suitability of this software for any purpose.

Point-to-Point Protocol. Copyright © 1989 by Carnegie-Mellon University. All rights reserved. The name of the University may not be used to endorse or promote products derived from this software without specific prior written permission. Redistribution and use in source and binary forms are permitted provided that the above copyright notice and this paragraph are duplicated in all such forms and that any documentation, advertising materials, and other materials related to such distribution and use acknowledge that the software was developed by Carnegie Mellon University. The name of the University may not be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED ``AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

RES_RANDOM.C. Copyright © 1997 by Niels Provos <provos@physnet.uni-hamburg.de> All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement: This product includes software developed by Niels Provos.
4. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

Copyright © 1990 by John Robert LoVerso. All rights reserved. Redistribution and use in source and binary forms are permitted provided that the above copyright notice and this paragraph are duplicated in all such forms and that any documentation, advertising materials, and other materials related to such distribution and use acknowledge that the software was developed by John Robert LoVerso.

Kerberos. Copyright © 1989, DES.C and PCBC_ENCRYPT.C Copyright © 1985, 1986, 1987, 1988 by Massachusetts Institute of Technology. Export of this software from the United States of America is assumed to require a specific license from the United States Government. It is the responsibility of any person or organization contemplating export to obtain such a license before exporting. WITHIN THAT CONSTRAINT, permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of M.I.T. not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. M.I.T. makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

DNSSIGNER (from BIND distribution) Portions Copyright (c) 1995-1998 by Trusted Information Systems, Inc. Portions Copyright (c) 1998-1999 Network Associates, Inc.

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THE

SOFTWARE IS PROVIDED "AS IS" AND TRUSTED INFORMATION SYSTEMS DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL TRUSTED INFORMATION SYSTEMS BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

ERRWARN.C. Copyright © 1995 by RadioMail Corporation. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of RadioMail Corporation, the Internet Software Consortium nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission. THIS SOFTWARE IS PROVIDED BY RADIOMAIL CORPORATION, THE INTERNET SOFTWARE CONSORTIUM AND CONTRIBUTORS ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL RADIOMAIL CORPORATION OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE. This software was written for RadioMail Corporation by Ted Lemon under a contract with Vixie Enterprises. Further modifications have been made for the Internet Software Consortium under a contract with Vixie Laboratories.

IMAP4R1.C, MISC.C, RFC822.C, SMTP.C Original version Copyright © 1988 by The Leland Stanford Junior University

ACCPORNAM technology Copyright (c) 1999 by Brian Schenkenberger - TMESIS SOFTWARE

NS_PARSER.C Copyright © 1984, 1989, 1990 by Bob Corbett and Richard Stallman
This program is free software. You can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 1, or (at your option) any later version. This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details. You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 675 Mass Ave, Cambridge, MA 02139 USA

IF_ACPC Copyright © 1985 and IF_DDA.C Copyright © 1986 by Advanced Computer Communications

IF_PPP.C Copyright © 1993 by Drew D. Perkins

ASCII_ADDR.C Copyright © 1994 Bell Communications Research, Inc. (Bellcore)

DEBUG.C Copyright © 1998 by Lou Bergandi. All Rights Reserved.

NTP_FILEGEN.C Copyright © 1992 by Rainer Pruy Friedrich-Alexander Universitaet Erlangen-Nuernberg

RANNY.C Copyright © 1988 by Rayan S. Zachariassen. All Rights Reserved.

MD5.C Copyright © 1990 by RSA Data Security, Inc. All Rights Reserved.

Portions Copyright © 1981, 1982, 1983, 1984, 1985, 1986, 1987, 1988, 1989 by SRI International

Portions Copyright © 1984, 1989 by Free Software Foundation

Portions Copyright © 1993, 1994, 1995, 1996, 1997, 1998 by the University of Washington. Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notices appear in all copies and that both the above copyright notices and this permission notice appear in supporting documentation, and that the name of the University of Washington or The Leland Stanford Junior University not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. This software is made available "as is", and THE UNIVERSITY OF WASHINGTON AND THE LELAND STANFORD JUNIOR UNIVERSITY DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, WITH REGARD TO THIS SOFTWARE, INCLUDING WITHOUT LIMITATION ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, AND IN NO EVENT SHALL THE UNIVERSITY OF WASHINGTON OR THE LELAND STANFORD JUNIOR UNIVERSITY BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, TORT (INCLUDING NEGLIGENCE) OR STRICT LIABILITY, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Portions Copyright © 1980, 1982, 1985, 1986, 1988, 1989, 1990, 1993 by The Regents of the University of California. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:

This product includes software developed by the University of California, Berkeley and its contributors.

4. Neither the name of the University nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Portions Copyright © 1993 by Compaq Computer Corporation.

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies, and that the name of Compaq Computer Corporation not be used in advertising or publicity pertaining to distribution of the document or software without specific, written prior permission. THE SOFTWARE IS PROVIDED "AS IS" AND COMPAQ COMPUTER CORP. DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL COMPAQ COMPUTER CORPORATION BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING

FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Portions Copyright © 1995 by International Business Machines, Inc.

International Business Machines, Inc. (hereinafter called IBM) grants permission under its copyrights to use, copy, modify, and distribute this Software with or without fee, provided that the above copyright notice and all paragraphs of this notice appear in all copies, and that the name of IBM not be used in connection with the marketing of any product incorporating the Software or modifications thereof, without specific, written prior permission. To the extent it has a right to do so, IBM grants an immunity from suit under its patents, if any, for the use, sale or manufacture of products to the extent that such products are used for performing Domain Name System dynamic updates in TCP/IP networks by means of the Software. No immunity is granted for any product per se or for any other function of any product. THE SOFTWARE IS PROVIDED "AS IS", AND IBM DISCLAIMS ALL WARRANTIES, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. IN NO EVENT SHALL IBM BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE, EVEN IF IBM IS APPRISED OF THE POSSIBILITY OF SUCH DAMAGES.

Portions Copyright © 1995, 1996, 1997, 1998, 1999, 2000 by Internet Software Consortium. All Rights Reserved. Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies. THE SOFTWARE IS PROVIDED "AS IS" AND INTERNET SOFTWARE CONSORTIUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL INTERNET SOFTWARE CONSORTIUM BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Copyright (c) 1996-2000 Internet Software Consortium.

Use is subject to license terms which appear in the file named ISC-LICENSE that should have accompanied this file when you received it. If a file named ISC-LICENSE did not accompany this file, or you are not sure the one you have is correct, you may obtain an applicable copy of the license at: <http://www.isc.org/isc-license-1.0.html>. This file is part of the ISC DHCP distribution. The documentation associated with this file is listed in the file DOCUMENTATION, included in the top-level directory of this release. Support and other services are available for ISC products - see <http://www.isc.org> for more information.

ISC LICENSE, Version 1.0

1. This license covers any file containing a statement following its copyright message indicating that it is covered by this license. It also covers any text or binary file, executable, electronic or printed image that is derived from a file that is covered by this license, or is a modified version of a file covered by this license, whether such works exist now or in the future. Hereafter, such works will be referred to as "works covered by this license," or "covered works."
2. Each source file covered by this license contains a sequence of text starting with the copyright message and ending with "Support and other services are available for ISC products - see <http://www.isc.org> for more information." This will hereafter be referred to as the file's Bootstrap License.
3. If you take significant portions of any source file covered by this license and include those portions in some other file, then you must also copy the Bootstrap License into that other file, and that file becomes a covered file. You may make a good-faith judgement as to where in this file the bootstrap license should appear.
4. The acronym "ISC", when used in this license or generally in the context of works covered by this license, is an abbreviation for the words "Internet Software Consortium."
5. A distribution, as referred to hereafter, is any file, collection of printed text, CD ROM, boxed set, or other collection, physical or electronic, which can be distributed as a single object and which contains one or more works covered by this license.
6. You may make distributions containing covered files and provide copies of such distributions to whomever you choose, with or without charge, as long as you obey the other terms of this license. Except as stated in (9), you may include as many or as few covered files as you choose in such distributions.

7. When making copies of covered works to distribute to others, you must not remove or alter the Bootstrap License. You may not place your own copyright message, license, or similar statements in the file prior to the original copyright message or anywhere within the Bootstrap License. Object files and executable files are exempt from the restrictions specified in this clause.
8. If the version of a covered source file as you received it, when compiled, would normally produce executable code that would print a copyright message followed by a message referring to an ISC web page or other ISC documentation, you may not modify the file in such a way that, when compiled, it no longer produces executable code to print such a message.
9. Any source file covered by this license will specify within the Bootstrap License the name of the ISC distribution from which it came, as well as a list of associated documentation files. The associated documentation for a binary file is the same as the associated documentation for the source file or files from which it was derived. Associated documentation files contain human-readable documentation which the ISC intends to accompany any distribution.

If you produce a distribution, then for every covered file in that distribution, you must include all of the associated documentation files for that file. You need only include one copy of each such documentation file in such distributions.

Absence of required documentation files from a distribution you receive or absence of the list of documentation files from a source file covered by this license does not excuse you from this requirement. If the distribution you receive does not contain these files, you must obtain them from the ISC and include them in any redistribution of any work covered by this license. For information on how to obtain required documentation not included with your distribution, see: <http://www.isc.org/getting-documentation.html>.

If the list of documentation files was removed from your copy of a covered work, you must obtain such a list from the ISC. The web page at <http://www.isc.org/getting-documentation.html> contains pointers to lists of files for each ISC distribution covered by this license.

It is permissible in a source or binary distribution containing covered works to include reformatted versions of the documentation files. It is also permissible to add to or modify the documentation files, as long as the formatting is similar in legibility, readability, font, and font size to other documentation in the derived product, as long as any sections labeled CONTRIBUTIONS in these files are unchanged except with respect to formatting, as long as the order in which the CONTRIBUTIONS section appears in these files is not changed, and as long as the manual page which describes how to contribute to the Internet Software Consortium (hereafter referred to as the Contributions Manual Page) is unchanged except with respect to formatting.

Documentation that has been translated into another natural language may be included in place of or in addition to the required documentation, so long as the CONTRIBUTIONS section and the Contributions Manual Page are either left in their original language or translated into the new language with such care and diligence as is required to preserve the original meaning.

10. You must include this license with any distribution that you make, in such a way that it is clearly associated with such covered works as are present in that distribution. In any electronic distribution, the license must be in a file called "ISC-LICENSE".

If you make a distribution that contains works from more than one ISC distribution, you may either include a copy of the ISC-LICENSE file that accompanied each such ISC distribution in such a way that works covered by each license are all clearly grouped with that license, or you may include the single copy of the ISC-LICENSE that has the highest version number of all the ISC-LICENSE files included with such distributions, in which case all covered works will be covered by that single license file. The version number of a license appears at the top of the file containing the text of that license, or if in printed form, at the top of the first page of that license.

11. If the list of associated documentation is in a separated file, you must include that file with any distribution you make, in such a way that the relationship between that file and the files that refer to it is clear. It is not permissible to merge such files in the event that you make a distribution including files from more than one ISC distribution, unless all the Bootstrap Licenses refer to files for their lists of associated documentation, and those

references all list the same filename.

12. If a distribution that includes covered works includes a mechanism for automatically installing covered works, following that installation process must not cause the person following that process to violate this license, knowingly or unknowingly. In the event that the producer of a distribution containing covered files accidentally or wilfully violates this clause, persons other than the producer of such a distribution shall not be held liable for such violations, but are not otherwise excused from any requirement of this license.

13. COVERED WORKS ARE PROVIDED "AS IS". ISC DISCLAIMS ALL WARRANTIES WITH REGARD TO COVERED WORKS INCLUDING THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

14. IN NO EVENT SHALL ISC BE LIABLE FOR ANY SPECIAL, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OF COVERED WORKS.

Use of covered works under different terms is prohibited unless you have first obtained a license from ISC granting use pursuant to different terms. Such terms may be negotiated by contacting ISC as follows:

Internet Software Consortium
950 Charter Street
Redwood City, CA 94063
Tel: 1-888-868-1001 (toll free in U.S.)
Tel: 1-650-779-7091
Fax: 1-650-779-7055
Email: info@isc.org
Email: licensing@isc.org

DNSSAFE LICENSE TERMS

This BIND software includes the DNSsafe software from RSA Data Security, Inc., which is copyrighted software that can only be distributed under the terms of this license agreement.

The DNSsafe software cannot be used or distributed separately from the BIND software. You only have the right to use it or distribute it as a bundled, integrated product.

The DNSsafe software can ONLY be used to provide authentication for resource records in the Domain Name System, as specified in RFC 2065 and successors. You cannot modify the BIND software to use the DNSsafe software for other purposes, or to make its cryptographic functions available to end-users for other uses.

If you modify the DNSsafe software itself, you cannot modify its documented API, and you must grant RSA Data Security the right to use, modify, and distribute your modifications, including the right to use any patents or other intellectual property that your modifications depend upon.

You must not remove, alter, or destroy any of RSA's copyright notices or license information. When distributing the software to the Federal Government, it must be licensed to them as "commercial computer software" protected under 48 CFR 12.212 of the FAR, or 48 CFR 227.7202.1 of the DFARS.

You must not violate United States export control laws by distributing the DNSsafe software or information about it, when such distribution is prohibited by law.

THE DNSSAFE SOFTWARE IS PROVIDED "AS IS" WITHOUT ANY WARRANTY WHATSOEVER. RSA HAS NO OBLIGATION TO SUPPORT, CORRECT, UPDATE OR MAINTAIN THE RSA SOFTWARE. RSA DISCLAIMS ALL WARRANTIES, EXPRESS, IMPLIED OR STATUTORY, AS TO ANY MATTER WHATSOEVER, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A

PARTICULAR PURPOSE AND NON-INFRINGEMENT OF THIRD PARTY RIGHTS.

If you desire to use DNSsafe in ways that these terms do not permit, please contact:

RSA Data Security, Inc.

100 Marine Parkway

Redwood City, California 94065, USA

to discuss alternate licensing arrangements.

Secure Shell (SSH). Copyright © 2000. This License agreement, including the Exhibits ("Agreement"), effective as of the latter date of execution ("Effective Date"), is hereby made by and between Data Fellows, Inc., a California corporation, having principal offices at 675 N. First Street, 8th floor, San Jose, CA 95112170 ("Data Fellows") and Process Software, Inc., a Massachusetts corporation, having a place of business at 959 Concord Street, Framingham, MA 01701 ("OEM").

All other trademarks, service marks, registered trademarks, or registered service marks mentioned in this document are the property of their respective holders.

MultiNet is a registered trademark and Process Software and the Process Software logo are trademarks of Process Software.

Copyright ©1997, 1998, 1999, 2000 Process Software Corporation. All rights reserved. Printed in USA.

Copyright ©2000, 2001 Process Software, LLC. All rights reserved. Printed in USA.

If the examples of URLs, domain names, internet addresses, and web sites we use in this documentation reflect any that actually exist, it is not intentional and should not to be considered an endorsement, approval, or recommendation of the actual site, or any products or services located at any such site by Process Software. Any resemblance or duplication is strictly coincidental.

Contents

Preface

Obtaining Technical Support	xix
Before Contacting Technical Support	xix
Sending Electronic Mail	xx
Calling Technical Support.....	xxi
Contacting Technical Support by Fax.....	xxi
Obtaining Online Help.....	xxi
MultiNet Frequently Asked Questions List.....	xxii
Accessing the MultiNet Public Mailing List	xxii
Process Software World Wide Web Server.....	xxii
Obtaining Software Patches Over the Internet	xxii
RFCs (Requests for Comment).....	xxiii
Typographical Conventions	xxiv

Chapter 1 MultiNet DCL Command Reference

Command Summary	1-1
MULTINET ACCOUNTING.....	1-6
MULTINET CHECK.....	1-7
MULTINET CONFIGURE	1-8
MULTINET DIG	1-11
Example	1-15
MULTINET DNSKEYGEN.....	1-17
MULTINET DNSSIGNER.....	1-20
Input/output details	1-20
Parent file handling	1-20
NXT details	1-21
Key details	1-21
SIG expiration details	1-21

MULTINET FONT COMPILE	1-27
MULTINET FONT INFO	1-28
MULTINET FONT LIST	1-29
MULTINET FONT MKFONTDIR.....	1-30
MULTINET FONT SHOW	1-31
MULTINET FONT UNCOMPILE	1-33
MULTINET HOST_TABLE COMPILE.....	1-34
MULTINET HOST_TABLE GET.....	1-36
MULTINET HOST_TABLE INSTALL.....	1-38
MULTINET IPP SHOW	1-39
MULTINET KERBEROS DATABASE DUMP	1-45
MULTINET KERBEROS DATABASE EDIT	1-46
MULTINET KERBEROS DATABASE INITIALIZE.....	1-49
MULTINET KERBEROS DATABASE LOAD	1-50
MULTINET KERBEROS DATABASE NEW_MASTER_KEY	1-51
MULTINET KERBEROS DATABASE SRVTAB.....	1-52
MULTINET KERBEROS DATABASE STASH.....	1-53
MULTINET LOAD.....	1-54
MULTINET NETCONTROL	1-55
MULTINET NFSDISMOUNT	1-77
MULTINET NFSMOUNT.....	1-78
MULTINET NSLOOKUP	1-84
MULTINET NSUPDATE.....	1-88
MULTINET PING	1-91
MULTINET RDATE	1-93
MULTINET RMTALLOC.....	1-94
MULTINET RWALL.....	1-101
MULTINET SET /ARP.....	1-102
MULTINET SET /DECNET.....	1-104
MULTINET SET /INTERFACE.....	1-106
Restrictions:	1-107
MULTINET SET /ROUTE	1-112
MULTINET SET /TIMEZONE	1-114
MULTINET SHOW	1-115
MULTINET TCPDUMP.....	1-122
MULTINET TCPVIEW	1-126
MULTINET TRACEROUTE	1-131
MULTINET X11DEBUG	1-134

Chapter 2 MultiNet Secure/IP DCL Commands

MULTINET PROFILE /DELETE	2-3
MULTINET PROFILE /MODIFY.....	2-4
MULTINET PROFILE /SHOW.....	2-5
MULTINET PROFILE /SUMMARY	2-6
MULTINET SKEY	2-7

MULTINET TOKEN CRYPTOCARD /CLEAR	2-9
MULTINET TOKEN CRYPTOCARD /LOAD	2-10
MULTINET TOKEN CRYPTOCARD /TEST	2-18
MULTINET TOKEN SKEY /CLEAR	2-19
MULTINET TOKEN SKEY /INITIALIZE	2-20
MULTINET TOKEN SKEY /SHOW	2-23
MULTINET TOKEN SKEY /TEST	2-24
MULTINET TOKEN SNK /CLEAR	2-25
MULTINET TOKEN SNK /LOAD	2-26
MULTINET TOKEN SNK /TEST	2-29

Chapter 3 DECNET-CONFIG Command Reference

Command Summary	3-1
ADD	3-3
ATTACH	3-4
CLEAR	3-5
DELETE	3-6
ERASE	3-7
EXIT	3-8
GET	3-9
HELP	3-10
MODIFY	3-11
PUSH	3-12
QUIT	3-13
SAVE	3-14
SHOW	3-15
SPAWN	3-16
STATUS	3-18
USE	3-19
VERSION	3-20
WRITE	3-21

Chapter 4 MAIL-CONFIG Command Reference

Command Summary	4-1
ADD GATEWAY	4-5
ADD LOCAL-DOMAIN	4-6
ADD QUEUE-GROUP	4-7
ATTACH	4-8
CLEAR	4-9
DELETE GATEWAY	4-10
DELETE LOCAL-DOMAIN	4-11
DELETE QUEUE-GROUP	4-12
ERASE	4-13

EXIT	4-14
GET	4-15
HELP	4-16
PUSH	4-17
QUIT	4-18
REMOVE GATEWAY	4-19
REMOVE QUEUE-GROUP	4-20
SAVE	4-21
SET ACCOUNTING-HOST	4-22
SET ACCOUNTING-PORT	4-23
SET ALIAS-FILE	4-24
SET DECNET-DOMAIN	4-25
SET DELIVERY-RECEIPTS	4-26
SET DISALLOW-USER-REPLY-TO	4-27
SET DISABLE-PSMAIL	4-28
SET FORWARDER	4-29
SET FORWARD-LOCAL-MAIL	4-30
SET FORWARD-REMOTE-MAIL	4-31
SET HEADER-CONTROL	4-32
SET HOST-ALIAS-FILE	4-33
SET LOCAL-MAIL-FORWARDER	4-34
SET POSTMASTER	4-35
SET QUEUE-COUNT	4-36
SET REPLY-CONTROL	4-37
SET RESENT-HEADERS	4-38
SET RETRY-INTERVAL	4-39
SET RETURN-INTERVAL	4-40
SET RFC2789	4-41
SET SEND-BROADCAST-CLASS	4-42
SET SMTP-HOST-NAMES	4-43
SET START-QUEUE-MANAGER	4-44
SHOW	4-45
SPAWN	4-46
STATUS	4-47
USE	4-48
VERSION	4-49
WRITE	4-50

Chapter 5 NET-CONFIG Command Reference

ADD	5-4
ATTACH	5-13
CHECK	5-14
CLEAR	5-17
DELETE	5-18
DISABLE	5-19

ENABLE.....	5-20
ERASE.....	5-21
EXIT	5-22
GET.....	5-23
HELP.....	5-24
MODIFY	5-25
PUSH	5-26
QUIT	5-27
SAVE	5-28
SET ANONYMOUS-FTP-DIRECTORY	5-29
SET CLUSTER-SERVICE-ADDRESS	5-30
SET CLUSTER-SERVICE-NAMES	5-31
SET DEFAULT-RMT-TAPE-DEVICE	5-32
SET DEFAULT-ROUTE.....	5-33
SET DOMAIN-NAMESERVERS	5-34
SET HOST-NAME	5-36
SET IP-CLUSTER-ALIASES	5-37
SET LOAD-EXOS-DRIVER	5-38
SET LOAD-PWIP-DRIVER	5-39
SET LOCAL-DOMAIN	5-40
SET LPD-DEFAULT-USERNAME	5-41
SET NAMESERVER-RETRANSMISSION	5-42
SET SPOOL-DIRECTORY.....	5-43
SET TFTP-DIRECTORY	5-44
SET TIMEZONE	5-45
SET TIMEZONE-RULES	5-46
SET WHOIS-DEFAULT-SERVER	5-47
SET WINS-COMPATIBILITY	5-48
SHOW	5-49
SPAWN.....	5-51
STATUS	5-53
USE	5-54
VERSION	5-55
WRITE.....	5-56

Chapter 6 NFS-CONFIG Command Reference

Command Summary	6-1
ADD DECSTATION-MOUNT-POINT	6-6
ADD EXPORT	6-7
ADD MOUNT-RESTRICTION	6-8
ADD NFS-GROUP.....	6-9
ADD NFS-PASSWD-FILE	6-10
ADD UID-TRANSLATION	6-11
APPEND	6-12

ATTACH	6-13
CURRENT	6-14
DELETE DECSTATION-MOUNT-POINT	6-15
DELETE EXPORTED-FILE-SYSTEM	6-16
DELETE MOUNT-RESTRICTION	6-17
DELETE NFS-GROUP	6-18
DELETE NFS-PASSWD-FILE	6-19
DELETE UID-TRANSLATION	6-20
EXIT	6-21
GET	6-22
HELP	6-23
NETCONTROL	6-24
PUSH	6-25
QUIT	6-26
RELOAD	6-27
RESTART	6-28
SAVE	6-29
SELECT	6-30
SET APPROXIMATE-TEXT-SIZE-THRESHOLD	6-31
SET DIRECTORY-INFO-FLUSH-AGE	6-32
SET DIRECTORY-INFO-IDLE-FLUSH-AGE	6-33
SET FILE-CACHE-TIMER-INTERVAL	6-34
SET FILE-INFO-FLUSH-AGE	6-35
SET FILE-INFO-IDLE-FLUSH-AGE	6-36
SET MAXIMUM-CACHE-BUFFERS	6-37
SET MAXIMUM-CACHE-FILES	6-38
SET MAXIMUM-DIRTY-BUFFERS	6-39
SET MAXIMUM-FILESYSTEM-BUFFERS	6-40
SET MAXIMUM-FILESYSTEM-CHANNELS	6-41
SET MAXIMUM-FILESYSTEM-FILES	6-42
SET MAXIMUM-OPEN-CHANNELS	6-43
SET MAXIMUM-QUEUED-REMOVES	6-44
SET MAXIMUM-WRITE-JOBS	6-45
SET NUMBER-OF-DUPLICATE-REQUESTS-CACHED	6-46
SET NUMBER-OF-RPC-TRANSPORTS	6-47
SET READ-ONLY-FLUSH-AGE	6-48
SET READ-WRITE-FLUSH-AGE	6-49
SET SECONDS-BEFORE-WRITEBACK	6-50
SET USE-DIRECTORY-BLOCKING-ASTS	6-51
SET USE-FILE-BLOCKING-ASTS	6-52
SHOW	6-53
SPAWN	6-54
STATUS	6-56
USE	6-57
VERSION	6-58
WRITE	6-59

Chapter 7 NTYCP Command Reference

Command Summary	7-2
CREATE PORT	7-3
DELETE PORT	7-5
EXIT	7-6
HELP	7-7
MODIFY PORT	7-8

Chapter 8 ACCESS-CONFIG Commands

Command Summary	8-1
ADD	8-4
ATTACH	8-5
EXIT	8-6
GET	8-7
HELP	8-8
NETCONTROL	8-9
PUSH	8-10
QUIT	8-11
RELOAD	8-12
REMOVE	8-13
SAVE	8-14
SET	8-15
SHOW	8-19
SPAWN	8-20
STATUS	8-22
USE	8-23
VERSION	8-24
WRITE	8-25

Chapter 9 PRINTER-CONFIG Command Reference

Command Summary	9-1
ADD	9-5
ATTACH	9-6
CLEAR	9-7
DELETE	9-8
ERASE	9-9
EXIT	9-10
GET	9-11
HELP	9-12
MODIFY	9-13
PUSH	9-14
QUIT	9-15

SAVE.....	9-16
SELECT.....	9-17
SET ALLOW-USER-SPECIFIED-PRINTER	9-18
SET BASE-PRIORITY	9-19
SET BLOCK-LIMIT-LOWER.....	9-20
SET BLOCK-LIMIT-UPPER	9-21
SET BURST	9-22
SET CHARACTERISTICS.....	9-23
SET DEFAULT-FORM	9-24
SET DESCRIPTION	9-25
SET FLAG.....	9-26
SET LIBRARY.....	9-27
SET NOFEED	9-28
SET OWNER	9-29
SET PROTECTION	9-30
SET RETAIN-ON-ERROR.....	9-31
SET SCHEDULE-NOSIZE.....	9-32
SET SEPARATE-BURST.....	9-33
SET SEPARATE-FLAG	9-34
SET SEPARATE-RESET	9-35
SET SEPARATE-TRAILER.....	9-36
SET SUPPRESS-EOJ-FF.....	9-37
SET SUPPRESS-REMOTE-BANNER	9-38
SET SUPPRESS-TELNET.....	9-39
SET TAB-EXPAND.....	9-40
SET TRAILER	9-41
SET WS-DEFAULT.....	9-42
SET WS-EXTENT	9-43
SET WS-QUOTA.....	9-44
SHOW	9-45
SPAWN	9-46
STATUS	9-48
USE.....	9-49
VERSION.....	9-50
WRITE.....	9-51

Chapter 10 SERVER-CONFIG Command Reference

Command Summary.....	10-1
ADD.....	10-5
ATTACH	10-6
COPY.....	10-7
DELETE	10-8
DISABLE	10-9
ENABLE	10-10

EXIT	10-11
GET	10-12
HELP.....	10-13
NETCONTROL	10-14
PUSH	10-15
QUIT	10-16
RESTART	10-17
SAVE	10-18
SELECT	10-19
SET ACCEPT-HOSTS	10-20
SET ACCEPT-NETS	10-21
SET BACKLOG	10-22
SET CONNECTED	10-23
SET DISABLED-NODES	10-24
SET ENABLED-NODES	10-25
SET FLAGS	10-26
SET INIT	10-28
SET KEEPALIVE-TIMERS	10-29
SET LISTEN	10-30
SET LOG-ACCEPTS	10-31
SET LOG-FILE	10-32
SET LOG-REJECTS	10-33
SET MAX-SERVERS	10-34
SET PARAMETERS	10-35
SET PRIORITY	10-36
SET PROCESS	10-37
SET PROGRAM.....	10-38
SET REJECT-BY-DEFAULT	10-39
SET RECEIVE-BUFFER-SPACE	10-40
SET REJECT-HOSTS	10-41
SET REJECT-MESSAGE	10-42
SET REJECT-NETS	10-43
SET SEND-BUFFER-SPACE.....	10-44
SET SERVICE.....	10-45
SET SERVICE-NAME.....	10-46
SET SERVICE-TYPE	10-47
SET SOCKET-FAMILY	10-48
SET SOCKET-OPTIONS.....	10-49
SET SOCKET-PORT	10-50
SET SOCKET-TYPE.....	10-51
SET USERNAME	10-52
SET WORKING-SET-EXTENT.....	10-53
SET WORKING-SET-QUOTA	10-54
SHOW	10-55
SHUTDOWN.....	10-56
SPAWN.....	10-57

STATUS 10-59

USE..... 10-60

VERSION..... 10-61

WRITE..... 10-62

Index

Reader’s Comments

Preface

Obtaining Technical Support

Process Software provides technical support if you have a current Maintenance Service Agreement. If you obtained MultiNet from an authorized distributor or partner, you receive your technical support directly from them.

You can contact Technical Support by:

- Sending electronic mail (see the section *Sending Electronic Mail*).
- Calling the Technical Support Specialist (see the section *Calling Technical Support*).
- Faxing a description of your problem to the Technical Support Group (see the section *Contacting Technical Support by Fax*).

Before Contacting Technical Support

Before you call, or send e-mail or a fax, please:

- 1 Verify that your Maintenance Service Agreement is current.
- 2 Read the online Release Notes, available either in BookReader format or in SYSS\$HELP:MULTINET nnn . RELEASE_NOTES (nnn) is the current MultiNet software version installed on your system.
- 3 Have the following information available:
 - Your name
 - Your company name
 - Your e-mail address
 - Your voice and fax telephone numbers
 - Your Maintenance Agreement Number
 - OpenVMS architecture
 - OpenVMS version
 - MultiNet layered products and versions

- 4 Have complete information about your configuration, error messages that appeared, and problem specifics.
- 5 Be prepared to let an engineer connect to your system either with TELNET or by dialing in using a modem. Be prepared to give the engineer access to a privileged account to diagnose your problem.

You can obtain information about your OpenVMS architecture, OpenVMS version, MultiNet version, and layered products with the MULTINET SHOW /LICENSE command. For example:

```
$ MULTINET SHOW /LICENSE
```

```
Process Software MultiNet V4.4, VAXstation 4000-90, OpenVMS VAX V7.1
```

In this example:

- The machine or system architecture is VAX.
- The OpenVMS version is V7.1.
- The MultiNet version is V4.4

You can use the following table as a template to record the relevant information about your system.

Required Information	Your System Information
Your name	
Company name	
Your e-mail address	
Your voice and fax telephone numbers	
System architecture	VAX Alpha
OpenVMS version	
MultiNet version	
MultiNet optional software components:	
- MultiNet NFS Client	Installed? Yes No
- MultiNet NFS Server	Installed? Yes No
- MultiNet Secure/IP Client	Installed? Yes No
- MultiNet Secure/IP Server	Installed? Yes No
- TCP/IP applications	Installed? Yes No
- Online documentation	Installed? Yes No
- MultiNet Programmer’s Kit	Installed? Yes No

Sending Electronic Mail

For many questions, electronic mail is the preferred communications method. Technical support

via electronic mail is available to customers with a current support contract. Send electronic mail to **support@process.com**

At the beginning of your mail message, include the information listed in section *Before Contacting Technical Support*. Continue with the description of your situation and problem specifics. Include all relevant information to help your Technical Support Specialist process and track your electronic support request.

Electronic mail is answered Monday through Thursday from 8:30 a.m. to 7:00 p.m., and on Friday from 8:30 a.m. to 5:00 p.m. United States Eastern Time.

Calling Technical Support

For regular support issues, call 800-394-8700 or 508-628-5074 for support Monday through Thursday from 8:30 a.m. to 7:00 p.m., and on Friday from 8:30 a.m. to 5:00 p.m. United States Eastern Time.

For our customers in North America with *critical* problems, an option for support 7 days per week, 24 hours per day is available at an additional charge. Please contact your account representative for further details.

Before calling, have available the information described in *Before Contacting Technical Support*. When you call, you will be connected to a Technical Support Specialist.

Be prepared to discuss problem specifics with your Technical Support Specialist and to let that person connect to your system.

If a Specialist is not immediately available, your call will be returned as soon as possible.

Contacting Technical Support by Fax

You can send fax transmissions directly to Technical Support at 508-879-0042.

Before faxing comments or questions, complete the steps in *Before Contacting Technical Support* and include all your system information at the beginning of your fax message. Continue with the description of your situation and problem specifics. Include all relevant information to help your Technical Support Specialist process and track your fax support request.

Faxed questions are answered Monday through Thursday from 8:30 a.m. to 7:00 p.m., and on Friday from 8:30 a.m. to 5:00 p.m. United States Eastern Time.

Obtaining Online Help

Extensive information about MultiNet is provided in the MultiNet help library. For more information, use the following command:

```
$ HELP MULTINET
```

MultiNet Frequently Asked Questions List

You can obtain an updated list of frequently asked questions (FAQs) and answers about MultiNet products from the Process Software home page located at <http://www.support.process.com/multinet.html>.

Accessing the MultiNet Public Mailing List

Process Software maintains two public mailing lists for MultiNet customers:

- **Info-MultiNet@process.com**
- **MultiNet-Announce@process.com**

The **Info-MultiNet@process.com** mailing list is a forum for discussion among MultiNet system managers and programmers. Questions and problems regarding MultiNet can be posted for a response by any of the subscribers. To subscribe to Info-MultiNet, send a mail message with the word “SUBSCRIBE” in the body to Info-MultiNet-request@process.com. The information exchanged over Info-MultiNet is also available via the USENET newsgroup vmsnet.networks.tcp-ip.multinet.

You can retrieve the Info-MultiNet archives by anonymous FTP to [ftp.multinet.process.com](ftp://ftp.multinet.process.com). The archives are located in the directory [INFO-MULTINET].

You can also find the Info-MultiNet archives on the MultiNet consolidated CD-ROM in the [CONTRIBUTED-SOFTWARE.LIST-ARCHIVES.INFO-MULTINET] directory.

The **MultiNet-Announce@process.com** mailing list is a one-way communication (from Process Software to you) used for the posting of announcements relating to MultiNet (patch releases, product releases, etc.). To subscribe to MultiNet-Announce, send a mail message with the word “SUBSCRIBE” in the body to MultiNet-Announce-request@process.com.

Process Software World Wide Web Server

Electronic support is provided through the Process Software World Wide Web server, which you can access with any World Wide Web browser; the URL is <http://www.process.com> (select **Customer Support**).

Obtaining Software Patches Over the Internet

Process Software provides software patches in save set and ZIP format on its anonymous FTP server, [ftp.multinet.process.com](ftp://ftp.multinet.process.com). For the location of software patches, read the .WELCOME file in the top-level anonymous directory. This file refers you to the directories containing software patches.

To retrieve a software patch, enter the following commands (note that the first command is shown on two lines using the continuation character):

```
$ MULTINET FTP /USERNAME-ANONYMOUS /PASSWORD="emailaddress"
FTP.MULTINET.PROCESS.COM
```

A message welcoming you to the Process Software FTP directory appears next followed by the FTP prompt. Enter the following at the prompts:

```
FTP.MULTINET.PROCESS.COM>CD [CUSTOMER_SUPPORT.SOFTWARE_UPDATES_VMS.Vnn]
FTP.MULTINET.PROCESS.COM>GET update_filename
```

- *emailaddress* is your e-mail address in the standard *user@host* format.
- *nn* is the version of MultiNet you want to transfer.
- *update_filename* is the name of the file you want to transfer.

To transfer files from Process Software directly to an OpenVMS system, you can use the GET command without any other FTP commands. However, if you need to transfer a software patch through an intermediate non-OpenVMS system, use BINARY mode to transfer the files to and from that system.

In addition, if you are fetching the software patch in save set format, make sure the *save set record* size is 2048 bytes when you transfer the file from the intermediate system to your OpenVMS system:

- If you use the GET command to download the file from the intermediate system, use the FTP **RECORD-SIZE 2048** command *before* transferring the file.
- If you use the PUT command to upload the file to your OpenVMS system, log into the intermediate system and use the FTP **quote site rms resize 2048** command *before* transferring the file.

Process Software also supplies UNZIP utilities for OpenVMS VAX and Alpha for decompressing ZIP archives in the [THIRD_PARTY_TOOLS.VMS] directory. To use ZIP format kits, you need a copy of the UNZIP utility.

The following example shows how to use the UNZIP utility, assuming you have copied the appropriate version of UNZIP.EXE to your current default directory.

```
$ UNZIP := $SYS$DISK:[ ]UNZIP.EXE
$ UNZIP filename.ZIP
```

Use VMSINSTALL to upgrade your MultiNet system with the software patch.

RFCs (Requests for Comment)

The Defense Data Network (DDN) Network Information Center (NIC) has collected extensive online archives of information useful to TCP/IP network designers and managers. Of particular interest are the Internet RFCs (Requests For Comments) that detail (among other things) the protocol standards for the TCP/IP protocol suite.

The MultiNet consolidated distribution CD-ROM contains copies of the Internet RFCs in MULTINET:[CONTRIBUTED-SOFTWARE.RFC].

For a list of supported RFCs and information on obtaining them if your MultiNet distribution is on tape, invoke the following command:

```
$ HELP MULTINET RFC_INFO
```

Typographical Conventions

Examples in this guide use the following conventions:

Convention	Example	Meaning
Bold text	YES	Represents user input in instructions or examples.
Bold, uppercase Courier text	RETURN	Represents a key on your keyboard.
Bold Courier text with a slash	Ctrl/A	Indicates that you hold down the key labeled Control or Ctrl while simultaneously pressing another key; in this example, the "A" key.
A vertical bar within braces	{ ON OFF }	Indicates a list of values permitted in commands. The vertical bar separates alternatives; do not type the vertical bar in the actual command.
Italicized text	<i>file_name</i>	Represents a variable or placeholder; introduces new terminology or concepts; emphasizes something important; represents the title of a book or publication.
Square brackets	[FULL]	Indicates optional choices; you can enter none of the choices, or as many as you like. When shown as part of an example, square brackets are actual characters you should type.
Underscore or hyphen	<i>file_name</i> or <i>file-name</i>	Between words in commands, indicates the item is a single element.

Chapter 1

MultiNet DCL Command Reference

This chapter describes the MultiNet administration commands you can run from the DCL prompt.

Command Summary

Table 1-1 describes the MultiNet administrative commands available at the DCL prompt.

Table 1-1 MultiNet Command Summary

Command	Description
MULTINET ACCOUNTING	Processes the accounting file that FTP and SMTP can write.
MULTINET CHECK	Tests the MultiNet configuration.
MULTINET CONFIGURE /DECNET	Invokes the DECnet Circuit Configuration Utility (DECNET-CONFIG).
MULTINET CONFIGURE /MAIL	Invokes the Electronic Mail Configuration Utility (MAIL-CONFIG).
MULTINET CONFIGURE /MENU	Invokes the Menu-driven Configuration Utility (MENU-CONFIG).
MULTINET CONFIGURE /NETWORK	Invokes the Network Interface Configuration Utility (NET-CONFIG).
MULTINET CONFIGURE /PRINTERS	Invokes the Printer Configuration Utility (PRINTER-CONFIG).
MULTINET CONFIGURE /SERVERS	Invokes the Server Configuration Utility (SERVER-CONFIG).

Table 1-1 MultiNet Command Summary (Continued)

Command	Description
MULTINET CONFIGURE /SERVER_IMAGE	Specifies the master server image associated with the server configuration file.
MULTINET CONFIGURE /NOBOLD	Prevents MENU-CONFIG from downloading fonts to your terminal (when used with /MENU).
MULTINET CONFIGURE /CONFIGURATION_FILE	Specifies the configuration file read by the DECNET-, PRINTER-, or SERVER-CONFIG utility.
MULTINET DIG	Tests the domain name service (DNS) system.
MULTINET DNSKEYGEN	Generates and maintains keys for DNS Security (DNSSEC) within the DNS.
MULTINET DNSSIGNER	Signs zone files for DNS Security (DNSSEC) within the DNS (Domain Name System).
MULTINET FONT COMPILE	Compiles an ASCII BDF (bitmap distribution format) font file into a binary PCF (portable compiled format) file.
MULTINET FONT INFO	Displays font server information.
MULTINET FONT LIST	Lists font names and font information.
MULTINET FONT MKFONTDIR	Creates a DECW\$FONT_DIRECTORY.DAT file when adding fonts.
MULTINET FONT SHOW	Displays font data.
MULTINET FONT UNCOMPILE	Uncompiles a PCF file into an ASCII BDF file.
MULTINET HOST_TABLE COMPILE	Compiles a host table.
MULTINET HOST_TABLE GET	Retrieves a HOSTS.TXT file.
MULTINET HOST_TABLE INSTALL	Installs host tables as global sections.
MULTINET IPP SHOW	Allows a user to learn the capabilities supported by an IPP server.
MULTINET KERBEROS DATABASE DUMP	Stores the contents of the Kerberos database in an ASCII text file.
MULTINET KERBEROS DATABASE EDIT	Adds principal information to the database.

Table 1-1 MultiNet Command Summary (Continued)

Command	Description
MULTINET KERBEROS DATABASE INITIALIZE	Initializes the Kerberos database.
MULTINET KERBEROS DATABASE LOAD	Loads the database from an ASCII text file produced by the MULTINET KERBEROS DATABASE DUMP utility.
MULTINET KERBEROS DATABASE NEW_MASTER_KEY	Permits the Kerberos master key to be changed.
MULTINET KERBEROS DATABASE SRVTAB	Creates an encrypted server key file for a remote system.
MULTINET KERBEROS DATABASE STASH	Saves the Kerberos master key in a protected file for the KDC.
MULTINET LOAD	Loads and invokes the network image.
MULTINET NETCONTROL	Sends commands to MULTINET_SERVER internal services.
MULTINET NFSDISMOUNT	Dismounts a locally-mounted remote NFS file system.
MULTINET NFSMOUNT	Mounts a remote NFS file system so it can be used locally.
MULTINET NSLOOKUP	Sends a test query to DNS.
MULTINET NSUPDATE	Performs dynamic updates to the domain name service (DNS) server.
MULTINET PING	Tests connections by sending ICMP echo requests.
MULTINET RDATE	Queries the remote system for time and sets the local clock accordingly.
MULTINET RMTALLOC	Allocates a remote tape drive or CD-ROM for access by a single process.
MULTINET RWALL	Sends a message to all system users.
MULTINET SET /ARP	Changes ARP tables.
MULTINET SET /DECNET	Configures DECnet devices to run DECnet-over-UDP circuits.
MULTINET SET /INTERFACE	Sets parameters for network devices

Table 1-1 MultiNet Command Summary (Continued)

Command	Description
MULTINET SET /ROUTE	Specifies static IP routing.
MULTINET SET /TIMEZONE	Specifies the local timezone name.
MULTINET SHOW /ALL	Displays information provided by all other MULTINET SHOW qualifiers.
MULTINET SHOW /ARP	Displays Address Resolution Protocol (ARP) tables.
MULTINET SHOW /BUFFERS	Displays kernel memory usage statistics.
MULTINET SHOW /CONFIGURATION	Displays network interface configuration information.
MULTINET SHOW /CONTINUOUS	Continuously updates the display with information about the network using the VMS Screen Management Graphics (SMG) library routines.
MULTINET SHOW /FULL	Displays more information about a queue; used only with /QUEUE.
MULTINET SHOW /HOSTS	Displays the MultiNet kernel IMP tables; used only with hosts connected to ARPANET/MILNET PSNs.
MULTINET SHOW /INTERFACE	Displays information about a specific interface.
MULTINET SHOW /IP	Shows network connections; same as /CONNECTION.
MULTINET SHOW /LICENSE	Displays the status of MultiNet software product licenses.
MULTINET SHOW /NFSMOUNT	Indicates which hosts are mounted on your host, and what mount points are exported by the server.
MULTINET SHOW /OUTPUT	Specifies a file into which the output of the command is written.
MULTINET SHOW /PROTOCOLS	Specifies the protocols about which information is displayed.
MULTINET SHOW /QUEUE	Displays the contents of the specified local VMS queue and the corresponding remote LPD protocol queues.

Table 1-1 MultiNet Command Summary (Continued)

Command	Description
MULTINET SHOW /REMOTE	Displays network status and configuration information about a remote host using the NETSTAT service.
MULTINET SHOW /ROUTE	Displays routing information for the IP, NS, and SPX protocols.
MULTINET SHOW /RPC_PORTMAP	Displays the currently-registered RPC protocols.
MULTINET SHOW /STATISTICS	Displays network interface or protocol or both.
MULTINET SHOW /SYMBOLIC_ADDRESSES	Determines how certain fields in output should be formatted before being displayed.
MULTINET SHOW /TCP	Shows network connections; same as /CONNECTION.
MULTINET SHOW /VERSION	Displays the MultiNet and OpenVMS operating system versions.
MULTINET SHOW /WIDTH	Specifies the width of displayed output when used with the /ARP, /CONNECTION, /ROUTE qualifiers.
MULTINET TCPDUMP	Decodes network packets selected by a boolean expression.
MULTINET TCPVIEW	Traces packets and interprets the results.
MULTINET TRACEROUTE	Determines the route to the specified host.
MULTINET X11DEBUG	Performs tests on the most common causes of problems when running X11 clients over MultiNet.

MULTINET ACCOUNTING

Processes the accounting file that session accounting writes for SMTP and for FTP. It extracts the selected records from it and either displays it on the user's terminal or sends it to the specified output file.

FORMAT

```
$ MULTINET ACCOUNTING /INPUT=filename /SINCE=first_date_to_include
```

QUALIFIERS

/INPUT=accounting_file_name

/OUTPUT=output_file_name

/BEFORE=latest_date_to_include

/SINCE=first_date_to_include

/PROTOCOL=(MAIL,SMTP,FTP)

These are the protocols to include.

/CSV

Makes the output file a Comma Separated Values file that can be imported into an Excel-type document for processing.

MULTINET CHECK

Invokes the MultiNet configuration test utility to perform one or more checks for common MultiNet configuration problems. Requires CMKRNL, SYSPRV, and WORLD privileges.

FORMAT

MULTINET CHECK [*test,...*]

PARAMETER

test

Specifies the name of a test to be performed. Valid test names are ARP, BROADCASTS, DATABASES, HOST_NAME, HOST_TABLE, INTERFACES, LICENSE, MISCELLANEOUS, PARAMETERS, PROTOCOL_ERRORS, ROOT_NAMESERVERS, ROUTES, and VERSION. You can specify multiple tests by separating the names with commas. If you do not specify a test parameter, all tests are performed.

The host name check verifies that the address associated with the local host name matches one of the interface addresses.

QUALIFIERS

/IGNORE_ERRORS

/NOIGNORE_ERRORS (default)

MULTINET CHECK usually stops when it encounters an error. Specify this qualifier to force MULTINET CHECK to continue testing even after an error is encountered.

/OUTPUT=file-spec

/NOOUTPUT

MULTINET CHECK usually displays all output on the standard error output device. Specify this qualifier to either redirect output to the specified file or turn output off altogether.

/VERBOSE

/NOVERBOSE (default)

Causes MULTINET CHECK to display more information about the tests it performs. By default, it only displays a message when it encounters an error or if all tests pass.

MULTINET CONFIGURE

Invokes one of the MultiNet configuration utilities which are interactive programs that maintain network configuration information. If you do not specify a configuration utility with a qualifier, the network interface configuration utility (NET-CONFIG) is invoked.

FORMAT

MULTINET CONFIGURE [*/qualifier(s)*]

QUALIFIERS

/ACCESS

Invokes the Access Configuration Utility (ACCESS-CONFIG) that lets you examine, modify, and save MultiNet Secure/IP configuration files. MultiNet Secure/IP is a TCP/IP-based authentication system that extends the OpenVMS login facility to support authentication "tokens."

The MultiNet Secure/IP Client becomes part of logging in via TELNET, FTP, LAT, DECnet, and "hardwired" devices (for example, TX and TT).

The MultiNet Secure/IP Server provides authentication information to MultiNet Secure/IP clients when users try to log in.

/DECNET

Invokes the DECnet Configuration Utility (DECNET-CONFIG) that lets you view and alter the configuration of DECnet-over-IP services. If used with the /CONFIGURATION_FILE qualifier, DECNET-CONFIG reads the specified configuration file (by default, MULTINET:DECNET-CIRCUITS.COM).

/INTERFACES

Invokes the Network Interface Configuration Utility (NET-CONFIG) that lets you view and alter the configuration of network interfaces, routing, and host name lookup. If used with the /CONFIGURATION_FILE qualifier, NET-CONFIG reads the specified configuration file (by default, MULTINET:NETWORK_DEVICES.CONFIGURATION).

/MAIL

Invokes the Electronic Mail Configuration Utility (MAIL-CONFIG) that lets you view and alter SMTP configuration. If used with the /CONFIGURATION_FILE qualifier, MAIL-CONFIG reads the specified configuration file (by default, MULTINET_COMMON_ROOT:[MULTINET]START_SMTP.COM).

/MENU

Invokes the MultiNet Menu-driven Configuration Utility (MENU-CONFIG) that lets you configure network interfaces, global parameters, services, electronic mail, printing, DECnet-over-IP circuits, and, if installed, NFS and MultiWare.

Context-sensitive online help describes each configuration parameter and how to navigate the configuration menus.

MENU-CONFIG provides access modes for beginning and advanced users. Press PF1 to toggle between modes.

By default, MENU-CONFIG downloads fonts to your terminal; to prevent it from doing so (for example, when operating it over serial connections), use the /NOBOLD qualifier.

/NETWARE

Invokes the MultiWare Server Configuration Utility (NETWARE-CONFIG) for the MultiWare Server option. Synonymous with the /NW qualifier.

If used with the /CONFIGURATION_FILE qualifier, NETWARE-CONFIG reads the specified configuration file (by default, MULTINET:MULTIWARE.CONFIGURATION).

If used with the /PRINTER_CONFIGURATION_FILE qualifier, NETWARE-CONFIG reads the specified configuration file (by default, MULTINET:NETWARE-PRINTING.COM).

/NETWORK

Invokes the Network Interface Configuration Utility (NET-CONFIG) that lets you view and alter the configuration of network interfaces, routing, and host name lookup. If used with the /CONFIGURATION_FILE qualifier, NET-CONFIG reads the specified configuration file (by default, MULTINET:NETWORK_DEVICES.CONFIGURATION).

MULTINET CONFIGURE /NETWORK now has the command:

SET SNMP-AGENTX TRUE to enable SNMP Agent X service.

SET SNMP-AGENTX FALSE to disable SNMP Agent X service.

A line displays in the output of the SHOW command if SNMP Agent X subagents are enabled.

/NFS

Invokes the MultiWare NFS Server Configuration Utility (NFS-CONFIG) for the MultiWare NFS Server option.

If used with the /CONFIGURATION_FILE qualifier, NFS-CONFIG reads the specified configuration file (by default, MULTINET:NFS.CONFIGURATION).

/NOT

Invokes the NOT Configuration Utility NOT-CONFIG for DECnet applications services (formerly known as Phase/IP). DECnet application services allow you to run applications designed to use DECnet using TCP/IP instead. DECnet application services provide the DECnet API (Application Programming Interface) across TCP seamlessly, without DECnet protocols or software, and without the additional overhead of running both protocol stacks.

/PRINTERS

Invokes the MultiNet Printer Configuration Utility (PRINTER-CONFIG) that lets you view and alter the configuration of MultiNet-based print services. If used with the /CONFIGURATION_FILE qualifier, PRINTER-CONFIG reads the specified configuration file (by default, MULTINET:REMOTE-PRINTER-QUEUES.COM).

/SERVERS

Invokes the MultiNet Service Configuration Utility (SERVER-CONFIG) that lets you view and alter the configuration of MultiNet services. If used with the /CONFIGURATION_FILE qualifier, SERVER-CONFIG reads the specified configuration file (by default, MULTINET:SERVICES.MASTER_SERVER).

/SERVER_IMAGE=server_image_file

Used with the /SERVERS qualifier, server_image_file specifies the MultiNet master server image associated with the server configuration file. This file is used by SERVER-CONFIG to determine which network services are available. If not specified, SERVER-CONFIG uses MULTINET:SERVER.EXE.

/NOBOLD

Used with the /MENU qualifier to prevent MENU-CONFIG from downloading fonts to your terminal. Use /NOBOLD if your terminal does not support boldface characters (for example, early VT terminal emulators), or if you are working over a serial connection and you do not want to wait for fonts to download.

/CONFIGURATION_FILE=config_file

Used with the /DECNET, /PRINTERS, or /SERVERS qualifier, specifies the configuration file read by the corresponding utility.

MULTINET DIG

Similar to NSLOOKUP, DIG tests the domain name service (DNS) system. It uses the DNS resolver to send queries to the DNS server and prints out the response. DIG executes a single command or reads commands from a file (in "batch mode").

DIG can be used with the UNIX-style syntax by defining it as a foreign command:

```
$ DIG ::= $MULTINET:DIG.EXE
```

Both the UNIX-style options and the OpenVMS qualifiers are listed below.

FORMAT

```
MULTINET DIG [name [type [class]]]
```

PARAMETERS

name

Specifies a host or domain name.

Note! You must specify fully-qualified names. DIG will not append any domain names.

type

Specifies which TYPE resource records are asked for. The default is A (address records). Valid values are the same as for the NSLOOKUP /TYPE qualifier (see Table 1-37).

class

Specifies which CLASS resource records are asked for. The default is IN (internet records). Valid values are ANY, IN, CHAOS, and HESIOD.

QUALIFIERS

+*[no]*addit

/ADDITIONAL (default)

/NOADDITIONAL

Tells the resolver to print the additional section of the reply.

-x *ip-address*

/ADDRESS=*ip-address*

Convenient form to specify an inverse address mapping query. For example, MULTINET DIG/ADDRESS=10.5.64.1 is equivalent to MULTINET DIG 1.64.5.10.IN-ADDR.ARPA ANY.

+*[no]*answer

/ANSWER (default)

/NOANSWER

Tells the resolver to print the answer section of the reply.

+*[no]*author
/AUTHORITY (default)
/NOAUTHORITY

Tells the resolver to print the authority section of the reply.

-c *recordclass*
/CLASS=*recordclass*

Specifies which CLASS resource records are asked for. Alternative to specifying the class parameter. The *recordclass* value may be either the integer value of the class or the name of the class (ANY, IN, CHAOS, HESIOD). The default is IN (internet records).

+*[no]*cmd
/CMD (default)
/NOCMD

Tells DIG to echo parsed arguments from the command.

+*[no]*debug
/DEBUG
/NODEBUG (default)

Causes the resolver to print debugging information.

+*[no]*d2
/DEBUG2
/NODEBUG2 (default)

Causes the resolver to print additional, less useful debugging information.

-envsav
/ENVSARE

Specifies that the DIG environment (defaults, print options, etc.), after all of the arguments are parsed, should be saved to a file to become the default environment. This is useful if you do not like the standard set of defaults and do not desire to include a large number of options each time DIG is used. The environment consists of resolver state variable flags, timeout, and retries as well as the flags detailing DIG output. If the logical name LOCALDEF is set to the name of a file, this is where the default DIG environment is saved. If not, the file DIG.ENV is created in the current default directory.

Each time DIG is executed, it looks for DIG.ENV or the file specified by LOCALDEF. If such a file exists, then the environment is restored from this file before any arguments are parsed.

-envset
/ENVSET

This qualifier only affects batch query runs. When -envset is specified on a line in a DIG batch file, the DIG environment after the arguments are parsed becomes the default environment for the duration of the batch file, or until the next line which specifies -envset. Remember that commands in the DIG batch file must be in UNIX-style syntax.

-f *filename*

/FILE=*filename*

Causes DIG to run in batch mode, executing the commands in the specified file. The commands in this file must be in the UNIX-style syntax.

"+[no]Header"

/HEADER (default)

/NOHEADER

Tells the resolver to print basic header information.

+ [no]header

/HFLAGS (default)

/NOHFLAGS

Tells the resolver to print header flags.

+ [no]ignore

/IGNORE

/NOIGNORE (default)

Tells the resolver to ignore truncation in responses.

+ [no]ko

/KEEPOPEN

/NOKEEPOPEN (default)

If using virtual circuits (TCP), keeps the connection open.

-k *keydir+keyname*

/KEY=(KEYNAME=*key* [,KEYDIR=*directory*])

Specifies a TSIG key for DIG to use to sign its queries. The default value for KEYDIR is the current default directory.

Note! On UNIX systems, the syntax is *keydir:keyname*. On OpenVMS, the colon is replaced by a plus sign (+). The *keyname* must be specified to match the key and private filenames, with periods instead of dollar signs. This may not match the domainname if DNSKEYGEN had to abbreviate it to fit into an OpenVMS file name.

+pfand=*number*

/PFAND=*number*

Causes DIG to do a bitwise-AND of the print flags with the specified value.

+pfdef

/PFDEF (default)

/NOPFDEF

Sets the print flags to the default.

+pfmin
/PFMIN
/NOPFMIN (default)

Sets the print flags to the minimum.

+pfor=*number*
/PFOR=*number*

Causes DIG to do a bitwise-OR of the print flags with the specified value.

+pfset=*number*
/PFSET=*number*

Sets the print flags to the specified value.

"-P" *ping-command*
/PING[=*ping-command*]

Causes DIG to execute a ping command to the queried nameserver after the query returns, for response time comparison. If the optional *ping-command* is present, it is used as the ping command. The default ping command is "MULTINET PING".

-p *port*
/PORT=*port*

Specifies a port other than the standard nameserver port of 53.

+*[no]*qr
/QUERY
/NOQUERY (default)

Tells the resolver to print the outgoing query.

+*[no]*ques
/QUESTION (default)
/NOQUESTION

Tells the resolver to print the question section of the reply.

+*[no]*recurse
/RECURSE (default)
/NORECURSE

Requests that the name server use recursion to answer the query.

+*[no]*reply
/REPLY (default)
/NOREPLY

Tells the resolver to print the reply.

+retry=*retrycount*
/RETRY=*retrycount*

Specifies the number of retries the resolver makes when querying a name server via UDP. The

default is 4.

@*server*

/SERVER=*server*

Specifies the nameserver to query. May be specified as either a domain name or a dot-notation internet address. If a domain name is specified, DIG looks up the name using the default nameserver. If /SERVER is not specified, the default is to use the system's default nameserver.

+*[no]*stats

/STATS (default)

/NOSTATS

Tells the resolver to print query statistics.

-*[no]*stick

/STICKY

/NOSTICKY (default)

This qualifier only affects batch query runs. -stick specifies that the DIG environment (as read initially or set by -envset switch) is to be restored before each query (line) in a DIG batch file. The default -nostick means that the DIG environment does not stick, hence options specified on a single line in a DIG batch file will remain in effect for subsequent lines (i.e. they are not restored to the "sticky" default). Remember that commands in the DIG batch file must be in UNIX-style syntax.

+time=*seconds*

/TIMEOUT=*seconds*

Specifies a different period to wait for responses. The default is 4 seconds.

"-T" *seconds*

/TIMEWAIT=*seconds*

Causes DIG to wait the specified number of seconds between the start of successive queries when running in batch mode. Can be used to keep two or more batch DIG commands running roughly in sync. The default is 0.

-t *recordtype*

/TYPE=*recordtype*

Specifies which TYPE resource records are asked for. Alternative to specifying the type parameter. The *recordtype* value may be either the integer value of the type or the name of the type (see Table 1-37). The default is A (address records).

+*[no]*vc

/VC

/NOVC (default)

Specifies that the resolver use virtual circuits (TCP) instead of datagram (UDP) queries.

Example

The following is an example of the default DIG output:

```
$ multinet dig www.peh.com

; <<>> DiG 8.3 <<>> WWW.PEH.COM
;; res options: init recurs defnam dnsrch
;; got answer:
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 4
;; flags: qr aa rd ra; QUERY: 1, ANSWER: 2, AUTHORITY: 2, ADDITIONAL: 2
;; QUERY SECTION:
;;      WWW.PEH.COM, type = A, class = IN

;; ANSWER SECTION:
WWW.PEH.COM.          2H IN CNAME    peh.com.
peh.com.              2H IN A        209.196.131.83

;; AUTHORITY SECTION:
peh.com.              2H IN NS        ns1.pbi.net.
peh.com.              2H IN NS        ns2.pbi.net.

;; ADDITIONAL SECTION:
ns1.pbi.net.          2D IN A        206.13.28.11
ns2.pbi.net.          2D IN A        206.13.29.11

;; Total query time: 14289 msec
;; FROM: bite.process.com to SERVER: default -- 127.0.0.1
;; WHEN: Thu Jun  1 14:52:49 2002
;; MSG SIZE  sent: 29  rcvd: 141
```


MULTINET DNSKEYGEN

DNSKEYGEN (DNS Key Generator) is a tool to generate and maintain keys for DNS Security (DNSSEC) within the DNS (Domain Name System). DNSKEYGEN can generate public and private keys to authenticate zone data, and shared secret keys to be used for Request/Transaction Signatures.

DNSKEYGEN can be used with the UNIX-style syntax by defining it as a foreign command:

```
$ DNSKEYGEN ::= $MULTINET:DNSKEYGEN.EXE
```

Both the UNIX-style options and the OpenVMS qualifiers are listed below.

DNSKEYGEN stores each key in two files: *Kname.alg-footprint-private* and *Kname.alg-footprint-key*. *name* is the domainname with the periods replaced by dollar signs. The first file contains the private key in a portable format. The second file contains the public key in the DNS zone file format:

name IN KEY *flags protocol algorithm exponent/module*

If the domain name is too long for an OpenVMS filename, it is truncated to fit and the last six characters are replaced by unique digits. The full domain name can be found inside the key file.

FORMAT

MULTINET DNSKEYGEN *name*

PARAMETERS

-n *name*
name

Specifies the domain name to generate the key for.

QUALIFIERS

"-D" *size*
/DSA_DSS=*size*

"-H" *size*
/HMAC_MD5=*size*

"-R" *size*
/RSA=*size*

These flags specify the type of key to generate. **You must specify one and only one of these.**

If /DSA_DSS is specified, DNSKEYGEN generates a DSA/DSS key. *size* must be one of: 512, 576, 640, 704, 768, 832, 896, 960, or 1024.

If /HMAC_MD5 is specified, DNSKEYGEN generates an HMAC-MD5 key. *size* must be between 128 and 504.

If /RSA is specified, DNSKEYGEN generates an RSA key. *size* must be between 512 and 4096.

"-F"

/LARGE_EXPONENT

Used for RSA only. If specified, DNSKEYGEN uses a large exponent for key generation.

-z

/ZONE_KEY

-h

/HOST_KEY

-u

/USER_KEY

These flags define the type of key being generated. **You must specify one and only one of these.**

- Zone (DNS validation) key
- Host (host or service) key
- User (e.g., email) key

-a

/NOAUTHENTICATION

Indicates that the key CANNOT be used for authentication.

-c

/NOENCRYPTION

Indicates that the key CANNOT be used for encryption.

-p *num*

/PROTOCOL=*num*

Sets the key's protocol field to *num*. If /ZONE_KEY (-z) or /HOST_KEY (-h) is specified, the default is 3 (DNSSEC); otherwise, the default is 2 (EMAIL). Other accepted values are 1 (TLS), 4 (IPSEC), and 255 (ANY).

-s *num*

/STRENGTH=*num*

Sets the key's strength field to *num*; the default is 0.

EXAMPLE

The following example generates an RSA key.

```
$ MULTINET DNSKEYGEN/RSA=512/ZONE_KEY zone.example
** Adding dot to the name to make it fully qualified domain name**
Generating 512 bit RSA Key for ZONE.EXAMPLE.
```

```
Generated 512 bit Key for ZONE.EXAMPLE. id=49663 alg=1 flags=257
```

DNSKEYGEN generates the following (for example):

File KZONE\$EXAMPLE\$.001-49663-KEY:

```
ZONE.EXAMPLE. IN KEY 257 3 1 AQOojr8lq9PfmQXCUAJOoMu3CYaS78RZnhiV/  
uAfSbzZusWYLSeVF47OwZlmgwclswZoam5NSuzFX3w5RDIEwf9c
```

File KZONE\$EXAMPLE\$.001-49663-PRIVATE:

```
Private-key-format: v1.2  
Algorithm: 1 (RSA)  
Modulus: qI6/NbPT35kGwlACTqDLtwmGku/  
EWZ4Ylf7gH0m82arFmC0nlReOjsGJZoMHJbMGaGjOTUrsxV98OUQyAMH/Ww==  
PublicExponent: Aw==  
PrivateExponent: cF8qI8036mZD1uABjcCHz1uvDJ/  
YO767Dmqqv4Z95ntuhY7uIMmn8zy0Ur9kj/7P5Dvpu7ZG91ZtuQ1YhWAMyw==  
Prime1: 2IQQP2+DvU/G00380Coji00NDQHA0az8lDV1fh8Qf9k=  
Prime2: x0vGgXRlWVIfp5xnuCORP0UB4rK3sKVhQ246rx2hbFM=  
Exponent1: kFgKlPQCfjUvN4lS0BwXtN6Is1aBNnNTDXj4/r9gVTs=  
Exponent2: hN0vABhDjja/xRLv0Be2Kl4BQcv6dcOWLPQnH2kWSDc=  
Coefficient: YQGEh81Y720mRfAV/tEs3eWKd1lMm10b5R4lFjVwtAU=
```

MULTINET DNSSIGNER

DNSSIGNER is a tool to sign zone files for DNS Security (DNSSEC) within the DNS (Domain Name System). DNSSIGNER’s job is to read the data of one zone of DNS data, and perform the necessary work to produce the data for a secured zone.

DNSSIGNER can be used with the UNIX-style syntax by defining it as a foreign command:

```
$ DNSSIGNER ::= $MULTINET:DNSSIGNER.EXE
```

Both the UNIX-style options and the OpenVMS qualifiers are listed below.

You can get help on the UNIX-style options using:

\$ dnssigner -h	! for short help
\$ dnssigner -help	! for long help

Signing is done on a zone-by-zone basis, regardless of the relationship of zones to name servers. DNSSIGNER is designed to operate in a dynamic environment, including those in which secret keys are not available to all of those covering a zone, and where information may be arriving after the beginning of the signing process. DNSSIGNER makes an effort to retain valid signatures instead of computing new signatures.

Using traditional BIND DNS zone master files, there are two things necessary as input to use DNSSIGNER to sign a zone. One is the names of the input files and the other is the names of the keys to use. There are two kinds of data files used as input to the signing process. The standard zone master file, and a master file introduced by DNSSEC called the parent file. A parent file contains output from the signing of the parent zone, most importantly the signature by the parent of the zone’s keys.

Input/output details

The default input zone is START-ZONE. A different zone input file can be specified with /ZONE=(INPUT=*filename*) (-zi). There is no default input parent file. A parent file can be specified with /PARENT=(INPUT=*filename*) (-pi).

The default output files are FINISH-ZONE. and FINISH-PARENT.
/ZONE=(OUTPUT=*filename*) (-zo) changes the name of the zone output file, and
/PARENT=(OUTPUT=*filename*) (-po) changes the name of the parent file generated by the zone.

Parent file handling

There are two forms of parent file generation. One form is to place all of the parent files in one file (good for zones with many delegations), the other is to make a separate file for each delegation. Since it is easier to erase one file than potentially thousands, DNSSIGNER defaults to the single signer file.

/PARENT=NOBULK (-no-p1) turns single parent file generation off, /PARENT=BULK (-p1) turns it on. As mentioned earlier /PARENT=OUTPUT=*filename* (-po) sets the name of the single parent

file (default FINISH-PARENT.).

/PARENT=INDIVIDUAL (-ps) turns on individual parent files, /PARENT=NOINDIVIDUAL (-no-ps) turns it off. /PARENT=DIRECTORY=*spec* (-pd) sets the directory into which the individual files are put (default is the current working directory).

NXT details

/NONXT (-no-n) turns off RFC 2065 NXT processing.

/NXT (-n) (default) turns on RFC 2065 NXT processing.

Key details

Use the -k1 flag (the /SIG=(KEY=()) qualifier) or the -ks flag (no OpenVMS-style equivalent) to specify a key. -k1 is followed by a domain name owner of a key, the algorithm, and the key id. -ks is followed by a sequence of names, algorithms, and key ids until the end of the command line.

SIG expiration details

There are two time durations that are important to the handling of signatures. One is the duration until a newly generated signature is set to expire. The other is the duration in which existing signatures will be considered to be expired.

/SIG=DURATION=*ttl* (-dur) sets the duration for which a signature is valid.

The time included in the SIG RR expiration field is the current absolute time plus the duration. Wrapping around 32 bits is not a problem, as time is considered to be "circular."

/SIG=PURGE_PERIOD=*ttl* (-pt) sets the period into the future in which SIGs expiring then are considered to have expired. Any signature that has an expiry time in the past of the current time is thrown out, as well as signature whose expiry time falls into the span between now and the purge period duration. The past is considered to be the time from now back to 2 to the 31st seconds ago; the rest is the future.

FORMAT

MULTINET DNSSIGNER

QUALIFIERS

This section describes the syntax of all flags. The meanings can be found in RFC 2065 and the drafts associated with the DNSSEC working group.

-[no-]bind

/[NO]BIND

/BIND (-bind) instructs DNSSIGNER to use BIND's extended TTLs and KEY flags when writing files. This is the default. Use /NOBIND (-no-bind) to turn this feature off. In this case TTLs and flags are written as numeric values.

-l option
/DEBUG=option

Specifies the level of output (debug) messages that DNSSIGNER should print. Specify one of the following levels: (UNIX-syntax equivalents are also shown)

-l 7 -l deb DEBUGGER	Print source code locations, errors, and warnings.
-l 10 -l dev DEVELOPER	Print source code locations and cryptography messages.
-l 1 -l m MINIMAL	Print just errors.
-l 4 -l u USER	Print errors and warnings. This is the default.

-[no-]n
/[NO]NXT

/NXT (-n) (default) instructs DNSSIGNER to generate NXT RRs for the zone, signing them with the keys that sign the SOA record. (If none sign the SOA, no NXT's are signed.). Use /NONXT (-no-n) to turn this feature off.

-or domain
/ORIGIN=domain

This is equivalent to the \$ORIGIN *domain* directive in the zone file, except that the terminating period is not needed in the domain name. Specifying an origin is only mandatory for the root zones and other zones using relative names in the zone files. It is recommended that the \$ORIGIN *domain* directive be put in the data file. By default, this is unspecified.

/PARENT=(keyword[,...])

Specifies options related to parent zone files. Possible keywords (and their UNIX-syntax equivalents) are as follows.

There are two ways in which parent files are made: individual and bulk. The two methods use independent keywords. Both can be used, neither can be used, or just one. By default, the bulk

approach is used.

-[no-]p1 [NO]BULK	BULK (-p1) (default) tells DNSSIGNER to place all of the generated parent data for the zone's delegation points into one file. Separating lines are added to identify the start and end of the information destined for individual zones. Use NOBULK (-no-p1) to turn this feature off.
-pd directory DIRECTORY=directory	Specifies the directory to put individual parent files into. The default is the current default directory.
-[no-]ps [NO]INDIVIDUAL	INDIVIDUAL (-ps) tells DNSSIGNER to place the generated parent data into individual files, named <i>zone.PARENT</i> . For large delegated zones, there will be many files. The default is NOINDIVIDUAL (-no-ps).
-pi file INPUT=file	Specifies the parent file received from the parent zone to be used as input to this zone. If specified, all records that would conflict with it (apex upper NXT, KEYs, and SIGs for these) are dropped. If the UP policy is specified, then the parent's KEY, NS, and glue are also dropped. The default is to have no parent file.
-pa domain NAME=domain	Specifies the apex's parent zone. If the keys for this zone are known and the UP policy is used, the apex zone keys sign the key. If UP is used and this is not specified, then DNSSIGNER acts as if it does not otherwise know the parent's identity. This is equivalent to the \$PARENT directive in the zone file, except that relative domain names are treated as absolute names. By default, the parent's domain name is unspecified.
-po file OUTPUT=file	Specifies the name of the file to hold the bulk generated parent data. The default is FINISH-PARENT.

/POLICY=option

Specifies what policy to use when signing the zone. Specify one of the following options: (UNIX-syntax equivalents are also shown)

-dn DOWN	DNSSIGNER signs according to the DOWN policy. That is, the apex does not sign the parent's keys. The parent's keys and glue data are not expected from nor written to the parent files. This is the default.
-up UP	DNSSIGNER signs according to the UP policy. That is, the apex signs the parent's keys. The parent's keys and glue data are expected from and written to the parent files. Note! This policy is not recommended.

-[no-]ess
/[NO]SELF_SIGN

/SELF_SIGN (-ess) instructs DNSSIGNER to make sure each key in the file is signed by its corresponding private key. This is done by implicitly adding \$SIGNER directives to the zone file around each key set, adding those keys for just the set. If no private key is available, the \$SIGNER directive remains in the output file.

The intent of this feature is to insert proof into DNS that the public key’s corresponding private key is held by the owner (or at least the entity signing the zone).

The default is /NOSELF_SIGN (-no-ess).

/SIG=(keyword[,...])

Specifies options related to the generation of SIG RRs. Possible keywords (and their UNIX-style equivalents) are as follows.

For DURATION and PURGE_PERIOD, *tll* format is taken from the BIND definition of TTL. Numeric seconds is accepted, as well as:

<i>number</i> W	weeks
<i>number</i> D	days
<i>number</i> H	hours
<i>number</i> M	minutes (not months!)
<i>number</i> S	seconds

The "end of the future" and "beginning of the past" are points in time which have the same time representation (one second apart) in a 32-bit roll-over specification of time. The end of the future is 2 to the 31st power seconds from the current time.

-dur <i>tll</i> DURATION=<i>tll</i>	All SIG records generated are set to expire at a the current time + duration. The default is 31 days.
-ks <i>domain algorithm keyid</i> [...] (to end of line)	<p>Note! There is no OpenVMS syntax equivalent.</p> <p>This adds the specified keys (key owner, algorithm, and key id) to the list of keys with which to sign. Equivalent to \$SIGNER ADD <><> directives in the zone file. This switch is interpreted as the last switch of the command line. Any number of keys can be specified.</p> <p>See the description for -k1 for the <i>domain</i> syntax.</p>

-k1 domain algorithm keyid KEY=(DOMAIN=domain, ALGORITHM=algorithm, KEY_ID=keyid)	<p>This adds the specified key (key owner, algorithm, and key id) to the list of keys with which to sign. Equivalent to a \$SIGNER ADD <><> directive in the zone file. This switch may appear anywhere in the run command. It adds just one key.</p> <p>The default is that keys are specified by \$SIGNER directives in the data files. A zone may elect not to use any keys.</p> <p>Note! <i>domain</i> must be specified to match the key and private file names, with periods instead of dollar signs. This may not match the domain name if DNSKEYGEN had to abbreviate it to fit into an OpenVMS file name.</p>
-pt ttl PURGE_PERIOD=ttl	<p>Specifies that all SIG records with expiration times between the beginning of past up through (current time + the purge period) are treated as expired. SIG records with expiration times from (current + purge period) to the end of the future are retained if they are not proved invalid. The default is 1 week.</p>

-[no-]st
/[NO]STATISTICS

/STATISTICS (-st) instructs DNSSIGNER to print summary statistics at the end of the run. The default is /NOSTATISTICS (-no-st).

/ZONE=(keyword[,...])

Specifies options related to zone files. Possible keywords (and their UNIX-syntax equivalents) are as follows:

-zi file INPUT=file	<p>Specifies the zone data input file. The first RR must be an SOA. The first record may be found in an \$INCLUDED file. The default is START-ZONE.</p>
-zo file OUTPUT=file	<p>Specifies the file where signed zone data is left. The default is FINISH-ZONE.</p>

EXAMPLES

1. Assuming that the zone data is in f.zone and the parent file is in f.parent, to run the files through DNSSIGNER, do the following:

```
$ multinet dnssigner /zone=(input=f.zone)/parent=(input=f.parent)
```

or

```
$ dnssigner := $multinet:dnssigner.exe  
$ dnssigner -zi f.zone -pi f.parent
```

The outputs default to FINISH-ZONE. and FINISH-PARENT. This does no signing, but merges the files, removes duplicates, generates NXT resource records, and makes signing instructions for them (if the zone is judged to be signed).

2. To sign the above zone with the key of test. key id 27782:

```
$ multinet dnssigner/zone=(input=f.zone)/parent=(input=f.parent) -  
  /sig=(key=(domain=test.,alg=dsa,key_id=27782)
```

or

```
$ dnssigner -zi f.zone -pi f.parent -k1 test. dsa 27782
```

3. To sign with both keys 27782 and 3696:

```
$ dnssigner -zi f.zone -pi f.parent -ks test. dsa 27782 test. dsa 3696
```

MULTINET FONT COMPILE

Compiles an ASCII BDF (bitmap distribution format) font file into a binary PCF (portable compiled format) file.

FORMAT

MULTINET FONT COMPILE *[qualifiers] [bdf_font_file]*

QUALIFIERS

/BIT_ORDER=bit_order

Specifies the order in which bits in each glyph are placed. Accepted values are MSBFIRST (most significant bit) or LSBFIRST (least significant bit).

The default is LSBFIRST on both the OpenVMS VAX and AXP architectures.

/BYTE_ORDER=byte_order

Specifies the order in which multibyte data in the file is written. Multibyte data includes metrics and bitmaps. Accepted values are MSBFIRST (most significant bit) or LSBFIRST (least significant bit).

The default is LSBFIRST on both the OpenVMS VAX and AXP architectures.

/OUTPUT=file_name

Specifies an output file name in which the results are written.

/PADDING=font_glyph_padding

Sets the font glyph padding. Each glyph in the font has each scanline padding into the specified size. Accepted values are BYTE, WORD, LONGWORD, or QUADWORD. On an OpenVMS VAX system, the default is BYTE; on an AXP, the default is LONGWORD.

/SCANLINE=data_size

Specifies the unit of data swapped when the font bit order differs from the font byte order. Accepted values are BYTE, WORD, and LONGWORD. On an OpenVMS VAX system, the default is BYTE; on an AXP, the default is LONGWORD.

/SERVER=host:port

The /SERVER qualifier specifies the server from which the font is read. The default value is LOCALHOST:7000.

MULTINET FONT INFO

Displays X font information useful for determining the capabilities and defined values of a font server.

FORMAT

MULTINET FONT INFO *[qualifiers]*

QUALIFIERS

/OUTPUT=file_name

Specifies an output file name in which the results are written.

/SERVER=host:port

Specifies the server from which the font is read (by default, LOCALHOST:7000).

MULTINET FONT LIST

Lists the font names that match a specified pattern.

FORMAT

MULTINET FONT LIST *[qualifiers] [pattern]*

PARAMETER

pattern

Specifies the pattern to match in font names. Wildcards are permitted in the patterns. If you do not specify a pattern, an asterisk (*) is assumed.

QUALIFIERS

/BOUNDS

Indicates long listings should display the minimum and maximum bounds of each font.

/COLUMNS

Indicates listings should display in multiple columns.

/LISTING_TYPE=size

Specifies the relative length of a font listing. Accepted values are SMALL, MEDIUM, LONG, and VERYLONG.

Consider using /NOSORT if you want LONG or VERYLONG listings faster; otherwise, these types of listings can take a long time to generate. You can also use /OUTPUT to write the results to a file.

/NOSORT

Indicates the listing is not sorted. Using this qualifier decreases the time required to produce a listing.

/OUTPUT=file_name

Specifies an output file name in which the results are written.

/SERVER=host:port

Specifies the server from which the font is read (by default, LOCALHOST:7000).

/WIDTH=display_column_width

Specifies the width of the columns (by default, 79).

MULTINET FONT MKFONTDIR

Creates a DECW\$FONT_DIRECTORY.DAT file in each specified directory.

MKFONTDIR reads all font files in each specified directory. The order in which font files are read is *.PCF files, *.SNF files, then *.BDF files. For scalable fonts, you must edit the created DECW\$FONT_DIRECTORY.DAT file to insert the X font name. If you edit this file, back up your changes so they are not lost when MKFONTDIR is run again.

The command fails if you don't have the necessary privileges to write into the directory you specify.

FORMAT

MULTINET FONT MKFONTDIR *[directory_names]*

PARAMETER

directory_names

Specifies the list of directories in which MULTINET FONT MKFONTDIR creates a DECW\$FONT_DIRECTORY.DAT file.

MULTINET FONT SHOW

Displays font information from files that match the specified pattern.

FORMAT

MULTINET FONT SHOW [*qualifiers*] [*pattern*]

PARAMETER

pattern

Specifies the pattern to match in font names. Wildcards are permitted in the patterns. If you do not specify a pattern, an asterisk (*) is assumed.

QUALIFIERS

/BITMAP_PADDING=bitmap_size

Specifies how a character bitmap is padded. Accepted values are MINIMUM, MAXIMUM, and MAXWIDTH.

/BIT_ORDER=bit_order

Specifies the order in which bits in each glyph are placed. Accepted values are MSBFIRST (most significant bit) or LSBFIRST (least significant bit). The default is LSBFIRST on both the OpenVMS VAX and AXP architectures.

/BYTE_ORDER=byte_order

Specifies the order in which multibyte data (including metrics and bitmaps) in the file is written. Accepted values are MSBFIRST (most significant bit) or LSBFIRST (least significant bit). The default is LSBFIRST on both the OpenVMS VAX and AXP architectures.

/END=decimal_character_value

Specifies the ending character number (in decimal) about which you want font information listed. Use /END with the /START qualifier to specify character ranges. If you do not specify /END, all characters from the starting value to the end of the character set are listed. Possible values range from 0 to 255 for normal character sets, and from 0 to 65535 for X double-wide character sets.

/EXTENTS

Indicates that only the extents for a font are displayed.

/OUTPUT=file_name

Specifies an output file name in which the results are written.

/PADDING=font_glyph_padding

Sets the font glyph padding. Each glyph in the font has each scanline padding into the specified size. Accepted values are BYTE, WORD, LONGWORD, or QUADWORD. On an OpenVMS VAX system, the default is BYTE; on an AXP, the default is LONGWORD.

/SCANLINE=data_size

Specifies the unit of data swapped when the font bit order differs from the font byte order. Accepted values are BYTE, WORD, and LONGWORD. On an OpenVMS VAX system, the default is BYTE; on an AXP, the default is LONGWORD.

/SERVER=host:port

Specifies the server from which the font is read (by default, LOCALHOST:7000).

/START=decimal_character_value

Specifies the starting character number (in decimal) about which you want font information listed. Use /START with the /END qualifier to specify character ranges. If you do not specify /END, all characters from the starting value to the end of the character set are listed. Possible values range from 0 to 255 for normal character sets, and from 0 to 65535 for X double-wide character sets.

MULTINET FONT UNCOMPILE

Converts a binary PCF-format font file to an ASCII BDF-format file.

FORMAT

MULTINET FONT UNCOMPILE [*qualifiers*] [*pcf_font_file*]

QUALIFIERS

/OUTPUT=*file_name*

Specifies the output file name into which the results are written.

/SERVER=*host:port*

Specifies the server from which the font is read (by default, LOCALHOST:7000).

EXAMPLE

```
$ MULTINET FONT UNCOMPILE -  
_$_ -Adobe-Helvetica-Medium-R-Normal--25-180-100-100-P-130-ISO8859-1
```

MULTINET_HOST_TABLE_COMPILE

The MultiNet host table compiler generates binary host tables from the ASCII host table files. After modifying a MultiNet host table, use this command to compile it into its binary form.

After recompiling your host tables, reinstall the host tables by rebooting, or by invoking the @MULTINET:INSTALL_DATABASES command. Then make the host table usable to the MULTINET_SERVER process servers by restarting this process with the @MULTINET:START_SERVER command. MultiNet uses the compiled host tables for fast lookups of host names, and for translation of host, network, protocol, and service names to numbers.

FORMAT

MULTINET_HOST_TABLE_COMPILE [*files*]

PARAMETER

files

Contains a comma-separated list of one or more input files to be compiled. These files must be in the format described in RFC-952 "DoD Internet Host Table Specification." If not specified, the input files default to MULTINET:HOSTS.SERVICES, MULTINET:HOSTS.LOCAL, and MULTINET:HOSTS.TXT.

QUALIFIERS

/HOST_TABLE_FILE=file

Specifies the file to which the compiler writes the binary host table (by default, MULTINET:NETWORK_DATABASE).

/SILENTLY

/NOSILENTY (default)

Determines whether the compilation proceeds quietly. The default, /NOSILENTLY, can take some time to process.

/STARTING_HASH_VALUE=value

Specifies the initial hash size for the host table hash. Starting at this value, the host table compiler searches for an acceptable hashing function. The default for this qualifier is the "best value," which is computed from the size of the data as the utility attempts to create 512-byte units.

When you run HOST TABLE COMPILE, the hash value is listed in the displayed messages. To select a value for this qualifier, choose a number from the displayed range of values.

/TBLUK_FILE=file

Specifies the file to which the compiler writes the "host-completion" database, used by programs that allow for escape-completion of partially typed host names. The default is MULTINET:HOSTTBLUK.DAT.

/UNIX_HOST_FILE=file

Specifies the file to which the compiler writes a UNIX-style hosts file that can be used on most UNIX systems and with many other vendors' TCP implementations. The default, /NUNIX_HOST_FILE, inhibits the creation of a UNIX-style hosts file.

MULTINET_HOST_TABLE GET

Connects to the HOSTNAME port of NIC.DDN.MIL and uses the HOSTNAME protocol to retrieve the HOSTS.TXT file. After retrieving a new MultiNet host table, compile it into binary form with the MULTINET_HOST_TABLE COMPILE command so the host table can be accessed.

CAUTION! The HOSTS.TXT file located on NIC.DDN.MIL is no longer maintained by the DDN NIC (or anyone else). This file contains out-of-date information and should be used with caution. If your host is connected to the Internet, DNS is a desirable alternative to using host tables.

QUALIFIERS

/HOST=host (default NIC.DDN.MIL)

Specifies a host other than NIC.DDN.MIL. If you specify the host name instead of the address, the host name must exist in your existing host tables.

/OUTPUT_FILE=file

Specifies a different output file (by default, MULTINET:HOSTS.TXT).

/SILENTLY

/NOSILENTLY (default)

Specifies that various debugging information is written to SYS\$ERROR as the program executes.

/QUERY

Specifies an arbitrary HOSTNAME protocol request to the host of interest as follows:

- If the /QUERY qualifier is present, use its value
- Otherwise, if the /VERSION qualifier is present, user "VERSION"
- Otherwise, use "ALL"

/VERSION

Retrieves only the HOSTS.TXT version number.

The HOSTNAME protocol supports simple text query requests of the form:

command_key argument(s) [options]

command_key is a keyword indicating the nature of the request and square brackets ([]) indicate an optional field. The defined keys are described in the following table:

Keyword	Response
HELP	The information in this table.
VERSION	"VERSION: <i>string</i> " where <i>string</i> is different for each version of the host table.
HNAME <i>hostname</i>	One or more matching host table entries.

Keyword	Response
HADDR <i>hostaddr</i>	One or more matching host table entries.
ALL	The entire host table.
ALL-OLD	The entire host table without domain-style names.
DOMAINS	The entire top-level domain table (domains only).
ALL-DOM	Both the entire domain table and the host table.
ALL-INGWAY	All known gateways in TENEX/TOPS-20 INTERNET.GATEWAYS format.

MULTINET HOST_TABLE INSTALL

Installs the binary host tables as global sections. Do not run HOST_TABLE INSTALL directly. Instead, use the MULTINET:INSTALL_DATABASES.COM command procedure.

FORMAT

MULTINET HOST_TABLE INSTALL

MULTINET IPP SHOW

The MULTINET IPP SHOW utility allows a user to learn the capabilities supported by an IPP server. This utility queries the server and displays the supported attributes. The program can be used to see what a given server supports, by a program to gather information about a number of printers, or by a DCL or other program to check the capabilities of a given server before submitting a print job to a queue. The command syntax is:

```
$ MULTINET IPP SHOW server_URI /qualifiers...
```

Qualifiers

/ATTRIBUTE=*attribute*

Puts the program into a mode suitable for use from a DCL command procedure. Not compatible with the /FORMAT or /OUTPUT qualifiers or those associated with them. It causes the program to return the value of a single attribute as a character string in a DCL symbol. This is for a procedure to check to see if, for example, a given server supports color printing before submitting a job to a

queue that requires color output. Allowable values for *attribute* are:

Charset_Configured	Orientation_Requested_Default
Charset_Supported	Orientation_Requested_Supported
Color_Supported	Page_Ranges_Default
Compression_Supported	Page_Ranges_Supported
Copies_Default	PDL_Override_Supported
Copies_Supported	Print_Quality_Default
Document_Format_Default	Print_Quality_Supported
Document_Format_Supported	Printer_Current_Time
Finishings_Default	Printer_Driver_Installer
Finishings_Supported	Printer_Info
Gen_Natural_Language_Supported	Printer_Is_Accepting_Jobs
Job_Hold_Until_Default	Printer_Location
Job_Hold_Until_Supported	Printer_Make_and_Model
Job_Impressions_Supported	Printer_Message_From_Operator
Job_K_Octets_Supported	Printer_More_Info
Job_Media_Sheets_Supported	Printer_More_Info_Manufacturer
Job_Priority_Default	Printer_Name
Job_Priority_Supported	Printer_Resolution_Default
Job_Sheets_Default	Printer_Resolution_Supported
Job_Sheets_Supported	Printer_State
Media_Default	Printer_State_Message
Media_Supported	Printer_State_Reasons
Multiple_Doc_Handling_Default	Printer_Uptime
Multiple_Doc_Handling_Supported	Printer_URI_Supported
Multiple_Operation_Timeout	Queued_Job_Count
Natural_Language_Configured	Reference_URI_Schemes_Supported
Number_Up_Default	Sides_Default
Number_Up_Supported	Sides_Supported
Operations_Supported	URI_Security_Supported

/[NO]APPEND

Specifies that output should be appended to an existing output file if possible. /NOAPPEND is the default.

/FORMAT=*style*

Specifies what print style to use. *style* is either

- "SCREEN" (default) which writes in a human-friendly screen-formatted mode or
- "LIST" which writes an easy to parse, name=value format, one name/value pair per line.

/[NO]FULL

Causes all IPP attributes to be included in the display, whether the server supports them or not. Those not supported are marked as such. /NOFULL is the default.

/[NO]GLOBAL

Specifies whether the named symbol should be created as a DCL global symbol. Used only with /ATTRIBUTE. If specified as "/NOGLOBAL", the symbol will be local to the calling procedure level. /GLOBAL is the default.

/OUTPUT=*file*

Specifies a file to write output to. "SYS\$OUTPUT:" is the default.

/SYMBOL=*symbolname*

Specifies a DCL symbol name that should be set to the value of the specified attribute. Used only with /ATTRIBUTE. The default is "IPP SHOW_RESULT" if /SYMBOL is not specified.

EXAMPLES of MULTINET IPP SHOW Use and Output

1 Basic operation with all defaults:

```
$ MULTINET IPP SHOW LILLIES.FLOWERPOTS.COM
```

```
LILLIES.FLOWERPOTS.COM as of Tue Aug 7 16:08:43 2001
```

CURRENT INFO:

```
Printer State:      Idle
State Reasons:      none
Accepting Jobs?:    Yes
Queued Job Count:   0
```

PRINTER INFO:

```
Name:              Lexmark Optra T610
Make & Model:       Lexmark Optra T610
```

DEFAULTS:

```
Document Format:    application/octet-stream
Orientation:        Portrait
Number-Up:          1
Copies:             1
Job Media Sheets:   none
Character Set:       utf-8
Natural Language:   en-us
```

SUPPORTED FEATURES AND ALLOWED VALUES:

```
Color?:            No
Orientation:        Portrait, Landscape
Document Formats:   application/octet-stream, application/postscript,
                    application/vnd.hp-PCL, text/plain
Job Sheets:         none, standard
Number-Up:          1:16
Copies:             1:999
```

```
PDL Override:      not-attempted
Character Sets:    utf-8, us-ascii
Natural Languages: en-us
Operations:       Print_Job, Validate-Job, Cancel-Job,
                  Get-Job_Attributes, Get-Jobs,
                  Get-Printer_Attributes, Unknown: 18
```

URIs Supported and associated security options:

```
URI:      http://192.168.50.2/
Security: none
```

```
URI:      http://192.168.50.2:631/
Security: none
```

2 Operation with /FULL and output to a file (note that the "/" character in the URI requires use of quotes around the server URI parameter):

```
$ MULTINET IPP SHOW "LILLIES.FLOWERPOTS.COM/IPP" /FULL /OUTPUT=FOO.BAR
```

FOO.BAR contains:

LILLIES.FLOWERPOTS.COM/IPP as of Tue Aug 7 16:11:54 2001

CURRENT INFO:

```
Printer State:      Idle
State Reasons:      none
State Message:      <not supported>
Accepting Jobs?:    Yes
Queued Job Count:    <not supported>
Uptime (seconds):    <not supported>
Printer Time:        <not supported>
```

PRINTER INFO:

```
Name:              LILLIES
Printer Location:    <not supported>
Printer Info:        MANUFACTURER:Hewlett-Packard;COMMAND SET:PJL,ML -
                     C,PCL,PCLXL,POSTSCRIPT;MODEL:HP LaserJet 2100 -
                     Series;CLASS:PRINTER;DESCRIPTION:H
URL for more info:    <not supported>
URL for driver:        <not supported>
Make & Model:         <not supported>
URL for Maker:        <not supported>
```

DEFAULTS:

```
Document Format:      application/octet-stream
Orientation:          <not supported>
Number-Up:            <not supported>
Sides:                <not supported>
Copies:               <not supported>
Mult. Doc. Handling:  <not supported>
Media:                <not supported>
```

```

Job Media Sheets:    <not supported>
Finishings:          <not supported>
Job Priority:         <not supported>
Job Hold Until:      <not supported>
Print Quality:       <not supported>
Printer Resolution:  <not supported>
Character Set:       us-ascii
Natural Language:    en-us
Mult. Op. Timeout:   <not supported>

```

SUPPORTED FEATURES AND ALLOWED VALUES:

```

Color?:              <not supported>
Orientation:          <not supported>
Document Formats:    text/plain, text/plain; charset=US-ASCII,
                     application/postscript, application/vnd.hp-PCL,
                     application/octet-stream
Job Sheets:          <not supported>
Number-Up:           <not supported>
Sides:               <not supported>
Copies:              <not supported>
Mult. Doc. Handling: <not supported>
Media Names:         <not supported>
Job Media Sheets:    <not supported>
Finishings:          <not supported>
Job Priority:         <not supported>
Job Hold Until:      <not supported>
Page Ranges?:        <not supported>
Print Qualities:     <not supported>
Resolutions:         <not supported>
Compression Modes:   <not supported>
Job K-octets:        <not supported>
Job Impressions:     <not supported>
PDL Override:        not-attempted
Character Sets:       us-ascii, utf-8
Natural Languages:    en-us
URI Schemes:          <not supported>
Operations:           Print-Job, Validate-Job, Cancel-Job,
                     Get-Job_Attributes, Get-Jobs,
                     Get-Printer_Attributes

```

URIs Supported and associated security options:

```

URI:      /ipp
Security: none

```

```

URI:      /ipp/port1
Security: none

```

MESSAGE FROM OPERATOR:

<no Message>

- 3** Operation with /attribute and /SYMBOL and /GLOBAL to get a single attribute into a DCL symbol:

```
$ MULT IPP SHOW LEXIM /ATTRIB=NUMBER_UP_SUPPORTED /SYMBOL=NUMUP /GLOBAL
$ SHO SYM NUMUP
NUMUP == "1:16"
$
```

MULTINET KERBEROS DATABASE DUMP

Stores the contents of the Kerberos database in an ASCII text file. Use this command to transfer the contents of a master KDC database to another system which acts as a backup KDC. The ASCII format allows interchange among different vendors' implementations of Kerberos on different platforms. Passwords are output as encrypted text strings. Dumping the database to a text file and then editing it is the only way to delete users or principals from the database. Use MULTINET KERBEROS DATABASE LOAD to reload a dumped database.

FORMAT

MULTINET KERBEROS DATABASE DUMP *[outfile]*

QUALIFIER

/DATABASE_FILE=filename

Specifies that an alternative database is used instead of the MULTINET:KERBEROS_PRINCIPAL file. Do not specify a file name extension because the database code uses its own.

EXAMPLES

This example stores the Kerberos database named FOO into the DUMP_FILE.TXT text file. This text file can be loaded with the following command:

```
$ MULTINET KERBEROS DATABASE DUMP -  
_ $ /DATABASE_FILE=MULTINET:FOO. DUMP_FILE.TXT
```

In this example, the /DATABASE_FILE qualifier specifies the name of the database that is created.

```
$ MULTINET KERBEROS DATABASE LOAD -  
_ $ /DATABASE_FILE=MULTINET:FOO_TOO. DUMP_FILE.TXT
```

This example lists the contents of the database.

```
$ MULTINET KERBEROS DATABASE DUMP TT:
```

MULTINET KERBEROS DATABASE EDIT

Interactively adds principal information to the database.

FORMAT

MULTINET KERBEROS DATABASE EDIT

QUALIFIERS

/DATABASE_FILE=filename

Specifies that an alternative database is used instead of the MULTINET:KERBEROS_PRINCIPAL file. Do not specify a file name extension because the database code uses its own.

/PROMPT_FOR_KEY (default)

/NOPROMPT_FOR_KEY

Specifies that you are prompted to supply the master key password. /NOPROMPT_FOR_KEY causes the master key to be read from a file previously created with the MULTINET KERBEROS DATABASE STASH utility.

DESCRIPTION

MULTINET KERBEROS DATABASE EDIT adds principal information to the database. The principal can be either a user or a program. Table 1-2 describes the prompts displayed by this utility.

Table 1-2 KERBEROS DATABASE EDIT Prompts

At This Prompt...	Enter This Information
Enter Kerberos master key:	The encryption key for the Kerberos database. This is the master password for Kerberos administration and must be safeguarded. This is a standard VMS-style password except the value is case-sensitive and can be up to 64 bytes in length.
Principal name	A case-sensitive value, which generally is a user name if you are adding a user to the database, or the name of a principal used by a Kerberized server if you are entering a class of service. Exit KERBEROS DATABASE EDIT by pressing RETURN at the Principal name prompt.
Instance	A case-sensitive string value. When adding users to the database, enter an empty string (press RETURN). When associating a service type with a system, the instance is the system name. If the principal name is for a new user or application, the next prompt is "Not found, Create [y] ?". Enter y to create the principal entry, or n to enter another principal name.

Table 1-2 KERBEROS DATABASE EDIT Prompts (Continued)

At This Prompt...	Enter This Information
Change password	Change the password for a user or service. This prompt only appears if you specified an existing principal or instance name. If you enter y, you are prompted with the "New Password:" prompt; if you enter n, you are prompted for the Expiration date.
New password	Enter a new password. You can enter "RANDOM" for the password, which indicates the password is known only within the software. This feature adds additional security. Note: you must specify RANDOM in all uppercase letters. The only use for the RANDOM password feature with user accounts is to prevent users from accessing the Kerberos system. If you did not select the RANDOM feature and chose to change the password, enter a new password. You are prompted to verify the password you entered.
Expiration date	The date on which a user can no longer access the system, or the date that an application is no longer valid.
Max ticket lifetime	The maximum lifetime, in minutes, for a user's ticket. This can be any value from 5 to 1275 minutes (21 hours, 15 minutes).
Attributes	The valid range of this value is 0 to 65535, inclusive. The meaning of this value is system- and application-dependent. MultiNet applications do not currently use this value.

EXAMPLE

```

$ MULTINET KERBEROS DATABASE EDIT /NOPROMPT
Opening database...
Current Kerberos master key version is 1
Previous or default values are in [brackets],
enter Return to leave the same, or new value.
Principal name: rcmd
Instance: bigboote
<Not found>, Create [y] RETURN
Principal: rcmd, Instance: bigboote, kdc_key_ver: 1
New password: password
Verifying, please re-enter New Password: password
Principal's new key version = 1
Expiration date (enter yyyy-mm-dd) [ 2099-12-31 ] ? RETURN
Max ticket lifetime (*5 minutes) [ 255 ] RETURN
Attributes [ 0 ] ? RETURN
Edit O.K.
Principal name: john
Instance: RETURN
<Not found>, Create [y] RETURN

```

```
Principal: john, Instance: , kdc_key_ver: 1
New password: password
Verifying, please re-enter New Password: password
Principal's new key version = 1
Expiration date (enter yyyy-mm-dd) [ 2099-12-31 ] ? RETURN
Max ticket lifetime (*5 minutes) [ 255 ] RETURN
Attributes [ 0 ] ? RETURN
Edit O.K.
Principal name: RETURN
$
```


MULTINET KERBEROS DATABASE INITIALIZE

Initializes the Kerberos database. If you need to run this command on an already configured system, shut down Kerberos by first disabling the Kerberos and KADMIN servers using the MULTINET CONFIGURE /SERVERS command, then restart the MultiNet master server. Refer to the examples later in this section.

FORMAT

MULTINET KERBEROS DATABASE INITIALIZE

QUALIFIERS

/DATABASE_FILE=filename

Specifies the use of an alternative database instead of the MULTINET:KERBEROS_PRINCIPAL file. Do not specify a file name extension because the database code uses its own.

/REALM=realm

Specifies the Kerberos realm to use instead of the default (the local domain name specified in the MULTINET:KERBEROS.CONFIGURATION file). Note: the realm name is case-sensitive.

EXAMPLES

This example initializes the Kerberos database.

```
$ MULTINET KERBEROS DATABASE INITIALIZE
Realm name [REALM]: FLOWERS.COM
You will be prompted for the database Master Password.
It is important that you NOT FORGET this password.
Kerberos master key: password
Verifying, please re-enter Kerberos master key: password
$
```

This example shuts down Kerberos by disabling the KERBEROS and KADMIN servers, restarts the MASTER_SERVER process, then exits.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in symbols from SERVER image MULTINET:SERVER.EXE]
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>DISABLE KERBEROS
SERVER-CONFIG>DISABLE KADMIN
SERVER-CONFIG>RESTART
%RUN-S-PROC_ID, identification of created process is 2060005C
SERVER-CONFIG>EXIT
[Writing configuration to MULTINET_COMMON_ROOT:[MULTINET]
SERVICES.MASTER_SERVER]
```

MULTINET KERBEROS DATABASE LOAD

Loads the database from an ASCII text file produced by the MULTINET KERBEROS DATABASE DUMP utility. The ASCII text allows for interchange between different vendors' Kerberos implementations and different platforms, so the file being loaded does not need to be generated by the MultiNet Kerberos implementation.

FORMAT

MULTINET KERBEROS DATABASE LOAD [*outfile*]

QUALIFIER

/DATABASE_FILE=filename

Specifies that an alternative database is used instead of the MULTINET:KERBEROS_PRINCIPAL file. Do not specify a file name extension because the database code uses its own.

EXAMPLES

```
1 $ MULTINET KERBEROS DATABASE DUMP -  
  _$ /DATABASE_FILE=MULTINET:FOO. DUMP_FILE.TXT  
  $
```

This example stores the Kerberos database named FOO. into the DUMP_FILE.TXT text file. This text file can be restored with this command:

```
2 $ MULTINET KERBEROS DATABASE LOAD -  
  _$ /DATABASE_FILE=MULTINET:FOO_TOO. DUMP_FILE.TXT
```

The /DATABASE_FILE qualifier specifies the name of the created database.

MULTINET KERBEROS DATABASE NEW_MASTER_KEY

Permits the master key to be changed. After changing the master key, rebuild the database. Dump the database to an ASCII text file before using this command to change the master key. (You can dump the database to an ASCII text file with the MULTINET KERBEROS DATABASE UTILITY DUMP command.) After changing the key, re-stash the master key with the MULTINET KERBEROS DATABASE STASH command, and reload the database from the ASCII dump file with the MULTINET KERBEROS DATABASE UTILITY LOAD command.

FORMAT

MULTINET KERBEROS DATABASE NEW_MASTER_KEY

MULTINET KERBEROS DATABASE SRVTAB

Creates a service key file for use by server programs on the named system to decode KERBEROS authenticators. The output file name is of the form server-NEW-KERBEROS.SRVTAB, where server is the name of the remote system for which this file is being created. After creating the key file, transport it manually (not over the network, unless encryption is available) to the remote system, and copy it to MULTINET:KERBEROS.SRVTAB.

FORMAT

MULTINET KERBEROS DATABASE SRVTAB *host(s)*

PARAMETER

host(s)

Specifies one or more host names. *host* is *not* a fully qualified name and does not include dots. If specified in double quotes, mixed-case host names (for example, "Lot49") are preserved. If not specified in double quotes, all letters are converted to lowercase. If you do not supply this parameter, you are prompted for the host name(s).

QUALIFIERS

/PROMPT (default)

/NOPROMPT

Controls whether or not you are prompted to supply the master key password. /NOPROMPT causes the master key to be read from a file previously created with the MULTINET KERBEROS DATABASE STASH utility.

/REALM=realm

Specifies the Kerberos realm to use instead of the default (the local realm name specified in the MULTINET:KERBEROS.CONFIGURATION file). Note: the realm name is case-sensitive.

EXAMPLE

```
$ MULTINET KERBEROS DATABASE SRVTAB /REALM=FLOWERS.COM /NOPROMPT
```

MULTINET KERBEROS DATABASE STASH

Saves the master key in a protected file both for the KDC, which needs the master key to read the Kerberos database, and for the convenience of the administrator who does not have to enter the master password when accessing the Kerberos configuration utilities.

FORMAT

MULTINET KERBEROS DATABASE STASH

EXAMPLE

```
$ MULTINET KERBEROS DATABASE STASH
$
Kerberos master key: password
Verifying, please re-enter Kerberos master key: password
Current Kerberos master key version is 1.
```

MULTINET LOAD

Invokes the MultiNet network **LOADER**. This program loads a network image into the VMS kernel and starts the network.

Note! This utility is invoked automatically by the network startup command file generated by the Network Configuration Utility and should not be invoked by a user.

FORMAT

MULTINET LOAD

MULTINET NETCONTROL

Sends commands to services internal to the MULTINET_SERVER process. NETCONTROL can select any server provided in the MultiNet configuration or those previously added with the Server Configuration Utility. This command affects only the currently running configuration.

FORMAT

MULTINET NETCONTROL [*service*] [*command*]

PARAMETERS

service

Connects to the specified service (by default, NETCONTROL).

command

Sends a specified command string to the server. If you do not specify a command string, NETCONTROL enters interactive mode.

QUALIFIERS

/HOST=host

Connects to the NETCONTROL service on the specified host (by default, the NETCONTROL service on the local host).

/VERBOSE

Displays the entire NETCONTROL protocol conversation. This qualifier is useful only for debugging purposes.

DESCRIPTION

The NETCONTROL program sends commands to services internal to the MULTINET_SERVER process. NETCONTROL currently provides access to the following MultiNet services:

Table 1-3 MultiNet NETCONTROL Services

ACCESS	BOOTP	BWNFSD	CLUSTERALIAS
DHCLIENT	DHCP	DOMAINNAME	EKLOGIN
FONTSERVER	GATED	IPXRIP	KERBEROS
KLOGIN	KSHELL	NETCONTROL	NFS
NOT	NTP	PCNFSD	RARP
“R” Server	RDISC	REXEC	RLOGIN

Table 1-3 MultiNet NETCONTROL Services (Continued)

RPCBOOTPARAMS	RPCLOCKMGR	RPCMOUNT	RPCPORTMAP
RPCQUOTAD	RPCSTATUS	RSHELL	SAP
SNMP	SSH	SYSLOG	TELNET
TFTP	UCXQIO	VIADECNET	VIAPSI
XDM	XNTP		

For loadable services (those with an INIT setting of Merge_image), you can use the SERVER-CONFIG SET PROCESS process_name command to have the service run in an auxiliary master server process with the specified name, rather than in the main master server process (which has a process name of MULTINET_SERVER).

Unlike earlier versions of MultiNet:

- The auxiliary server no longer has to be manually started.
- The service(s) running in the auxiliary process can be controlled with NETCONTROL.

Use the SERVER-CONFIG SET FLAGS START_AUX_SERVER command to have the main master server start the auxiliary server process automatically. (You can also set it through MENU-CONFIG in "extended" mode.)

Services running in auxiliary master server processes can be controlled with NETCONTROL, independent of whether the START_AUX_SERVER flag is set, or whether the auxiliary process was started manually.

Auxiliary server processes are most useful for services which may require very large quantities of process quotas such as virtual memory. They can also be useful when there are problems with a loadable service that cause the master server to terminate abnormally; the service can be isolated in a separate process to prevent other services from being interrupted when the abnormal termination occurs.

The following command shuts down all services, including those run in auxiliary master server processes. (In earlier versions, services running in auxiliary master server processes were not affected by this command.)

```
$ MULTINET NETCONTROL NETCONTROL SHUTDOWN ALL
```

In addition, specifying a SET PROCESS command on the NETCONTROL service (in SERVER-CONFIG) has no effect; the NETCONTROL server always runs in the main master server process.

Invoke NETCONTROL with MULTINET NETCONTROL, or with NETCONTROL commands from inside the Server Configuration Utility or NFS Server Configuration Utility.

NETCONTROL connects to the NETCONTROL server on the local host, or on a remote host if one is specified. The following example demonstrates two ways of connecting to the RLOGIN service. Note: the NETCONTROL prompt indicates the name of the service to which you are connected.

\$ MULTINET NETCONTROL RLOGIN

Connected to NETCONTROL server on "LOCALHOST" < SP1.SPROCKET.COM Network Control 4.4 (nnn) at Mon 13-Mar-2002 7:42am-EST
RLOGIN>

\$ MULTINET NETCONTROL

Connected to NETCONTROL server on "LOCALHOST"
< SP1.SPROCKET.COM Network Control 4.4 (nnn) at Mon 13-Mar-2002 7:42am-EST
NETCONTROL>**SELECT RLOGIN**
RLOGIN>

The following example shows how to specify a NETCONTROL command from the command line. When used this way, NETCONTROL exits to DCL upon completion.

\$ MULTINET NETCONTROL RLOGIN SHOW

Connected to NETCONTROL server on "LOCALHOST"
< SP1.SPROCKET.COM Network Control 4.4 (nnn) at Mon 13-Mar-2002 7:42am-EST
< File Cache:
< MULTINET:HOSTS.EQUIV (Expires in 59 minutes)
< USERS:[MIGUEL].rhosts (Expired)
< Authorization Cache:
< EDUARDA (Expires in 59 minutes)
< MIGUEL (Expired)
\$

You can also use NETCONTROL to control the MULTINET_SERVER on a remote system, subject to the restrictions set on that system's NETCONTROL server.

The following example shows how to invoke NETCONTROL on a remote system.

\$ MULTINET NETCONTROL/HOST=SP1.SPROCKET.COM RLOGIN

Connected to NETCONTROL server on "SP1.SPROCKET.COM"
< SP1.SPROCKET.COM Network Control 4.4 (nnn) at Mon 13-Mar-2002 7:42am-EST
RLOGIN>

To change the ACCOUNTING and DEBUG parameters with the MULTINET NETCONTROL command, use the following commands. Use the DEBUG parameter to dynamically set the MultiNet server debugging level to the specified value *n*. By default, additional information is provided in the accounting record by the MultiNet server. You can disable this feature by setting *n* to 0. When set to 1, the remote name and service name are added to the ACCOUNTING record.

\$ MULTINET NETCONTROL NETCONTROL DEBUG *n* RETURN

\$ MULTINET NETCONTROL NETCONTROL ACCOUNTING *n* RETURN

Table 1-4 shows the NETCONTROL commands you can use at any time.

Table 1-4 NETCONTROL Commands Valid at any Time

Command	Description
LIST	Prints a list of the active services that support NETCONTROL.

Table 1-4 NETCONTROL Commands Valid at any Time (Continued)

Command	Description
NOOP	Does nothing; provided for testing the NETCONTROL server.
QUIT	Exits NETCONTROL.
QUOTE <i>string</i>	Sends a string verbatim to the NETCONTROL server.
SELECT <i>service</i>	Selects a service on which to operate. Use the question mark (?) character to get a list of services.
SERVER-VERSION	Prints the version number of the MULTINET_SERVER process.
STATISTICS	Prints server usage statistics.
TIMERS	Prints debugging information about the various scheduler events in the MULTINET_SERVER process.
VERBOSE	Turns on verbose printing of NETCONTROL commands and responses.
VERSION	Prints the version number of the selected server.

Table 1-5 shows the NETCONTROL commands you can use with the ACCESS server.

Table 1-5 NETCONTROL ACCESS Commands

Command	Description
DEBUG <i>n</i>	Sets the ACCESS debugging level. The larger the number, the more verbose the output.
RELOAD <i>n</i>	Rereads your access configuration file MULTINET:START_ACCESS.COM if it is not redefined with the configuration file parameter.

Table 1-8 shows the NETCONTROL commands you can use with the BOOTP server.

Table 1-6 NETCONTROL BOOTP Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
DUMP	Dumps the BOOTP database.
RELOAD	Reloads the BOOTP database.

Table 1-7 shows the NETCONTROL command you can use with the BWNFSD server.

Table 1-7 NETCONTROL BWNFSD Command

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.

Table 1-8 shows the NETCONTROL commands you can use with the CLUSTERALIAS server

Table 1-8 NETCONTROL CLUSTERALIAS Commands

Command	Description
DEBUG <i>n</i>	Sets the CLUSTERALIAS debugging level. The larger the number, the more verbose the output.
RELEASE <i>ip address</i>	Releases the system's lock of the cluster alias address.
SHOW <i>n</i>	Displays the state of the cluster alias.

Table 1-9 shows the NETCONTROL commands you can use with the DHCP client.

Table 1-9 NETCONTROL DHCP Client Commands

Command	Description
DEBUG <i>value</i>	Specifies a decimal integer that is a bitmask of debugging levels used to select messages to pass to OPCOM and the debug log file specified in the DEBUG-FILE parameter. The debugging levels are (in decimal): <ul style="list-style-type: none"> 1 Fatal Errors 3 Errors and Warnings 7 Informationals 15 Debug Messages 31 Dump Packets (Formatted) 63 Dump Packets (Hex) By default, Fatal Errors and Warnings are logged.
VERSION	Prints the version number of the DHCP Client Control component.
SHUTDOWN	Causes the DHCP Client to shut down. <p>Note! This command does not delete the service from the Master Server. It is still registered with NETCONTROL.</p>
START	Starts a DHCP Client that has been down by the DHCLIENT SHUTDOWN command.

Table 1-10 shows the NETCONTROL commands you can use with the DHCP server.

Table 1-10 NETCONTROL DHCP Commands

Command	Description
DEBUG <i>value</i>	<p>Specifies a decimal integer that is a bitmask of debugging levels used to select messages to pass to OPCOM and the debug log file specified in the DEBUG-FILE parameter. The debugging levels are (in decimal):</p> <ul style="list-style-type: none">1 Fatal Errors3 Errors and Warnings7 Informationals15 Debug Messages31 Dump Packets (Formatted)63 Dump Packets (Hex) <p>By default, Fatal Errors, Errors, and Warnings are logged.</p>
DHCP-CONTROL-VERSION	Prints the version number of the DHCP Control component.
DUMP <i>file</i>	Writes the in-memory configuration of the DHCP server to the file specified or to the DUMPFIL parameter value if <i>file</i> is not specified.
NEWLOG	Starts a new debug log file, if one is in use.
PARTNERDOWN	For Safe-Failover DHCP: Causes the DHCP server to transition into Partner Down state, which indicates that its safe-failover DHCP partner is down.
RELEASE <i>ip-address</i>	Forces the DHCP server to act as if it heard a DHCP release from the client. This applies to dynamically assigned IP addresses only. Note: the DHCP protocol has no way to tell the client that the address is released, so this command must be used with caution.
RESTART or RELOAD	Causes the server to restart, at which time it rereads the configuration file.

Table 1-10 NETCONTROL DHCP Commands (Continued)

Command	Description
SHOW	Prints a variety of information, depending on the arguments used.
SHOW ALL	Takes no arguments. Displays on your computer screen the SHOW SUBNET output for all subnets followed by information about all static assignments in the DHCP server configuration.
SHOW CID <i>client-identifier</i>	Shows all lease binding and static assignment details for the specified client identifier.
SHOW CLIENT <i>ip-address</i>	Shows lease binding details for the specified IP address. The IP address must be in a dynamic address pool.
SHOW HADDR <i>hardware-address</i>	Shows all lease binding and static assignment details for the specified hardware address.
SHOW ISKNOWN HOST <i>hardware-address-or- client-identifier</i>	Shows whether the given hardware address or client identifier is "known", that is if there is a <i>host</i> declaration for that hardware address or client address.
SHOW ISKNOWN SUBCLASS <i>class-name subclass-data</i>	Shows whether the given subclass data exists as a subclass within the given class.
SHOW SUBNET <i>ip-address</i>	Shows the DHCP address pools for the shared network that <i>ip-address</i> is in. Lists each subnet that is on the shared network and each IP address in each pool.
SHOW LEASES	Shows all IP addresses with leases (pending, active, or expired) for each shared network. Uses the same format as the SHOW ALL command.
SHOW POOLS	For each address pool, shows the total number of IP addresses, number of abandoned IP addresses, number reserved for secondary, and number available to be leased. Uses a table format.
SHUTDOWN	Stops the server. Note! This command does not delete the service from the master server. It is still registered with NETCONTROL.

Table 1-10 NETCONTROL DHCP Commands (Continued)

Command	Description
START	Starts a server that has been shut down by the DHCP SHUTDOWN command.
STATISTICS	This command is supplied only for backward compatibility with previous versions of MultiNet. It has been superseded by the SHOW POOLS command.
UPDATE [(file)]	Causes the server to execute the commands in the specified file, if any, or the file specified in the UPDATEFILE parameter, if any, or the default file MULTINET:DHCPD.UPDATES.

Table 1-11 shows the NETCONTROL commands you can use with the DOMAINNAME server.

Table 1-11 NETCONTROL DOMAINNAME Commands

Command	Description
DEBUG <i>n</i>	Sets the debug level of the Domain Nameserver (the default is no debugging). The larger the number, the more verbose the output. A value of 0 turns off debugging.
DUMP	Dumps the Domain Nameserver cache to the file MULTINET:DOMAIN-NAME-SERVICE.DB. Use to diagnose database problems.
MAXIMUM-TTL <i>ttl</i>	Changes the maximum time-to-live (TTL) that resource records are cached from the default of 604800 seconds (1 week) to the specified value.
MINIMUM-TTL <i>ttl</i>	Changes the minimum time-to-live (TTL) that resource records are cached from the default of zero (0) seconds to the specified value. Note! It is recommended you use this command only if there is a specific need. This could cause problems in that you may be caching resource records for longer than the authoritative administrator intended.
QUERYLOG	Toggles query logging ON and OFF. Query logging shows an informational message every time a query is received by the server. Query logging can be directed to OPCOM or a file in the MULTINET:NAMED.CONF file using the logging category <i>queries</i> .
RELOAD	Causes the Domain Nameserver to re-read the configuration file, and subsequently re-read any zone files that have changed.

Table 1-11 NETCONTROL DOMAINNAME Commands (Continued)

Command	Description
RESTART	Instructs the nameserver to shutdown if it exists, then instructs the master server to start a new nameserver process.
REWRITE-TTL <i>ttl</i>	Sets the time-to-live (TTL) that load balanced resource records are cached from the default of 300 seconds (5 minutes) to the specified value.
SHOW	Shows the nodename, address, and rating of any cluster server names.
START	Instructs the master server to start the nameserver process.
STATISTICS	Appends Domain Nameserver server statistics to the file MULTINET:DOMAIN-NAME-SERVICE.STATS and memory statistics to the file MULTINET:DOMAIN-NAME-SERVICE.MEMSTATS.
STOP or SHUTDOWN	Stops the server. Note! This command does not delete the service from the master server. It is still registered with NETCONTROL.
VERSION	Prints the current DNS server version number. (This is the version of BIND from which the MultiNet DNS server is derived.)

Table 1-12 shows the NETCONTROL commands you can use with the EKLOGIN server:

Table 1-12 NETCONTROL EKLOGIN Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
FLUSH-CACHE	Flushes the “KR” services authentication cache.

Table 1-13 shows the NETCONTROL commands you can use with the FONTSERVER server.

Table 1-13 NETCONTROL FONTSERVER Commands

Command	Description
DEBUG	Sets the FONTSERVER debugging level. The larger the number, the more verbose the output.
FLUSH	Removes the fonts loaded into the font server’s cache.

Table 1-13 NETCONTROL FONTSERVER Commands (Continued)

Command	Description
FS-CONTROL-VERSION	Prints the version number of the FONTSERVER control component.
RELOAD	Reloads the font server configuration file MULTINET:FONT_SERVER.CONFIGURATION.
RESET	Resets the server and closes down all connections to the client.
RESTART	Restarts the server.
START	Starts the server.
SHUTDOWN	Stops the server.

Table 1-14 shows the NETCONTROL commands you can use with the GATED server.

Table 1-14 NETCONTROL GATED Commands

Command	Description
DEBUG <i>n</i>	Sets the GATED debugging level. The larger the number, the more verbose the output. 0 (the default) is typical and suppresses any informational /debug messages.
DUMP	Dumps GATED's internal routing table to the trace file. A trace file must be set, either through the configuration file or by using the NETCONTROL TRACE-FILE command.
TRACE	Establishes the information to be logged in the trace file. Possible values are: ALL—all events NONE—no events INTERNAL-ERRORS—internal error conditions EXTERNAL-CHANGES—external changes to the routing table ROUTING-CHANGES—any changes to the routing table PACKETS—received packets EGP-UPDATES—any EGP routing updates RIP-UPDATES—any RIP routing updates HELLO-UPDATES—any HELLO routing updates ICMP-UPDATES—any ICMP routing updates This command corresponds to the trace directive in the configuration file.

Table 1-14 NETCONTROL GATED Commands (Continued)

Command	Description
TRACE-FILE	Sets the name of the trace file. The default is no trace file. This command corresponds to the trace directive in the configuration file.

Table 1-15 shows the NETCONTROL commands you can use with the IPXRIP server.

Table 1-15 NETCONTROL IPXRIP Commands

Command	Description
ADVERTISE <i>true</i> / <i>false</i>	Advertises non-local routes. The default is “true”.
DEBUG <i>n</i>	Sets the debugging log level.
FLUSH	Flushes the non-local routes and updates the interface configuration.
SEND	Sends the IPX RIP packets.
SHOW	Displays the IPX RIP routing table.

Table 1-16 shows the NETCONTROL command you can use with the KERBEROS server.

Table 1-16 NETCONTROL KERBEROS Command

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.

Table 1-17 shows the NETCONTROL commands you can use with the KLOGIN server.

Table 1-17 NETCONTROL KLOGIN Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
FLUSH-CACHE	Flushes the “KR” services authentication cache.

Table 1-18 shows the NETCONTROL commands you can use with the KShell server.

Table 1-18 NETCONTROL KShell Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
FLUSH-CACHE	Flushes the “KR” services authentication cache.

Table 1-19 shows the NETCONTROL commands you can use with the NETCONTROL server.

Table 1-19 NETCONTROL NETCONTROL Commands

Command	Description
ACCOUNTING <i>n</i>	Disables accounting with an integer value of 0. A positive value enables accounting. The accounting value is checked whenever the master_server starts up a service. The accounting provided is PID, host name, node name, and service name.
DEBUG <i>n</i>	Sets the NETCONTROL debugging level. The larger the number, the more verbose the output.
SHUTDOWN <i>all</i> or <i>service name</i>	Shuts down all services or shuts down a specific services.

Table 1-20 shows the NETCONTROL commands you can use with the NFS Server.

Table 1-20 NETCONTROL NFS Commands

Command	Description
ADD MOUNT-RESTRICTION	Exports a mount point for <i>read-only access</i> . Any attempt to write to the disk specified by this mount point fails. This restriction affects any NFS group associated with that particular mount point.
AVERAGE-RESPONSE-TIMES	Computes average response times. Do not use without first contacting Process Software Technical Support.
DUMP	Dumps the NFS Server cache into the file MULTINET:NFS_SERVER.DUMP for debugging; DUMP is ignored unless the NFS Server is running in user mode.
FILECACHE-DEBUG <i>n</i>	Sets the debug level of the file system cache portion of the server.

Table 1-20 NETCONTROL NFS Commands (Continued)

Command	Description
NFS-CONTROL-VERSION	Prints the version number of the NFS NETCONTROL module.
NFSDEBUG <i>n</i>	Sets the debug level of the NFS protocol portion of the server.
RECORD-RESPONSE-TIMES	Records response time data. Do not use without first contacting Process Software Technical Support.
RELOAD	Reloads the UID/GID table in the NFS Server. This command does not reload the client; that is done with NFSMOUNT/RELOAD. If you want to reload both, use MULTINET CONFIGURE /NFS when you modify the configuration file.
RESTART	Restarts the NFS Server process.
RPCDEBUG <i>n</i>	Sets the debug level of the RPC protocol portion of the server.
SHOW-RESPONSE-TIMES	Displays response time data. Do not use without first contacting Process Software Technical Support.
SHUTDOWN	Stops the server.
START	Starts the server.

Table 1-21 shows the NETCONTROL commands you can use with the NOT server.

Table 1-21 NETCONTROL NOT Commands

Command	Description
DEBUG	Sets the NOT debugging level. The larger the number, the more verbose the output.
RELOAD	Reloads the NOT.CONFIGURATION or the configuration file the parameter for the NOT service is set to.

Table 1-22 shows the NETCONTROL commands you can use with the NTP server.

Table 1-22 NETCONTROL NTP Commands

Command	Description
ADJUST-FRACTION <i>n</i>	Controls the rate at which the VMS system clock is adjusted. Do not use this parameter without first contacting Process Software Technical Support.
DEBUG <i>n</i>	Sets the debug level of the NTP server. The larger the number, the more verbose the output.
LOG-STATISTICS <i>n</i>	Controls whether clock adjustments are logged on OPCOM. The default is 0 (no logging); a non-zero value enables logging.
SHOW	Shows parameters governing the NTP filters and a list of the NTP peers.

Table 1-23 shows the NETCONTROL command you can use with the PCNFSD server.

Table 1-23 NETCONTROL PCNFSD Command

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.

Table 1-24 shows the NETCONTROL commands you can use with the RARP server.

Table 1-24 NETCONTROL RARP Commands

Command	Description
DEBUG <i>n</i>	Sets the RARP debugging level. The larger the number, the more verbose the output.
RELOAD	Reloads the RARP database.

Table 1-25 shows the NETCONTROL commands you can use with NETCONTROL REXEC, NETCONTROL RLOGIN, or NETCONTROL RSHELL.

Table 1-25 NETCONTROL "R" Server Commands

Command	Description
DEBUG	Sets the "R" SERVICES debugging level. The larger the number, the more verbose the output.

Table 1-25 NETCONTROL "R" Server Commands (Continued)

Command	Description
FLUSH-CACHE	Flushes the "R" services authentication caches.
SHOW-CACHE	Prints the contents of the "R" services authentication caches.

Table 1-26 shows the NETCONTROL commands you can use with the RDISC server.

Table 1-26 NETCONTROL RDISC Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
FLUSH-CACHE	Flushes the "KR" services authentication cache.

Table 1-27 shows the NETCONTROL commands you can use with the RPCBOOTPARAMS server.

Table 1-27 NETCONTROL RPCBOOTPARAMS Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
RELOAD	Reloads the RPC boot parameters for diskless hosts.

Table 1-28 shows the NETCONTROL commands you can use with the RPCLOCKMGR server.

Table 1-28 NETCONTROL RPCLOCKMGR Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
NOOP	Does nothing; provided for testing the NETCONTROL server.
RPCLOCKMGR-CONTROL-VERSION <i>n</i>	Displays the version number of the RPC Lock Manager Control Server.
SHOW <i>n</i>	Shows the locks associated with this server.
START	Starts the RPC Lock Manager.
STOP	Stops the RPC Lock Manager.

Table 1-28 NETCONTROL RPCLOCKMGR Commands (Continued)

Command	Description
TIMERS <i>n</i>	Displays the timers.

Table 1-29 shows the NETCONTROL commands you can use with the RPCMOUNT server.

Table 1-29 NETCONTROL RPCMOUNT Commands

Command	Description
CLEAR	Clears the database of clients that have file systems mounted.
DEBUG <i>n</i>	Sets the RPCMOUNT debugging level. The larger the number, the more verbose the output.
DUMP	Forces RPCMOUNT to write the current mount database to the on-disk cache; it is normally only written every few minutes.
RELOAD	Reloads export and restriction databases from the NFS.CONFIGURATION file.
SHOW	Prints the current mount database.

Table 1-30 shows the NETCONTROL commands you can use with the RPC Portmapper server.

Table 1-30 NETCONTROL RPCPORTMAP Commands

Command	Description
DEBUG <i>n</i>	Sets the RPCPORTMAP debugging level. The larger the number, the more verbose the output.
SHOW	Prints the current portmap database.

Table 1-31 shows the NETCONTROL command you can use with the RPCQUOTAD server.

Table 1-31 NETCONTROL RPCQUOTAD Command

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.

Table 1-32 shows the NETCONTROL commands you can use with the RPCSTATUS server.

Table 1-32 NETCONTROL RPCSTATUS Commands

Command	Description
DEBUG <i>n</i>	Sets the RPCSTATUS debugging level. The larger the number, the more verbose the output.
RELOAD	Reloads the RPCSTATUS database.
SHOW	Shows the parameters governing RPCSTATUS.
SIMULATE-CRASH	Causes the server to notify all monitoring clients that the system has crashed. Do not use this command without first contacting Process Software Technical Support.

Table 1-33 shows the NETCONTROL commands you can use with the SAP server.

Table 1-33 NETCONTROL SAP Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
FLUSH	Flushes the advertised services.
NEAREST-SERVER-REPLIES <i>true / false</i>	SAP responds to the nearest server requests. The default is true.
QUERY	Performs an SAP query.
REFRESH	Performs an SAP bindery refresh.
SEND	Sends an SAP packet.
SHOW	Displays SAP status and information.
BROADCAST-DEATHS <i>true / false</i>	Broadcasts SAP server deaths. The default is true.

Table 1-34 shows the NETCONTROL commands you can use with the SNMP server.

Table 1-34 NETCONTROL SNMP Commands

Command	Description
RELOAD	Causes the SNMP Agent to reread the configuration file.

Table 1-34 NETCONTROL SNMP Commands (Continued)

Command	Description
SHUTDOWN	Stops the SNMP Agent. Note! This command does not delete the service from the master server. It is still registered with NETCONTROL.
SNMP-CONTROL-VERSION	Prints the version number of the SNMP Agent component.
START	Starts a SNMP Agent that has been shut down by the SNMP SHUTDOWN command.

Table 1-35 shows the NETCONTROL commands you can use with the SSH server.

Table 1-35 NETCONTROL SSH Commands

Command	Description
DEBUG	Toggles debugging on/off in all SSHD daemon processes running on the server.
MASTER_RESTART	Stops and restarts only the SSHD Master process. All other SSH processes and users are not affected.
RESTART	Stops and restarts the server. This stops not only the SSHD_MASTER process but also all SSHD processes running on the server, which has the effect of logging out all SSH sessions currently active on the server.

Table 1-35 NETCONTROL SSH Commands (Continued)

Command	Description
SHOW	<p>Displays information on all executing daemon processes. For example:</p> <pre> RAPTOR_\$ mu netcontrol ssh show Connected to NETCONTROL server on "LOCALHOST" < raptor.pscos.com Network Control V4.4(10) at Tue 9-May-2002 11:41AM-MDT < < SSHD Master PID = 20800099 < < Process "SSHD 0000" (pid 20800156) < User = OREILLY < From system 217.225.229.75 port 1064 < Started: 05/09/2002 17:41:43 < Bytes in: 23 out: 425 (from child process: 425) < PTD Device = _FTA5: < Current child process = "OREILLY_@FTA5" (pid 20800157) < < End of Show SSH RAPTOR_\$ </pre>
SHUTDOWN	Stops the server. This stops not only the SSHD_MASTER process but also all SSHD processes running on the server, which has the effect of logging out all SSH sessions currently active on the server.
START	Starts the server.

Table 1-36 shows the NETCONTROL commands you can use with the SYSLOG server.

Table 1-36 NETCONTROL SYSLOG Commands

Command	Description
DEBUG <i>n</i>	Sets the debugging log level.
RELOAD	Reloads the configuration file.

Table 1-37 shows the NETCONTROL commands you can use with the TELNET server.

Table 1-37 NETCONTROL TELNET Commands

Command	Description
DEBUG	Sets the TELNET debugging level. The larger the number, the more verbose the output.

Table 1-37 NETCONTROL TELNET Commands (Continued)

Command	Description
TRACE <i>n</i>	Sets the trace level.

Table 1-38 shows the NETCONTROL commands you can use with the TFTP server.

Table 1-38 NETCONTROL TFTP Commands

Command	Description
DEBUG <i>n</i>	Sets the TFTP debugging level. The larger the number, the more verbose the output.
RELOAD	Reloads the TFTP server parameters (the default TFTP directory and MULTINET:TFTP.FILENAME-TRANSLATIONS).
SHOW	Prints the current status of the TFTP server.
SHOW-TRANSLATION	Shows the TFTP file name translation table.

Table 1-39 shows the NETCONTROL command you can use with the UCXQIO server.

Table 1-39 NETCONTROL UCXQIO Command

Command	Description
DEBUG <i>n</i>	Sets the UCXQIO debugging level. The larger the number, the more verbose the output.

Table 1-40 shows the NETCONTROL commands you can use with the VIADECNET server.

Table 1-40 NETCONTROL VIADECNET Commands

Command	Description
DEBUG <i>n</i>	Sets the VIADECNET debugging level. The larger the number, the more verbose the output.
RELOAD	Reloads the configuration from the network kernel.
SHUTDOWN	Stops the server.

Table 1-41 shows the NETCONTROL commands you can use with the VIAPSI server.

Table 1-41 NETCONTROL VIAPSI Commands

Command	Description
DEBUG <i>n</i>	Sets the VIAPSI debugging level. The larger the number, the more verbose the output.
DISCONNECT <i>interface-or-DTE</i>	Clears the X.25 connection for the given interface (for example, psi0) or peer DTE.
IDLE <i>seconds</i>	Sets the default connection-idle interval.
RELOAD	Checks the PSI devices for the configuration, and if changes were made, reinitializes the configuration.
SHUTDOWN	Stops the server; not yet implemented.

Table 1-42 shows the NETCONTROL commands you can use with the XDM server.

Table 1-42 NETCONTROL XDM Commands

Command	Description
DEBUG	Sets the XDM debugging level. The larger the number, the more verbose the output.
RELOAD	Causes the XDM server to reload its configuration file.
RESTART	Restarts the XDM server.
SHOW	Shows the status of all managed displays.
START	Starts the server.
SHUTDOWN	Stops the server.
XDM-CONTROL-VERSION	Prints the version number of the XDM Control component.

Table 1-43 shows the NETCONTROL commands you can use with the XNTP server.

Table 1-43 NETCONTROL XNTP Commands

Command	Description
DEBUG <i>level</i>	Sets the XNTP debugging level. The larger the number, the more verbose the output.

Table 1-43 NETCONTROL XNTP Commands (Continued)

Command	Description
RELOAD	Causes the server to reload the configuration file by stopping and restarting.
SHOW	Shows the current state of all server and peer connections.
SHUTDOWN	Stops the server.
START	Starts the server.
VERSION	Shows the version of the server.
WAYTOOBIG <i>level</i>	Sets the largest value (in seconds) that will be corrected. The default is 4000 seconds, or just over 66 minutes.
XNTP-CONTROL-VERSION	Shows the version of the XNTP control program.

MULTINET NFSDISMOUNT

Dismounts a remotely mounted NFS file system.

FORMAT

MULTINET NFSDISMOUNT *mount_device*

PARAMETER

mount_device

Specifies an NFSx: device associated with a remotely mounted file system.

QUALIFIERS

/ALL [*host_name*]

Specifies that NFSDISMOUNT notifies remote systems that no file systems are currently mounted (this is usually used as part of the reboot procedure).

Note! NFSDISMOUNT/ALL does not dismount file systems, but rather notifies an NFS server that the local system does not have any mounted. If you do not specify *host_name*, NFSDISMOUNT broadcasts the request to the local network.

/LOG

Specifies that NFSDISMOUNT displays information when a dismount occurs.

EXAMPLE

This example shows how to dismount a remotely mounted file system attached to the local mount device NFS3:.

```
$ MULTINET NFSDISMOUNT NFS3:
```

MULTINET NFSMOUNT

Mounts a remote NFS file system so it can be used locally. NFSMOUNT requires CMKRNL, SETPRV, SYSPRV, SYSNAM, ALTPRI, DETACH, ACNT, and SYSLOCK privileges.

FORMAT

MULTINET NFSMOUNT *node::mount_point logical_name*

PARAMETERS

node

Specifies the name of the computer serving the file system to the network.

mount_point

Specifies the portion of an NFS file system to be mounted. The format of the specified mount point depends on the server. Enclose mount_point in quotes if it contains special or lowercase characters.

logical_name

Specifies an OpenVMS logical name to assign to the mount device. OpenVMS users can access remote files using this logical name.

QUALIFIERS

/FID_CACHE=size

Specifies the size (in bytes) of the File Identifier (FID) cache. Values range from 5 to 5000000. The default is 10000.

**/LOCKING=([local,]
[network])**

Specifies the type of file locking used on the NFS-mounted file system.

- **LOCAL**—Specifies that OpenVMS file-locking operations will only be consistent on the local system.
- **NETWORK**—Uses the NFS Network Lock Manager to obtain consistent file locking between all NFS clients. Use of the **/LOCKING=NETWORK** qualifier adds protocol overhead.

If you specify both **LOCAL** and **NETWORK**, network locking is attempted; if the remote lock manager cannot be contacted, local locking is used.

/PAGEFILE=pages

Specifies the page file quota for the **NFS_CLIENT_ACP** process. This process is created when the first NFS file system is mounted. This qualifier is ignored on subsequent mounts. The default is 65535 pages.

/PORT=*port_number*

Specifies the remote port to connect to for NFS service.

/PRIORITY=*priority*

Specifies the base process priority of the NFS_CLIENT_ACP process created when the first NFS file system is mounted. The qualifier is ignored on subsequent mounts. The default is 7.

/PROCESSOR={UNIQUE | SAME}

Determines whether a separate ACP process is created for every NFS device. This mechanism allows NFS devices to function in parallel so that one NFS device does not have to wait for an NFS operation on another NFS device to complete. Multiple ACPs allow for multiple outstanding I/O, and operations happen in parallel.

A setting of UNIQUE creates a separate NFS_CLIENT_*n* process for each mount, where *n* is the number of the NFS device (such as NFS_CLIENT_2, which corresponds with the device NFS2).

A setting of /PROCESSOR=SAME=*nfs_device* assigns the mount to the same ACP process as the specified *nfs_device*. For example, /PROCESSOR=SAME=NFS3 assigns this mount to the NFS_CLIENT_3 ACP process.

Any mounts specified without the /PROCESSOR qualifier use a single, default process.

It is recommended that you use the /PROCESSOR qualifier to group mounts based on the remote server. That way, if the server goes down, it does not cause access to other servers to hang. (You can use the /SOFT qualifier to permit NFS operations to time out instead of hanging indefinitely.)

/READ_SIZE=*read_size*

Specifies the maximum size of the read operations the NFS Client performs. The default, 8192, is correct for most servers.

/RELOAD

Instructs the NFS client software to reload its UID translation table from the NFS configuration file.

```

[ advisory_close, ]
[ case_insensitive_filenames, ]
[ nofdl_files, ]
[ nolinks, ]
[ nostream_conversion, ]
[ nounique_fileno, ]
/SEMANTICS=( [ noversions, ]
[ novms_access_checking, ]
[ preserve_dates, ]
[ upper_case_default, ]
[ vms_filenames, ]
[ vms_server, ]

```

Specifies the capabilities and characteristics of the NFS Server that control the behavior of the

MultiNet NFS Client, as described in the following table.

Attribute	Description
ADVISORY_CLOSE	Sends a VMS server a command to close the file when there are no more references to it on the client.
CASE_INSENSITIVE_FILENAMES	<p>Specifies that UNIX files accessed by an OpenVMS system not have their file names converted using the conversion characters (see HELP MULTINET File_Name_Character_Map for a list of these characters).</p> <p>Use this option when an NFS server treats all file names as case-insensitive. When this option is set, all file names accessed through NFS are converted to lowercase. When returned to the server, they are handled in lowercase. The NFS server must be able to accept lowercase file names. This option is disabled by default.</p>
NOFDL_FILES	Disables the use of ".\$fdl\$" files by the MultiNet NFS Client to store RMS attributes. This option must be used if the NFS server doesn't allow these file names. Its use severely limits the ability of the NFS Client to store record attributes.
NOLINKS	Disables the automatic creation of hard links to the latest version of a file. The NFS Client normally uses a hard link operation to link the top version of a file name "foo.bar;12" to the unversioned name "foo.bar" for more convenient access from the NFS Server side. This option may be used either to reduce the overhead in creating it or if the NFS Server does not support hard links.
NOSTREAM_CONVERSION	Disables the automatic conversion of text files to STREAM format. The NFS Client normally converts requests to create Variable Length Record Carriage Return Carriage Control files into requests to create Stream files. This option disables this conversion.

Attribute	Description
NOUNIQUE_FILENO	Specifies whether or not the NFS Server is to generate unique file numbers for each file (most NFS servers do). If the client knows that file numbers are unique, it uses a faster algorithm to refresh stale directory entries in the cache. Use of this qualifier disables the faster refresh algorithm, and is equivalent to the /NOUNIQUE_FILENO qualifier.
NOVERSIONS	Disables support for multiple file versions. The NFS Client normally stores multiple versions of OpenVMS files by using the semicolon character in the file name on the NFS Server side. You must use this option to disable the ability to create multiple versions of files if the NFS Server does not support file names with the semicolon character.
NOVMS_ACCESS_CHECKING	Specifies that the client does not perform a full OpenVMS access check, including a check for ACLs and security alarms. If this option is not specified, the NFS Client considers ACLs and security alarms when granting or denying access.
PRESERVE_DATES	Allows you to store VMS-style dates and times for files.
UPPER_CASE_DEFAULT	Assumes file names are in uppercase on the server until it sees the \$ character used to toggle case.
VMS_FILENAMES	Specifies that the NFS Client should not perform the usual mapping between OpenVMS and UNIX-style file names. This option can be used to permit all OpenVMS file names to be stored using the NFS client; however, its use prevents the NFS Client from being used to access files which do not conform to the OpenVMS file name conventions.
VMS_SERVER	Specifies that the NFS server is a MultiNet NFS Server of revision V3.0 or later and supports OpenVMS-specific extensions to the NFS protocol to store file attributes. If the NFS Server does not support these extensions, the mount will fail. This option is equivalent to the /VMS_SERVER qualifier and overrides any other semantics specified.

/SOFT

Specifies that, if the NFS client is unable to reach the NFS server after the time period specified by /TIMEOUT, an error is returned to the user (SS\$_UNREACHABLE). If the file system is mounted without the /SOFT qualifier, the NFS client retries the operation forever.

/TIMEOUT=*timeout*

Specifies the total time, in tenths of a second, that it takes for an RPC request to timeout. Retries are attempted via UDP for an interval of one-fifth the value specified for /TIMEOUT. The minimum value allowed for this setting is 30 tenths of a second. /TIMEOUT does not affect TCP timeouts.

**/TRANSPORT=([*tcp*,]
[*udp*])**

Specifies the underlying transport used for the NFS requests. (The default is UDP if /TRANSPORT is not specified.) The TCP transport can be used with servers that support it. If you specify both transports, TCP is tried first; if it fails, the mount uses UDP.

/UNIQUE_FILENO (default)**/NOUNIQUE_FILENO**

Specifies whether or not the NFS Server is to generate unique file numbers for each file (most NFS servers do). If the NFS Client knows that file numbers are unique, it uses a faster algorithm to refresh stale directory entries in the cache. The /NOUNIQUE_FILENO qualifier is equivalent to /SEMANTICS=NOUNIQUE_FILENO.

/VMS_SERVER

Specifies that the NFS server is a MultiNet NFS Server of revision V3.0 or later and supports OpenVMS-specific extensions to the NFS protocol to store file attributes. If the NFS Server does not support these extensions, the mount fails. This qualifier is equivalent to /SEMANTICS=VMS_SERVER and overrides any other semantics specified.

/VOLUME=*volume_name*

Specifies the display name of the mounted volume (which appears via SHOW DEVICE). (The default is the remote mount_point name.)

/WRITE (default)**/NOWRITE**

Specifies whether or not the file system is to be mounted for both read and write access. /NOWRITE prevents users from modifying the file system.

/WRITE_SIZE=*write_size*

Specifies the maximum size of packets written by the NFS client. The default, 8192, is correct for most servers.

/WSEXTENT=*pages*

Specifies the working set extent for the NFS_CLIENT_ACP process. This process is created when the first NFS file system is mounted. The qualifier is ignored on subsequent mounts. The default is

20000 pages.

/WSQUOTA=pages

Specifies the working set quota for the NFS_CLIENT_ACP process. This process is created when the first NFS file system is mounted. The qualifier is ignored on subsequent mounts. The default is 2000 pages.

EXAMPLES

This example shows how to mount the remote file system `"/usr"` on the server named `"sunset"` on the local mount device `NFS3:`.

```
$ MULTINET NFSMOUNT SUNSET::"/usr" disk$sunset
%NFSMOUNT-I-MOUNTED, SUN::/ufs NFS mounted on _NFS3:
$
```

This example illustrates the use of `/PROCESSOR=UNIQUE`, creating four ACP processes-one for each device.

```
$ MULTINET NFSMOUNT/VMS/PROCESSOR=UNIQUE SCOOPY::USERS: SCOOPY1
$ MULTINET NFSMOUNT/VMS/PROCESSOR=UNIQUE SCOOPY::USERS2: SCOOPY2
$ MULTINET NFSMOUNT/VMS/PROCESSOR=UNIQUE SHAGGY::USERS: SHAGGY1
$ MULTINET NFSMOUNT/VMS/PROCESSOR=UNIQUE SHAGGY::USERS2: SHAGGY2
```

This example illustrates the use of `/PROCESSOR=SAME`. In this example, all access to the server named `SCOOPY` goes through one ACP process, and all access to `SHAGGY` goes through another process.

```
$ MULTINET NFSMOUNT/VMS SCOOPY::USERS: SCOOPY1
$ MULTINET NFSMOUNT/VMS/PROCESSOR=SAME=SCOOPY1 SCOOPY::USERS2: SCOOPY2
$ MULTINET NFSMOUNT/VMS SHAGGY::USERS: SHAGGY1
$ MULTINET NFSMOUNT/VMS/PROCESSOR=SAME=SHAGGY1 SHAGGY::USERS2: SHAGGY2
```

MULTINET NSLOOKUP

Performs test queries on the domain name service (DNS) system. When invoked with no parameters, MULTINET NSLOOKUP allows commands to be run interactively. Table 1-44 lists the commands that can be run in interactive mode.

Table 1-44 NSLOOKUP Commands

Command	Description
<i>name</i>	Prints information about <i>name</i> using the default server.
<i>name server</i>	Prints information about <i>name</i> using <i>server</i> .
exit	Exits NSLOOKUP.
finger [<i>user</i>]	Finger the optional <i>user</i> at the current default host.
help or ?	Prints help information.
set all	Prints the current status of all options.
set class= <i>class</i>	Sets the query class to one of these: IN, CHAOS, HESIOD, or ANY.
set [no]debug	Prints debugging information.
set [no]d2	Prints exhaustive debugging information.
set [no]defname	Appends the domain name to each query.
set [no]recurse	Asks for a recursive answer to a query.
set [no]vc	Always uses a virtual circuit.
set domain= <i>name</i>	Sets the default domain name to <i>name</i> .
set port= <i>port</i>	Sets the port number on which to send a query.
set root= <i>name</i>	Sets the root name server to <i>name</i> .
set retry= <i>n</i>	Sets the number of retries to <i>n</i> .
set srchlist= <i>name1</i> [/ <i>name2</i> /.../ <i>name6</i>]	Sets the domain to <i>name1</i> and the search list to <i>name1</i> through <i>name6</i> .
set timeout= <i>n</i>	Sets the timeout interval to <i>n</i> .
set query-type= <i>type</i> or set type= <i>type</i>	Sets the resource record (RR) type to query for. See Table 1-37.
server <i>name</i>	Sets the default server to <i>name</i> , using the current default server.

Table 1-44 NSLOOKUP Commands (Continued)

Command	Description
lserver name	Sets the default server to <i>name</i> , using the original default server.
root	Sets the current default server to the root.
ls [<i>option</i>] name [> <i>file</i>]	Lists the domain <i>name</i> , with output optionally going to <i>file</i> . <i>option</i> is one of the following: -a List fully-qualified names and aliases -h List HINFO (CPU type and operating system) -s List well-known services -d List all records -t <i>type</i> List records of the given type (such as A, CNAME, and MX)

FORMAT

MULTINET NSLOOKUP [*name*] [*nameserver*]

PARAMETERS

name

Specifies a host or domain name.

nameserver

Specifies the name server to query.

QUALIFIERS

/CLASS=recordclass

Specifies which CLASS records are asked for. Valid classes are ANY, IN, CHAOS, and HESIOD. (The default is /CLASS=IN, Internet records.)

/DEBUG

/NODEBUG (default)

Causes the resolver to print debugging information, including formatted responses.

/DEBUG2

/NODEBUG2 (default)

Causes the resolver to print formatted queries, and additional, less useful debugging information.

/DEFNAMES (default)

/NODEFNAMES

Specifies that the resolver adds this system's domain name to any name not explicitly terminated

with a period. /DEFNAMES is the default.

/DNSRCH (default)
/NODNSRCH

Specifies that the resolver searches up the domain tree from this system's name for any name not explicitly terminated with a period.

/DOMAIN=domainname

Specifies a default domain other than the domain of this host.

/IGNTC
/NOIGNTC (default)

Tells the resolver to ignore truncation in responses.

/PORT=port

Specifies a port other than the standard nameserver port of 53.

/RECURSE (default)
/NORECURSE

Requests that the name server use recursion to answer the query.

/RETRY=retrycount

Specifies the number of retries the resolver makes when querying a name server via UDP (by default, 4).

/ROOT_SERVER=rootservername

Specifies a root name server other than A.ROOT-SERVERS.NET.

/TIMEOUT=seconds

Specifies a different period to wait for responses. The default is 4 seconds.

/TYPE=recordtype

Specifies which TYPE resource records are asked for. The default is /TYPE=A (address records).

All standard DNS record types are supported. Table 1-45 gives a partial list of valid values for the /TYPE qualifier.

Table 1-45 Sample Resource Record Types for NSLOOKUP/TYPE Qualifier

Resource Record	Description	Resource Record	Description
A	Address records	MR	Mail rename domain name
ANY	Any	MX	Mail exchanger
AXFR	Zone transfer	NS	Authoritative name server

Table 1-45 Sample Resource Record Types for NSLOOKUP/TYPE Qualifier (Continued)

Resource Record	Description	Resource Record	Description
CNAME	Fully-qualified name for an alias	PTR	Domain name pointer
GID	Group ID	SOA	Start of a zone of authority
HINFO	Host information	TXT	Arbitrary text
MAILB	Mailbox for a user	UID	User ID
MB	Mailbox domain name	UINFO	Arbitrary user information
MG	Mail group member	WKS	Well-known service description
MINFO	Mailbox or mail list information		

/VC

/NOVC (default)

Specifies that the resolver uses virtual circuits instead of datagram queries.

MULTINET NSUPDATE

Performs dynamic updates to the domain name service (DNS) server. NSUPDATE can read commands from a specified file or from the terminal.

NSUPDATE can be used with the UNIX-style syntax by defining it as a foreign command:

```
$ NSUPDATE ::= $MULTINET:NSUPDATE
```

Both the UNIX-style options and the OpenVMS qualifiers are listed below.

NSUPDATE reads input records, one per line, each line contributing a resource record to an update request. All domain names used in a single update request must belong to the same DNS zone. A blank line causes the accumulated records to be formatted into a single update request and transmitted to the zone's authoritative name servers. Additional records may follow, which are formed into additional, completely independent, update requests. For the last request to be transmitted, a blank line must end the input.

Records take one of two general forms:

- *Prerequisite* records specify conditions that must be satisfied before the request will be processed.
- *Update* records specify changes to be made to the DNS database.

An update request consists of zero or more prerequisites and one or more updates. Each update request is processed atomically, that is, all prerequisites must be satisfied before all updates will be performed.

NSUPDATE understands the input record formats listed in Table 1-46

Table 1-46 NSUPDATE Commands

Command	Description
<code>prereq nxdomain <i>name</i></code>	Requires that no RR of any type exists with name <i>name</i> .
<code>prereq nxrrset <i>name</i> [<i>class</i>] <i>type</i></code>	Requires that no RR exists of the specified <i>type</i> and <i>name</i> .
<code>prereq yxdomain <i>name</i></code>	Requires that at least one RR named <i>name</i> must exist.
<code>prereq yxrrset <i>name</i> [<i>class</i>] <i>type</i> [<i>data</i>...]</code>	Requires that a RR exists of the specified <i>type</i> and <i>name</i> . If <i>data</i> is specified, it must match exactly.
<code>update add <i>name</i> <i>ttl</i> [<i>class</i>] <i>type</i> <i>data</i>...</code>	Adds a new RR with specified <i>ttl</i> , <i>type</i> , and <i>data</i> .
<code>update delete <i>name</i> [<i>class</i>] [<i>type</i> [<i>data</i>...]]</code>	Deletes RRs named <i>name</i> . If <i>type</i> (and possibly <i>data</i>) is specified, only matching records will be deleted.

FORMAT

MULTINET NSUPDATE [*filename*]

PARAMETERS

filename

Specifies a file containing NSUPDATE commands to be executed.

QUALIFIERS

-d

/DEBUG

/NODEBUG (default)

Causes the resolver to print debugging information.

-k *keydir+keyname*

/KEY=(KEYNAME=*key*[,KEYDIR=*directory*])

Specifies a TSIG key for NSUPDATE to use to sign its updates. The default value for KEYDIR is the current default directory.

Note! On Unix, the syntax is *keydir:keyname*. On OpenVMS, the colon is replaced by a plus sign (+). The *keyname* must be specified to match the key and private filenames, with periods instead of dollar signs. This may not match the domainname if DNSKEYGEN had to abbreviate it to fit into an OpenVMS file name.

-v

/VC

/NOVC (default)

Specifies that the resolver uses virtual circuits (TCP) instead of datagram (UDP) messages.

EXAMPLES

The following example illustrates the interactive use of NSUPDATE to change an IP address by deleting any existing A records for a domain name and then inserting a new one. Since no prerequisites are specified, the new record will be added even if there were no existing records to delete.

Note! The trailing blank line is required to process the request.

```
$ multinet nsupdate
> update delete test.example.com A
> update add test.example.com 3600 A 10.1.1.1
>
```

In this example, a CNAME alias is added to the database only if there are no existing A or CNAME records for the domain name.

```
$ multinet nsupdate
> prereq nxrrset www.example.com A
> prereq nxrrset www.example.com CNAME
> update add www.example.com 3600 CNAME test.example.com
>
```

MULTINET PING

Sends ICMP Echo Request packets to the specified host to measure network packet loss and latency. MULTINET PING returns the following status codes:

Status Code	Description
SS\$_NORMAL	Successful PING.
SS\$_IVBUFLEN	An invalid length was specified on the /DATA_LENGTH qualifier. The maximum value is 65468.
SS\$_NOSUCHNODE	Failed attempt to PING an unknown host.
SS\$_PROTOCOL	Remote system is not configured to support ICMP.
SS\$_NOPRIV	Access to PING denied by the system manager.
SS\$_DATA_LOST	Some PING responses were received, but some were lost; that is, a PING success rate of less than 100%.
SS\$_UNREACHABLE	No responses were received.

FORMAT

MULTINET PING *host*

PARAMETER

host

Specifies the host to ping.

QUALIFIERS

/DATA_LENGTH=number-of-bytes

Specifies the number of bytes of data to attach to ICMP Echo Request packets. If not specified, a reasonable default value is supplied. Increase the DATA_LENGTH to check for gateways that do not fragment IP packets correctly.

/DEBUG

/NODEBUG (default)

Enables socket-level debugging in the MultiNet kernel. This qualifier is usually only useful for debugging the MultiNet kernel.

/FLOOD

Indicates that MULTINET PING is used to flood the network with ICMP Echo packets. MULTINET PING /FLOOD transmits these packets 100 times per second or whenever a response

is received. Requires SYSPRV privilege.

/NUMBER_OF_PACKETS=number_of_packets_to_send

Specifies the number of ICMP Echo Responses received before terminating. If not specified, MULTINET PING runs until you press **Ctrl/C**.

/PRELOAD=number_of_packets_to_send

Specifies the number of packets sent in rapid succession before entering the normal mode of operation.

/QUIET

/NOQUIET (default)

Causes MULTINET PING to not display information when packets are received.

/RECORD_ROUTE

Displays a list of IP routers that the ICMP Echo Request packets traverse. This qualifier uses the IP record route option to display a list of IP routers that the ICMP Echo Request packet traverses. Not all implementations of IP handle this option correctly, so the use of /RECORD_ROUTE may result in a garbled response.

Note! The record route IP option is not supported correctly by 4.3 BSD-derived Internet hosts, including MultiNet. Use the MULTINET TRACEROUTE utility to find the path between two hosts.

/ROUTE (default)

/NOROUTE

Disables IP routing of ICMP packets. The default, /ROUTE, allows IP routing to get the packet to destinations separated by gateways.

/VERBOSE

/NOVERBOSE (default)

Displays extra information as ICMP packets are sent or received.

EXAMPLES

This example shows using PING to test the round-trip delay to a distant host.

```
$ MULTINET PING TRUTH.GREEN.AC.N
PING TRUTH.GREEN.AC.NZ (130.217.64.3) : 56 data bytes
64 bytes from 130.217.64.3: icmp_seq=1 time=670 ms
64 bytes from 130.217.64.3: icmp_seq=2 time=670 ms
64 bytes from 130.217.64.3: icmp_seq=3 time=670 ms
64 bytes from 130.217.64.3: icmp_seq=4 time=650 ms <Ctrl/C>
----TRUTH.GREEN.AC.NZ  PING Statistics----
4 packets transmitted, 4 packets received, 0% packet loss
round trip (ms)    min/avg/max = 650/663/670
```

MULTINET RDATE

Uses the TCP TIME service to query a remote system for the current time and sets the clock on the local system to that time.

FORMAT

MULTINET RDATE *host*

PARAMETER

host

Specifies the name or Internet address of the host to query.

QUALIFIERS

/DELTA

/NODELTA (default)

Displays the time difference between the local and remote hosts, expressed in standard VMS time format.

/LOG

/NOLOG

Displays a message indicating that the time has been set. The /NOLOG qualifier suppresses this message.

/SET

/NOSET

RDATE usually sets the VMS time; /NOSET retrieves, but does not set, the current time.

MULTINET RMTALLOC

Provides local access to a remote tape or CD-ROM device on the specified remote host. RMTALLOC does not actually read from or write to the magnetic tape, or read from the CD-ROM; other programs supplied with the VMS Operating System provide this support. Optionally, RMTALLOC can associate a logical name with the device.

FORMAT

MULTINET RMTALLOC *host.domain[:][["]device-name["]] [logical-name[:]]*

PARAMETERS

host.domain

Specifies the remote host name on which the tape or CD-ROM device is allocated (the domain name-either just the domain name or the fully qualified domain name-of the remote host).

device-name

Specifies an optional device name entered with single or double colons. If the device name contains special characters, such as a UNIX-style device name (/dev/rst8), enclose the name in double quotes ("/dev/rst8").

logical-name

Specifies the name associated with the device. Use a name you created or one designated by your system manager. The string is from 1 to 255 alphanumeric characters. If the string contains spaces, enclose the string in single quotes. (Do not use trailing colons.) The logical name you specify becomes a process name, with the device name as the equivalence name. The logical name remains defined until it is explicitly deleted or until your process terminates.

QUALIFIERS

/CD

/NOCD (default)

Specifies that the remote device is a CD-ROM rather than a tape device. When /CD is specified, the local device takes the RCDxxx: name. When /NOCD is specified, the local device takes the RMTxxx: name. The remote system is tested to ensure that the specified device type exists; if not, an error displays and RMTALLOC fails.

Note! /CD cannot be used with either the /SEMANTICS or /WRITE qualifiers.

/LOG (default)

/NOLOG

Displays a message indicating the name of the local device allocated, and the official host name of the remote host and device name.

/PASSWORD[=password]

Specifies the password to use to access the remote host. You may optionally specify the password as the qualifier value (which is not recommended). Specifying /PASSWORD without the value causes the password to be prompted for and read without echoing it (if the current input device supports it). If present, this qualifier causes RMTALLOC to use the REXEC server on the remote host rather than the RSHELL server.

[blocksize=blocksize]
[comment="comment"]
[density=density]

/SEMANTICS=[([label="label"])]

[[no]mount]
[[no]rewind]
[[no]unload]

Specifies attributes for a magnetic tape device. Do not use with the /CD qualifier. Enter keywords separated by commas and enclosed in parentheses. These values pass information to the system operator at the remote system. For example, the values in LABEL and COMMENT display on the remote system console and request that the tape name indicated by LABEL be mounted.

Attribute	Description
BLOCKSIZE	Specifies the remote tape blocksize.
COMMENT	<p>Specified as a string enclosed in double quotes; the information is displayed in the remote OPCOM message, either appended to or replacing the default text, depending on whether the resulting length is less than the maximum of 78 characters. Supplying the COMMENT value is the only way you can send a tape-specific message to the remote operator.</p> <p>The OPCOM message from the DCL MOUNT/COMMENT command is not passed to the remote RMT server; this message is only sent to OPCOM for a local operation. The default RMTALLOC command causes the remote tape to be mounted foreign, causing an OPCOM message to be generated if the tape drive is offline.</p> <p>The default RMTALLOC command is equivalent to the RMTALLOC /SEMANTICS=MOUNT command, which causes RMTALLOC to not complete until a tape has been physically loaded and the drive is online. Therefore, use the COMMENT value to ensure that the operator is informed of your request. Override the RMTALLOC default with the RMTALLOC /SEMANTICS=NOMOUNT command, which allocates the tape unit but does not wait for completion.</p> <p>Without the comment, RMTALLOC provides user, node, and device information, as shown in this example:</p> <pre> %%% OPCOM 25-MAR-2002 11:24:35.46 %%% FROM NODE WHORFIN AT 25-MAR-2002 11:24:35.44 REQUEST 87, FROM USER HOLMES ON WHORFIN Please mount device _WHORFIN\$ mka500 : RMT tape service request from WHORFIN.FLOWERS.COM </pre>
DENSITY	Specifies the density in bits per inch (BPI).
LABEL	Indicates the name by which the tape is known to the remote system. This could be your name, a site-specific numbering scheme, and so on.
[NO]MOUNT	Indicates whether the tape needs to be mounted. This option does not replace the MOUNT command; it only means that RMTALLOC should continue until the remote tape is mounted.
[NO]REWIND	Indicates whether the tape must be rewound before or after use.
[NO]UNLOAD	Indicates whether the tape must be unloaded from the drive after use.

Note! The remote tape drive must be able to write variable length blocks to permit VMS BACKUP to work correctly. Sun QIC tapes cannot do this and do not work with the VMS BACKUP utility.

The RMTALLOC /SEMANTICS=NOMOUNT command does not work correctly with multivolume BACKUP save sets.

When using RMTALLOC to allocate a remote VMS TMSCP tape drive, the VMS COPY utility cannot copy files from a tape if the TMSCP tape drive is served from a different node than the one specified in the RMTALLOC command.

/TRUNCATE_USERNAME

/NOTRUNCATE_USERNAME (default)

Truncates VMS user names to eight characters or less. Under the UNIX Operating System, the remote user name has a maximum of eight characters. If a longer user name is supplied to such a system, a "remuser too long" error results and RMTALLOC fails.

/UNIX_SERVER=value

Specifies that RMTALLOC provide special handling for systems with problematic tape devices. Accepted values are:

Value	Description
BROKEN	Enables one OpenVMS BACKUP save set to be written to a remote UNIX tape. Use this value for SunOS 4.1 and SunOS 4.1.2. May also be useful on other UNIX-incompatible tapes and servers.
UNIX	Enables full OpenVMS tape functionality on an ULTRIX tape drive.

/USERNAME=remote-username

Specifies the remote user name to which you want to log in. If not specified, the default is the user name associated with your process.

/VMS_ATTRIBUTES (default)

/NOVMS_ATTRIBUTES

Verifies whether the remote RMT server is also running MultiNet. If it is, RMT uses an improved RMT protocol to transfer VMS device attributes and I/O completion status values between your system and the remote host. Because this negotiation is compatible with UNIX Operating System implementations of RMT (including BSD and SunOS), it is enabled by default, but may be disabled if compatibility problems arise.

/WRITE (default for mag tapes)

/NOWRITE (default for CD-ROMs)

Specifies that the tape is not write-protected; if /NOWRITE is specified, the tape is write-protected. /WRITE cannot be specified with /CD.

EXAMPLES

This example illustrates the use of the VMS TAR utility. (VMS TAR is a public domain program available from CETS.) First the tape is allocated with RMTALLOC, then the drive is mounted. Next, a file is written to the tape, the tape contents are listed, and the file is extracted back from the tape. Finally, the tape is dismounted and deallocated.

```
$ RMTALLOC CONE.FLOWERS.COM::MUA0: MYTAPE
%RMT-I-ALLOC, _MYSYS$RMT1: allocated (CONE.FLOWERS.COM::MUA0:)

$ MOUNT /FOREIGN /RECORD_SIZE=512 /BLOCK_SIZE=10240 MYTAPE
%MOUNT-I-MOUNTED, MYTAPE mounted on _MYSYS$RMT1:

$ TAR /ARCHIVE=MYTAPE WRITE AFILE.TXT
%TAR-S-WRITTEN, written USERS:[ME]AFILE.TXT;1 (13495 bytes)
%TAR-S-TOTWRITE, total of 1 file written

$ TAR LIST /ARCHIVE=MYTAPE
Listing of archive _MYSYS$RMT2:
-rw----- 0/ 0 13495 24 Apr 2002 14:31 afile.txt
Total of 1 files listed, 1 files in archive.

$ TAR /ARCHIVE=MYTAPE EXTRACT AFILE.TXT
%TAR-S-TOTCREAT, total of 0 files created, 1 file scanned

$ DISMOUNT _MYSYS$RMT1:

$ DEALLOCATE _MYSYS$RMT1:
```

This example illustrates how to allocate access to a UNIX tape.

```
$ RMTALLOC FOO::"/dev/rst42" UNIXTAPE
%RMT-I-ALLOC, _MIURA$RMT7: allocated (FOO.BAR.COM::/dev/rst8)
$
```

This example allocates remote UNIX operating system tape device /dev/rst42 on host FOO.BAR.COM and associates UNIXTAPE with the _MIURA\$RMT7 local pseudo-device.

```
$ RMTALLOC/CD/NOWRITE CONTROL::DISK$CD: -
_$ DISK$CONTROL_CD/USER=SYSTEM
%RMT-I-ALLOC _GRUB$RCD3: allocated (CONTROL.FLOWERS.COM::DISK$CD:)

$ MOUNT/OVER=ID DISK$CONTROL_CD:
%MOUNT-I-WRITELOCK, volume is write locked
%MOUNT-I-MOUNTED, VMS055LST1 mounted on _GRUB$RCD3:

$ DISMOUNT DISK$CONTROL_CD:

$ DEALLOCATE DISK$CONTROL_CD
$
```

This example allocates a CD-ROM for access between two VMS systems. The drive is allocated, mounted, dismounted, and deallocated.

The next example allocates a CD-ROM drive on a remote machine running UNIX.

```
$ RMTALLOC /CD/NOWRITE SYS1:: DISK$SYS1_CD/USER=ROOT
%RMT-I-ALLOC, _GRUB$RCD3: allocated (SYS1.FLOWERS.COM::/dev/rsr0)

$ MOUNT /OVER=ID DISK$MEL_CD:
%MOUNT-I-WRITELOCK, volume is write locked
%MOUNT-I-MOUNTED, VMS055LST2 mounted on _GRUB$RCD3:

$ DISMOUNT DISK$MEL_CD:

$ DEALLOCATE DISK$MEL_CD:
$
```

This example allocates a UNIX CD drive. The device name defaults to /dev/rsr0. You could specify another device name, using the same example with the SYS1::"/dev/rsr42" value in the RMTALLOC command. After the device is allocated in the previous example, it is mounted, dismounted, and finally deallocated.

The next example allocates a tape and then invokes BACKUP to write to it.

```
$ REPLY /ENABLE

$ RMTALLOC COMMENT="PLEASE MOUNT TAPE #A1234" -
_$ WHORFIN::MKA500: TAPE
%%%%%%%% OPCOM 25-MAR-2002 11:24:35.46 %%%%%%%%%
(FROM NODE WHORFIN AT 25-MAR-2002 11:24:35.44)
REQUEST 87, FROM USER HOLMES ON WHORFIN
Please mount device _WHORFIN$mka500:
RMT tape service request from WHORFIN.FLOWERS.COM
Please mount tape #A1234
%%%%%%%% OPCOM 25-MAR-2002 11:25:29.12 %%%%%%%%%
(FROM NODE HOLMES
25-MAR-2002 11:25:29.12)
REQUEST 87 WAS SATISFIED.
%RMT-I-ALLOC, _HOLMES$RMT2: ALLOCATED (WHORFIN.FLOWERS.COM::MKA500:)

$ INIT TAPE: FOO

$ BACKUP/LOG/INGORE=LABEL/VERIFY USERS:[ATMA.TEST]*.EXE;0 -
TAPE:EXES.BCK/SAVE
%MOUNT-I-MOUNTED, FOO MOUNTED ON _HOLMES$RMT2:
. .

$ BACKUP/LOG/IGNORE=LABEL/VERIFY USERS:[ATMA.TEST]*.H;0 -
TAPE:H.BCK/SAVE
. .
```

```
$ BACKUP/LOG/INGORE=LABEL/VERIFY USERS:[ATMA.TEST]*.C;0 -  
TAPE:C.BCK/SAVE  
. .
```

```
$ DISMOUNT/NOUNLOAD TAPE:
```

```
$ MOUNT/OVER=ID TAPE:  
%MOUNT-I-MOUNTED, FOO MOUNTED ON _HOLMES$RMT2:
```

```
$ DIR TAPE:  
DIRECTORY _HOLMES$RMT2:[ ]  
EXES.BCK;1      H.BCK;1      C.BCK;1  
TOTAL OF  3 FILES.
```

```
$ DISMOUNT TAPE:
```

```
$ DEALL TAPE:  
$
```

This example allocates access to a tape, then writes to it.

When issuing a RMTALLOC to a remote MultiNet system, the remote tape drive must be online with the tape physically loaded. Otherwise, RMTALLOC fails with the error, "%SYSTEM-F-MEDOFL, medium is offline."

You can override this default with the /SEMANTICS=MOUNT qualifier. RMTALLOC does not complete until a tape has physically been loaded and the tape drive is online. Use the /SEMANTICS=COMMENT keyword to specify a mount message to send to the operator via OPCOM.

MULTINET RWALL

Uses Remote Procedure Calls (RPCs) to send a network broadcast message to all users on the specified host. If you specify the host as an asterisk (*), the message is broadcast to all hosts on Ethernets to which the local host is attached.

FORMAT

MULTINET RWALL [*qualifier1*] [*qualifier2* . . .] [*"message_text"*]

RESTRICTION

RWALL messages are only received on hosts that support RWALL service.

PARAMETER

message_text

Contains the message to broadcast.

QUALIFIERS

/HEADER[="header_text"]

/NOHEADER

Adds header text to the specified message. If you use the /NOHEADER qualifier, RWALL does not preface any header text to the specified message. By default, the header is prefaced with "Broadcast message from username@hostname:", although you may specify any header text as the value of this qualifier.

/HOST=[hostname]

Specifies the host on which the message is displayed. The default is /HOST=LOCALHOST, which prints the message on the host from which the RWALL command was invoked. If you specify the qualifier as /HOST=*, the network broadcast displays on all directly reachable hosts on all connected networks that support broadcasting. /HOST=* is most appropriate for network-wide system shutdown messages.

EXAMPLE

This example shows how to broadcast a shutdown message to users on the local host.

```
$ MULTINET MULTINET RWALL "Node ROMEO is shutting down"
RWALL MESSAGE:
Broadcast message from HOLMES@ROMEO: Node ROMEO is shutting down
```

MULTINET SET /ARP

Modifies Address Resolution Protocol (ARP) tables. These tables are normally modified dynamically by the ARP protocol. Use with MULTINET SHOW /ARP to view the contents of the ARP table.

QUALIFIERS

**/ADD=(PROTOCOL=protocol,HOST_ADDRESS=host_addr,
ETHER_ADDRESS=ether_addr)**

Adds a specified host-to-Ethernet address translation to the ARP tables. The PROTOCOL specification identifies which protocol (IP, for example) is being described. The HOST_ADDRESS specification gives the host address in IP form. The ETHER_ADDRESS specification gives the hardware Ethernet address in the form "aa:bb:cc:dd:ee:ff", where "aa" through "ff" are specified in hexadecimal. If not specified, the default is PROTOCOL=IP.

/COMMUNITY_NAME=string

Overrides the default community string (private) for remote SNMP SET requests. The /SNMP_HOST qualifier must be present if the /COMMUNITY_NAME qualifier is specified.

/DELETE=host

Deletes the specified host-to-Ethernet address translation from the ARP tables.

/FLUSH

Flushes the current ARP table. By default only temporary entries are flushed. If the qualifier /PERMANENT is specified, all entries are flushed.

/PERMANENT

/TEMPORARY (default)

Indicates that the translation to be added is kept (or deleted) permanently (used with the /ADD or /FLUSH qualifiers). The default (/TEMPORARY) indicates that this entry is considered for normal ARP table purging of old entries.

/PROXY

Used with the /ADD qualifier, indicates that the translation to the local host's Ethernet address is published on behalf of another host.

/PUBLISH

Indicates that the translation to be added is published on behalf of another host (that is, this host should answer with the specified translation on behalf of the other host). This qualifier is used with the /ADD qualifier.

/SNMP_HOST=hostname

Specifies the host affected by the MULTINET SET /ARP command. The SNMP agent on the remote host must support read-write access to elements of the MIB-II variable ipNetToMedia.

EXAMPLES

This example displays the contents of the ARP table. Note: if the host name and IP address are longer than the "Host Network Address" field, they are truncated to fit.

```
$ MULTINET SHOW /ARP /SYMBOLIC=NAMESEVER
```

Multinet ARP table:

Host Network Address	Ethernet Address	Arp Flags
-----	-----	-----
FSGATE.CC.FSTONE.COM (IP 128.0.33.123	AA:00:04:00:79:4C	Temporary
EXPLORER.ME.FSTONE.COM (IP128.0.41.1	08:00:11:00:90:B0	Temporary
GOOFY.CC.FSTONE.COM (IP 128.0.83.122)	08:00:20:01:27:6D	Temporary
BEGWS2.BEG.FSTONE.COM (IP 128.0.30.23	AA:00:04:00:65:4C	Temporary
ARPAGATEWAY.FSTONE.COM (IP 128.0.11.2	AA:00:04:00:0F:4C	Temporary
PORTAL1.CC.FSTONE.COM (IP 128.0.19.10	08:00:4C:00:23:CE	Temporary
WILMA.CC.FSTONE.COM (IP 128.0.7.125)	AA:00:04:00:64:4C	Temporary
FS4.CC.FSTONE.COM (IP 128.0.19.251)	AA:00:04:00:12:4C	Temporary

This example is often used to solve a problem that occurs in environments with a mixture of UNIX 4.2 BSD and 4.3 BSD systems. 4.2 BSD systems use zero-filled (nn.mm.0.0) IP broadcast addresses, while 4.3 BSD systems use ones-filled (nn.mm.255.255) broadcast addresses. To prevent 4.2 BSD systems from creating Ethernet "broadcast storms" when they issue ARP requests for the 4.3 BSD broadcast address, the above command publishes an ARP translation for the ones-filled broadcast address.

```
$ MULTINET SET /ARP /ADD=(HOST=128.0.255.255,-
                        PROTOCOL=IP, -
                        ETHER=0:0:D:E:A:D) /PUBLISH
```

```
$
```

This example flushes all temporary ARP table entries.

```
$ MULTINET SET /ARP /FLUSH
```

MULTINET SET /DECNET

Configures the DECnet TCPA x : devices for running DECnet-over-UDP circuits.

QUALIFIERS

/BUFFERS=buffercount

Specifies the number of buffers the driver preallocates for this device (by default, 6).

/CLOSE

Shuts down and deletes a socket created with the **socket()** routine. After issuing a CLOSE command, the socket cannot be used again until the MULTINET SET/DECNET command is reissued.

/CONNECT

Issues a **connect()** call to bind the remote address of the socket to the address specified in /REMOTE_ADDRESS.

/DEVICE=device

Specifies the DECnet device name (by default, TCPA0:).

/FILTER_OUT_OF_ORDER=AUTOMATIC (default)

/FILTER_OUT_OF_ORDER=OFF

/FILTER_OUT_OF_ORDER=ON

Controls the handling of out-of-order DECnet packets arriving via IP. Prior to VMS V4.7, DECnet could not handle packets arriving out-of-order and would drop the line if it received them. If you have any VMS V4.6 or earlier systems in your DECnet network with which you are communicating, you must use the /FILTER_OUT_OF_ORDER=ON qualifier. The default action, /FILTER_OUT_OF_ORDER=AUTOMATIC, selects the correct filtering based on the VMS version of the current system only.

/LOGDATA

Specifies that **send()** and **recv()** log a sample of the data passed through them to OPCOM. Use this qualifier only for debugging network problems.

/LOGERRORS

Specifies that **send()** and **recv()** errors are logged to OPCOM. The default is to log all errors except these.

/PORT=UDP-port-number

Specifies the UDP port number to use for communication (by default, 700).

/REMOTE_ADDRESS=ip-address

Specifies the peer's IP address.

/TCP=mode

/TCP=CONNECT

/TCP=LISTEN

Specifies that DECnet is encapsulated in TCP instead of UDP. This mode is not supported by the normal configuration utility, but is of use over high-loss lines. LISTEN specifies that this end of the connection listens on the specified port; CONNECT specifies that this end attempts to connect to the listener on the specified port.

MULTINET SET /INTERFACE

Sets parameters for the specified network device. This command is invoked automatically by the network startup command file generated by the NET-CONFIG utility.

FORMAT

MULTINET SET/INTERFACE *interface*

PARAMETER

interface

Specifies the name of the interface to change; for example, "se0".

QUALIFIERS

/ADDRESS=network_address

Specifies a network address to assign to the network interface. The address format is dependent on the protocol specified with the /PROTOCOL specifier:

IP-address is of the form AA.BB.CC.DD

IPX-address is a hexadecimal value

/ARP (default)

/NOARP

/NOARP disables the Address Resolution Protocol on the specified interface (supported only on Ethernet interfaces).

/COMMON_LINK=line-ids

The /COMMON_LINK qualifier works for systems that have multiple interfaces on a common Ethernet, FDDI, or Token Ring cable. The system manager configures this support using the following qualifier:

```
$ MULTINET SET /INTERFACE xxx/COMMON_LINK=(yyy[ ,zzz...])
```

xxx is the pseudo device (see the *MultiNet for Open VMS Administrator's Guide* for an example on how to set up a pseudo device) to which the actual IP address of the machine is tied. yyy and zzz are device names like se0, se1, and se2. With this qualifier, MultiNet links the interfaces together. A performance benefit of this linking occurs if data is to be transmitted on an interface that happens to be busy, MultiNet assigns the data to the least busy linked interface for transmission.

This linking also provides a level of redundancy. If a linked interface is shut down using MULTINET SET/INTERFACE/DOWN or if a fatal error is detected with the interface and an automatic restart can not be attempted, then any routing table entries or pseudo devices associated with the shut down interface will be failed over to one of the common link interfaces.

Restrictions:

- The joined interfaces must be connected to the same cable.
- The joined interfaces must have the same MTU.

/COMMUNITY_NAME=string

Overrides the default community string (private) for remote SNMP SET requests. The /SNMP_HOST qualifier must be present if the /COMMUNITY_NAME qualifier is specified.

/D1**/NOD1 (default)**

Enables or disables the device-dependent IFF_D1 flag.

/D2**/NOD2 (default)**

Enables or disables the device-dependent IFF_D2 flag.

/D3**/NOD3 (default)**

Enables or disables the device-dependent IFF_D3 flag.

/DEBUG**/NODEBUG (default)**

Enables interface-specific debugging. Some interfaces have debugging code and send debugging information to the users with OPCOM OPERATOR messages enabled.

/DECNET_ETHERNET_ADDRESS (default)**/NODECNET_ETHERNET_ADDRESS**

Initializes a DECnet shared Ethernet interface to determine what Ethernet address to use. If other protocols are currently using the device, the Ethernet address cannot be changed and this qualifier is ignored.

The default behavior, /DECNET_ETHERNET_ADDRESS, is used by MULTINET SET /INTERFACE to look at the SCSSYSTEMID SYSGEN parameter and set the Ethernet address to match. If SCSSYSTEMID is not set, the address on the Ethernet card's PROM is used.

If /NODECNET_ETHERNET_ADDRESS is specified, MultiNet uses the PROM address.

/DOWN

Marks the network interface as not UP and packets are no longer accepted or transmitted. See /UP for more information.

/DYNAMIC**/NODYNAMIC (default)**

Reverts the terminal line to a normal VMS terminal line if a modem hangup occurs. Use /DYNAMIC to create dynamic-dialup SLIP links with the /LINK_LEVEL=SLIP qualifier. When creating a dynamic SLIP link, CMKRNL, LOG_IO, and SYSPRV privileges are required.

/FFI_BUFFERS=number_of_buffers

Initializes a shared VMS Ethernet or FDDI interface, and specifies the number of packet buffers to allocate to each protocol port of the VMS device driver (by default, 4).

/FILTER**/NOFILTER (default)**

Associates a packet filter list with particular network interfaces. You can also use /FILTER=FILE.DAT to associate a packet filter list with specific network interfaces.

/HARDWARE_DEVICE=primary_interface

Specifies the name of the real interface for a secondary IP address device, and connects the interface to the specified primary interface.

/IP_BROADCAST=ip_address

Specifies a non-standard IP broadcast address. The default IP broadcast address has all bits in the host part of an IP address set to 1 (the standard format under 4.3 BSD). Some sites may still use the 4.2 BSD standard of IP broadcasts with the host part of an IP address set to 0.

/IP_SUBNET_MASK=ip_address

Specifies the network portion of the interface IP address. ip_address is an IP address in which each bit corresponding to a bit in the network portion is set to 1. All interfaces on the same subnet must have the same subnet mask.

By default, MultiNet uses the subnet mask implied by the interface's IP address. Do not use the default subnet mask if your site has subnets. For example, the default subnet mask of an interface with the address 161.44.128.15 is 255.255.0.0. (255.255.255.0 would be a suitable subnet mask if that interface is on a subnet, and there are fewer than 256 subnets, and the total number of hosts is less than 256.)

[802]

[ethernet]

[extended_8022]

[ppp]

/LINK_LEVEL=(*[proteon]***)**

[slip]

[standard_8022]

[raw_8023]

Specifies the type of device being initialized. Use /LINK_LEVEL with the /VMS_DEVICE qualifier. This qualifier supersedes the former /SLIP_DEVICE and /PROTEON_DEVICE qualifiers.

- Specify 802 or STANDARD_8022 for IEEE 802.2 encapsulation.
- Specify EXTENDED_8022 for IEEE 802.2 with SNAP (System Network Access Protocol) extensions.
- Specify PPP for Point-to-Point Protocol devices.

- Specify SLIP for Serial Line Internet Protocol (SLIP) devices.
- Specify RAW_8023 for 802.3 encapsulation.
- Specify ETHERNET for ETHERNET_II encapsulation.

/LOCAL=node_name

Specifies the name of the local node on this side of an IP interface; may be used with DECnet and PSI links.

/MTU=mtu

Specifies the Maximum Transmission Units-the size of IP packets over a given interface. Not all devices support the use of /MTU, and there may be additional, device-dependent restrictions dictating when it can be used.

/MULTICAST=ALL

Enables reception of all multicast packets. Use this qualifier only for OpenVMS VAX V5.5-2 and later. Reception is enabled automatically in OpenVMS VAX V6.1 and OpenVMS AXP versions.

/PEER=peer_name

Specifies the name of the node on the other side of an IP interface; used with DECnet and PSI links.

/POINT_TO_POINT_DESTINATION=ip_address

Specifies the IP address of the node on the other side of a point-to-point interface.

/PPP_NOICMP

Prevents ICMP packets from being passed to IP via the PPP interface.

/PPP_OPTIONS=options_list

Specifies values for the PPP options included in a comma-separated option_list. The following options may be enabled:

ACCM=mark	MRU=size
AUTHENTICATION=method	NOICMP
COMPRESS_PROTOCOL	TCP_COMPRESSION
COMPRESS_ADDRESS_AND_CONTROL	TERMINATION_RETRIES=count
CONFIGURATION_RETRIES=count	TIMEOUT=seconds
IDLE=seconds	

/PROTOCOL=protocol_name

Specifies the protocol to which the /ADDRESS qualifier refers (by default, IP).

/RARP**/NORARP (default)**

Initializes the VMS Ethernet device to receive RARP packets. The /RARP qualifier is used with the /VMS_DEVICE qualifier. The RARP packet type is disabled by default and must be enabled to use the RARP service on VMS Ethernet devices.

/SNMP_HOST

Specifies the host affected by the MULTINET SET /INTERFACE command. The SNMP agent on the remote host must support read-write access to the MIB-II variable ifAdminStatus.

/SNMP_HOST can only be used with the /UP or /DOWN qualifiers.

The device specified with the /SNMP_HOST qualifier may be either the full text string of the remote interface name or the numeric index of the interface to be set. You can display a list of remote interface names with the MULTINET SHOW/INTERFACE/SNMP_HOST command.

/TRAILERS**/NOTRAILERS (default)**

Enables IP trailer encapsulation for the specified interface (only supported on Ethernet and FDDI interfaces). If trailers are enabled, the use of IP trailer encapsulation is negotiated between hosts as a byproduct of IP-to-Ethernet address resolution using Address Resolution Protocol (ARP). On a Compaq Computer Ethernet controller, /TRAILERS must be used with /VMS to initialize the trailer protocol ports.

/UP (default)**/DOWN**

/UP marks the network interface as "up" and ready to accept or transmit packets. /DOWN marks the network interface "down" and packets are no longer accepted or transmitted.

/VMS_DEVICE=[vms_device]

Initializes an interface that has an associated VMS device, telling the MultiNet kernel which VMS device to associate with the IP device. If /VMS_DEVICE is used with /DOWN, the specified VMS device is disconnected from the IP device and made available to other VMS applications.

EXAMPLES

This example disables the se0 interface.

```
$ MULTINET SET/INTERFACE se0 /DOWN
```

This example enables the se0 interface with the address 192.0.0.1.

```
$ MULTINET SET/INTERFACE se0 /UP/ADDRESS=192.0.0.1
```

This example enables a dynamic SLIP line.

```
$ MULTINET SET/INTERFACE SL1 /DYNAMIC/LINK_LEVEL=SLIP/VMS_DEVICE
```

Enter the following command at MultiNet startup:

```
$ MULTINET SET/INTERFACE PD0/COMMON_LINK=(SE0,SE1)
```

The PD0 has the real IP address, the SE n devices have something else (like 10. $n.n.n$).

MULTINET SET /ROUTE

Specifies static IP routing, including the default route. This command is invoked automatically by the network startup command file generated by the Network Configuration Utility (NET-CONFIG). Before making changes with SET /ROUTE, use MULTINET SHOW /ROUTE to view the routing information.

QUALIFIERS

/ADD=(DESTINATION=ip-address, GATEWAY=ip-address [, INTERFACE])

Adds a static IP route to the MultiNet kernel routing tables.

- The DESTINATION specification gives the NETWORK or HOST for which the routing information is valid.
- The GATEWAY specification gives the next hop for the packet to take on its way to the DESTINATION.
- The optional INTERFACE keyword forces the routing to be for a locally connected interface, and is normally not used.

/COMMUNITY_NAME=string

Overrides the default community string (private) for remote SNMP SET requests. The /SNMP_HOST qualifier must be present if the /COMMUNITY_NAME qualifier is specified.

/DELETE=(DESTINATION=ip-address, GATEWAY=ip-address [, INTERFACE])

Deletes an IP route from the MultiNet kernel routing tables.

- The DESTINATION specification gives the NETWORK or HOST for which the routing information is valid.
- The GATEWAY specification gives the next hop for the packet to take on its way to the DESTINATION.
- The optional INTERFACE keyword forces the routing to be for a locally connected interface, and is normally not used.

/FLUSH

Deletes all IP routes in the MultiNet kernel.

/FORCE_HOST

Interprets the DESTINATION as a HOST address when used with the /ADD or the /DELETE qualifiers.

/FORCE_NETWORK

Interprets the DESTINATION as a NETWORK address when used with the /ADD or the /DELETE qualifiers.

/NETWORK_IMAGE=file-spec

Specifies the network image associated with the running MultiNet kernel. This is used to read IP

routing information in the MultiNet kernel. If not specified, the image currently loaded is used.

/SNMP_HOST=hostname

Specifies an IP host. The SNMP agent on the remote host must support read-write access to elements of the MIB-II variable ipRouteTable.

EXAMPLES

This example displays the current state of the MultiNet routing tables. /NOSYMBOLIC forces MULTINET SHOW/ROUTE to display the information numerically.

```
$ MULTINET SHOW /ROUTE /NOSYMBOLIC
MultiNet IP Routing tables:
Destination    Gateway      Flags        Refcnt      Use      Interface
-----
127.0.0.1      127.0.0.1    Up,Host      2           2529     lo0
192.0.0.1      192.0.0.2    Up,Host      3           10521    sl0
0.0.0          192.0.0.1    Up,Gateway   3           6105     sl0
192.0.0.64     192.0.0.65   Up           2           2372     se0
```

This example deletes the default route to FLOWERS.COM.

```
$ MULTINET SET/ROUTE/DELETE=(DEST=DEFAULT,GATE=192.0.0.1)
Delete Route DEFAULT, Gateway FLOWERS.COM
$
```

MULTINET SET /TIMEZONE

Specifies the local timezone name that was either previously compiled into MultiNet or is a name from a selected timezone in the timezone database files.

FORMAT

MULTINET SET /TIMEZONE *localzone*

PARAMETER

localzone

The name of the local timezone; for example, "PST."

QUALIFIERS

/LOG

/NOLOG (default)

Displays a list of the timezones that are loaded, and a list of the compiled-in zones that were selected but not loaded because they were compiled in.

/SELECT=(rule1 [,rule2 [...]])

Specifies a list of countries or timezones to load. Specifying a country loads all timezones in that country.

/FILES=(file1 [,file2 [...]])

Specifies a list of files from which to load the timezone data. The default is MULTINET:TIMEZONES.DAT. Locally-written rules are normally added to MULTINET:TIMEZONES.LOCAL.

EXAMPLES

This example sets the local timezone to PST.

```
$ MULTINET SET /TIMEZONE PST
```

This example sets the local timezone to MST and loads Arizona timezone rules.

```
$ MULTINET SET /TIMEZONE MST/SELECT="US/ARIZONA"
```

MULTINET SHOW

Displays MultiNet network information.

FORMAT

MULTINET SHOW

QUALIFIERS

/ALL

Displays information provided by all other MULTINET SHOW qualifiers.

/ARP

Displays the Address Resolution Protocol (ARP) tables.

/BUFFERS

Displays MultiNet kernel memory usage statistics.

/COMMUNITY_NAME=community

Overrides the default community string (public) for remote SNMP requests. The /SNMP_HOST qualifier must be present if the /COMMUNITY_NAME qualifier is specified. A value must be passed to this qualifier.

/CONFIGURATION

Displays network interface configuration information.

[all,]

[pid,]

/CONNECTIONS[=([process_names])]

[nokernel]

Displays network connections.

- If you specify MULTINET SHOW with no qualifiers, /CONNECTIONS is the default.
- If you specify the ALL keyword, sockets associated with active listeners also display.
- If you specify the PID keyword, the process ID (PID) displays.
- If you specify the PROCESS_NAMES keyword, the name of the process that owns each socket displays. Sockets not associated with a process (for example, an inbound TELNET session) display with a process name of kernel.
- If you specify PID or PROCESS_NAMES and the NOKERNEL keyword, connections not associated with processes do not display.

Warning! Line information is truncated if the display width is too small. As a consequence, IP addresses may appear incomplete. To display more complete information, increase the display width with the SET TERM /WIDTH=[value] or MULTINET SHOW /CONNECTIONS/

WIDTH=[value] at the command prompt.

/CONTINUOUS

Updates the display continuously with information about the network by using the VMS Screen Management Graphics (SMG) library routines. If used with more than one other qualifier, MULTINET SHOW cycles between the different displays.

/FULL

Displays more information about a queue. Use /FULL only with /QUEUE. (See /QUEUE for more information.)

/HOSTS

Displays the MultiNet kernel IMP tables. Use this command only with systems connected to ARPANET/MILNET PSNs.

/INTERFACE

Displays information about a specific interface. Use the MULTINET SHOW /STATISTICS command to display the available interfaces, then use SHOW /INTERFACE to display additional information on each interface.

/IP

Shows network connections. (/IP is the same as /CONNECTION.)

/MIB_VAR=mibIIvalue

Displays the value of SNMP MIB variables; used with the /SNMP_HOST qualifier. This value can be any MIB II variable described in RFC-1213.

[all,]

[multinet,]

/LICENSE[(*[nfs_server,]*)]

[nfs_client]

Displays the status of MultiNet software product licenses. Without a keyword, this qualifier displays license information including the authorization for MultiNet products. The ALL keyword is the default. All other values display license status for the specified product.

[all,]

/NFSMOUNT[(*[directory,]*)]

[exports]

Indicates which hosts are mounted on your system, and what mount points are exported by the server.

- ALL displays all remote mounts.
- DIRECTORY displays directories that have been remotely mounted by clients.
- EXPORTS displays a list of exported file systems.

Use /NFSMOUNT with /REMOTE to display information about a remote host.

/OUTPUT=file_spec

Specifies a filename to which the command output is written. The default is SYS\$OUTPUT.

```

        [ all, ]
        [ internet, ]
        [ ip, ]
        [ ipx, ]
/PROTOCOLS=( [ netware, ] )
        [ ns, ]
        [ spx, ]
        [ tcp ]

```

Specifies the protocols about which information is displayed. The default, /PROTOCOLS=ALL, displays information about all active protocols. Use /PROTOCOLS with other qualifiers. The quantity of information displayed varies by queue hardware; for example, the UNIX operating system shows more than just queues handled by other independent vendor's queue controllers.

```

        [ /full ]
/QUEUE=queue_name [ /nofull (default) ]

```

Displays the contents of the specified local VMS and corresponding remote LPD protocol queues. Use the TCP LPD service to access the contents of the remote queue for display. If /FULL is specified, the queue is displayed in long form. If the remote system is also running MultiNet, the long form is identical to the short form. MultiNet queues configured with the STREAM protocol cannot be displayed with this command.

/REMOTE_HOST=host

Displays network status and configuration information about a remote host by using the NETSTAT service. The host specification can be either a host name or address. The remote host must support the NETSTAT service for this command to work.

If the remote host is also a MultiNet system, this command is the same as typing MULTINET SHOW /ALL on the remote host.

```

        [ /destinations=(dest1[,dest2, . . . ]) ]
/ROUTE [ /gateways=(gateway1[,gateway2, . . . ]) ]
        [ /interfaces=(interface1[,interface2, . . . )]]

```

Displays routing information for the IP, IPX, NETWARE, NS, and SPX protocols.

- /DESTINATIONS displays only routes to these destination addresses; this qualifier is only valid for IP routes.
- /GATEWAYS displays only routes through these gateways; this qualifier is only valid for IP routes.
- /INTERFACES displays only routes through these interfaces.

You can use all other MULTINET SHOW qualifiers with MULTINET SHOW /ROUTE.

Note! The /ROUTE qualifier must precede all other qualifiers.

/RPC_PORTMAP

Displays the currently registered RPC protocols by contacting the RPC portmapper.

[interface]
/STATISTICS[= *[protocol]*]
[all]

Displays network interface statistics, protocol statistics, or both. If /STATISTICS is specified with no value, interface statistics are displayed.

/SNMP_HOST=hostname

Used with the following MULTINET SHOW qualifiers to obtain information from a remote SNMP agent. You can override the default community name (public) using the /COMMUNITY_NAME qualifier.

/COMMUNITY_NAME
/CONNECTIONS[=(all)]
/ARP
/MIB_VAR
/ROUTE (note: /ROUTE must precede /SNMP_HOST on the command line)
/STATISTICS

[host_table (default)]
/SYMBOLIC_ADDRESSES [= *[nameserver]*]
/NOSYMBOLIC_ADDRESSES *[nameserver_first]*

Determines how certain fields in the output are formatted before being displayed to the user. These qualifiers are used with the other MULTINET SHOW qualifiers.

- **/SYMBOLIC_ADDRESSES=HOST_TABLE** specifies that the static host tables are used to translate IP addresses to host names, network numbers to network names, and port numbers to service names.
- **/SYMBOLIC_ADDRESSES=NAMESEVER** specifies that the Domain Name System (DNS) is queried to translate IP addresses into host names if the normal host table lookup fails. This operation can generate many queries to DNS domain servers (and can, therefore, be quite slow).
- **/SYMBOLIC_ADDRESSES=NAMESEVER_FIRST** specifies that the DNS is queried first to translate IP addresses into host names, falling back to the host tables if the query should fail.
- **/NOSYMBOLIC_ADDRESSES** specifies that "raw" protocol addresses and port number are displayed in the output, rather than determining the host, network, and service names that correspond to the addresses and numbers.

/TCP

Shows network connections. (/TCP is the same as /CONNECTION.)

/VERSION

Displays the MultiNet version and the version of the VMS Operating System.

/WIDTH=width

Specifies the width of displayed output when used with the /ARP, /CONNECTIONS, /ROUTE, and /STATISTICS qualifiers. The width must be greater than 80.

EXAMPLES

This example shows how to use the /OUTPUT qualifier to direct the output of a MULTINET SHOW command to the file MULTINET.ALL.

```
$ MULTINET SHOW /ALL /OUTPUT=MULTINET.ALL
$
```

```
$ MULTINET SHOW
```

MultiNet Active Connections:

Proto	Rcv-Q	Snd-Q	Local Address (Port)	Foreign Address	State
TCP	0	0	LOCALHOST(790)	LOCALHOST(RPC)	TIME_WAIT
TCP	0	0	LOCALHOST(1033)	LOCALHOST(SMTP)	TIME_WAIT
TCP	0	0	FLOWERS(NETSTAT)	WARBUCKS(3335)	FIN_WAIT_2
TCP	0	0	FLOWERS(FTP)	WARBUCKS(3334)	ESTABLISHED
TCP	0	0	FLOWERS(1031)	WARBUCKS(TELNET)	ESTABLISHED
UDP	0	0	FLOWERS(NAMESERV)	*(*)	
UDP	0	0	LOCALHOST(NAMESERV)	*(*)	
UDP	0	0	FLOWERS(DECNET)	IU(DECNET)	

```
$ MULTINET SHOW /CONFIGURATION
```

** Configuration for file "MULTINET:NETWORK_DEVICES.CONFIGURATION" **

Device	Adapter	CSR	Address	Flags/Vector
se0 (Shared VAX/VMS Ethernet)	-NONE-	-NONE-	-NONE-	
s10 (Serial Line IP)	-NONE-	-NONE-	-NONE-	
dn0 (IP over DECNet link)	-NONE-	-NONE-	-NONE-	

```
$ MULTINET SHOW /STATISTICS=INTERFACE
```

MultiNet Network Interface statistics:

Name	Mtu	Network	Address	Ipkts	Ierrs	Opkts	Oerrs	Collis
se0	1500	FLOWERS-NET	FLOWERS.COM	150	0	116	0	0
s10	1006	FLOWERS-NET	FLOWERS.COM	597	0	697	0	0
pd0	1500	FLOWERS-NET	192.0.0.1	0	0	0	0	0
dno*	1500	FLOWERS-NET	FLOWERS.COM	0	0	0	0	0
lo0	1536	LOOPBACK-NET	LOCALHOST	53	0	53	0	0

```
$
```

This example displays the status of MultiNet licenses.

```
$ MULTINET SHOW /LICENSE
MultiNet V4.4
Product      License      Authorization
-----
MULTINET     Yes          A-2336-15873
NFS-SERVER   Yes          A-2336-15879
NFS-CLIENT   Yes          A-2336-15882
$
```

In this example, user ROSE on host FLOWERS.COM has issued a print request to print the file PROGRAMMERS.PS on the REMOTE_PS local queue. The REMOTE_PS queue, however, is a MultiNet VMS remote print queue that uses the LPD protocol to send the print request to the print queue SY\$PS on host 192.0.0.89.

The MULTINET SHOW /QUEUE command is then used to display the contents of both queues; the remote queue first (SY\$PS on FLOWERS) then the local queue (REMOTE_PS).

```
$ PRINT /QUEUE=REMOTE_PS PROGRAMMERS.PS
Job PROGRAMMERS (queue REMOTE_PS, entry 972) started on REMOTE_PS
```

```
$ MULTINET SHOW /QUEUE=REMOTE_PS
Jobname      Username      Entry  Blocks  Status
-----
MANAGE       DAISY         111    988     Printing
INSTALL      DAISY         115    238     Pending
Printer queue REMOTE_PS, on FLOWERS::NLP0:"192.0.0.89/SY$PS"
Jobname      Username      Entry  Blocks  Status
-----
PROGRAMMERS  ROSE          972    1112    Printing at block 370
$
```

This example displays the routing table on the local host without doing IP address-to-name translation.

```
$ MULTINET SHOW /ROUTE /NOSYMB
MultiNet IP Routing tables:
Destination  Gateway      Flags          Refcnt  Use  Interface
-----
192.41.228.129 127.0.0.1    Up,Gateway,H  0        0    lo0
127.0.0.1      127.0.0.1    Up,Host       2        53    lo0
192.41.228.130 192.41.228.129 Up,Host       3       340    sl0
192.41.228.131 192.41.228.129 Up,Host       0         0    dn0
0.0.0          192.41.228.130 Up,Gateway    0       353    sl0
192.41.228.64  192.41.228.65 Up             2       112    se0
192.41.228     192.41.228.1 Up             0         0    pd0
$
```


This example displays local host information.

```
$ MULTINET SHOW/ROUTE/DESTINATIONS=127.0.0.1
```

MultiNet IP Routing tables:

Destination	Gateway	Flags	Refcnt	Use	Interface
-----	-----	-----	-----	---	-----
LOCALHOST	LOCALHOST	Up,Host	1	464	lo0

```
$
```

This example displays the current version of MultiNet and the VMS Operating System.

```
$ MULTINET SHOW /VERSION
```

FLOWERS MultiNet V4.4

```
$
```

MULTINET TCPDUMP

Displays the contents of Ethernet packet headers that match the specified boolean expression. To stop the dump, press **Ctrl/Z**.

FORMAT

MULTINET TCPDUMP [*expression*]

RESTRICTIONS

The following restrictions apply to the use of MULTINET TCPDUMP.

- Although the TCPDUMP expression grammar allows the use of the exclamation point (!) character as the NOT operator and as part of the NOT-EQUAL comparator, DCL interprets it as a comment character. Therefore, use NOT instead.

For example, to print the start and end packets (the SYN and FIN packets) of each TCP conversation that involves a remote host:

```
$ MULTINET TCPDUMP NOT (TCP[13] & 3 = 0) AND NOT SRC -  
_ $ AND DST NET LOCALNET
```

- PHY_IO privilege is required to use TCPDUMP, currently only supported for use with Compaq Computer Ethernet cards.
- The packet filter code is not very efficient and adds significant overhead to your VMS system when monitoring a busy network. In addition, if you are using DNS and a problem occurs with name server access, TCPDUMP can appear to hang while waiting for a response from the network.
- IP options are ignored and not displayed.
- Understands PPP frames and does not treat all data as IP datagrams.
- No attempt is made to reassemble IP fragments or at least compute the right length for the higher level protocol.
- Name server inverse queries are not dumped correctly. An empty question section is printed rather than the real query in the answer section.

PARAMETER

expression

Selects which packets are dumped. If an expression is not given, all packets on the net are dumped. Otherwise, only packets for which the expression is "true" are dumped. Enter **HELP MULTINET TCPDUMP EXPRESSION** for a list of expression values.

QUALIFIERS

/AFTER=time

Selects packets dated after the specified time. The time value can be any valid OpenVMS time specification (absolute, delta, or a combination of the two).

/BEFORE=time

Selects packets dated prior to the specified time. The time value can be any valid OpenVMS time specification (absolute, delta, or a combination of the two).

/COUNT=number_of_packets

Exits TCPDUMP after the specified number of packets is received. The default is 0, or no limit.

/DEBUG

Displays debugging information.

/DEVICE=device name

Specifies the VMS device name of the Ethernet device to use. By default, TCPDUMP searches for EZA0, EXA0, EFA0, ETA0, ESA0, XEA0, and XQA0 devices.

/DOMAINS

/NODOMAINS

Displays host names with the domain information; /NODOMAINS strips the domain names.

/EBCDIC

Modifies the behavior of the /HEXADECIMAL qualifier by adding the EBCDIC translation of the data in addition to the ASCII translation to the TCPDUMP output.

/ETHERNET_HEADER

Displays the Ethernet header (source, destination, protocol, and length) on each dump line.

/FILE_FORMAT=SNIFFER

Use in conjunction with /READ_BINARY or /WRITE_BINARY to read or generate output automatically formatted for display on version 2.0 Network General sniffers.

/FOREIGN_NUMERICALLY

Displays "foreign" Internet addresses numerically rather than symbolically.

/HEXADECIMAL_DUMP

Displays each packet (less its 14-byte Ethernet header) in hexadecimal format. Up to 64 bytes of the packet are printed.

/INTERFACE=device

Specifies the device to trace. Valid devices are those for Ethernet/FDDI (se), the loopback connection (lo0), SLIP lines (sl), PPP lines (ppp), PSI connections (psi), and IP-over-DECNET connections (dn). This qualifier cannot be used with the /DEVICE qualifier.

/NUMERICALLY

Specifies that host addresses and port numbers are not converted to names on output.

/OUTPUT=filename

Redirects TCPDUMP output to a file.

/QUIET

Specifies that less protocol information is displayed, making output lines shorter.

/READ_BINARY=binary_file

Reads in a file previously written using the /WRITE_BINARY qualifier. (Refer to /WRITE_BINARY for more information.)

You can use /READ_BINARY with /FILE_FORMAT=SNIFFER to read output formatted automatically for display on version 2.0 Network General sniffers. This feature permits sites to analyze Network General analyzer, rather than only examining the TCPDUMP packets. (TCPVIEW also provides the ability to analyze packet traces.)

/RPC

Interprets RPC calls in the output.

/SNAPSHOT_SIZE=snaplen

Indicates the specified number of bytes of data to capture from each packet rather than the default of 54 bytes (which is adequate for most applications). 96 bytes is adequate for IP, ICMP, TCP, and UDP, but may truncate protocol information from name server and NFS packets.

/TIMESTAMPS=value**/NOTIMESTAMPS (default)**

Causes TCPDUMP to display a timestamp on each output line. Accepted values are DEFAULT, UNIX, DELTA, and RELATIVE. The /NOTIMESTAMPS qualifier disables the TCPDUMP timestamp on each output line.

/VERBOSE

Provides additional information in the output listing.

/WRITE_BINARY=binary_file

Stores the output of TCPDUMP in a file. Use this qualifier to "record" the TCPDUMP information until you press **Ctrl/Y**. After recording the output of a TCPDUMP session, use /READ_BINARY to read in the binary file for examination.

You can use /WRITE_BINARY with /FILE_FORMAT=SNIFFER to generate output automatically formatted for display on version 2.0 Network General sniffers. This feature permits sites to analyze Network General analyzer, rather than only examining the TCPDUMP packets. (TCPVIEW also provides the ability to analyze packet traces.)

EXAMPLES

This example displays all traffic addressed to or transmitted from host OL.SLG.COM.

```
$ MULTINET TCPDUMP HOST OL.SLG.COM
18:56:24.25 BIG.SLG.COM.x11 > OL.SLG.COM.1030:.ack 21527130 win 4096.
```

This example displays all traffic between local hosts and hosts at the network IRIS-ETHER at flowers.

```
$ MULTINET TCPDUMP NET IRIS-ETHER
. .
```

This example displays all FTP traffic being sent to host BETTY.URUB.EDU.

```
$ MULTINET TCPDUMP -
DST HOST BETTY.URUB.EDU AND (PORT FTP OR PORT FTP-DATA)
```

This example displays IP traffic not sent from or destined for the network IRIS-ETHER. If IRIS-ETHER is the local network, only transient traffic displays.

```
$ MULTINET TCPDUMP IP AND NOT NET IRIS-ETHER
```

MULTINET TCPVIEW

Traces packets and interprets the results.

FORMAT

MULTINET TCPVIEW [*filename*]

PARAMETER

filename

Specifies the name of the optional file to be analyzed. If not specified, TCPVIEW itself can capture network traffic to analyze packets. If you specify a file name, the file must be a Network General Sniffer Version 2 data file, or a TCPDUMP file created with the TCPDUMP/WRITE_BINARY qualifier. (Network General data file version IV does not work with TCPVIEW.)

QUALIFIERS

/COUNT=number_of_packets

If used, TCPVIEW exits after receiving the specified number of packets.

/DEVICE=devicename

Specifies the OpenVMS device name of the Ethernet device to use. By default, TCPVIEW searches for EZA0, EFA0, EXA0, ETA0, ESA0, XEA0, and XQA0. This qualifier is provided for backward compatibility; use the /INTERFACE qualifier instead. /DEVICE bypasses MultiNet's BPF (Berkeley Packet Filter) feature and allows only a single user to access TCPVIEW. /DEVICE cannot be used with the /INTERFACE qualifier.

/DOMAINS (default)

/NODOMAINS

Displays host names with the domain information; /NODOMAINS strips the domain names.

/ETHERNET_HEADER

Prints the Ethernet header (source, destination, protocol, and length) on each dump line.

/FILE_FORMAT=SNIFFER

Specifies that the binary packet trace being read by TCPVIEW is in Network General v2.0 sniffer format.

/INTERFACE=device

Specifies the device to trace. Valid devices are those for Ethernet, FDDI, the loopback connection, SLIP lines, PSI connections, and IP-over-DECnet connections. /INTERFACE cannot be used with the /DEVICE qualifier.

/PROMISCUOUS

Specifies that all network packets are displayed. Using this qualifier adds a significant load to a

system.

/SNAPSHOT_SIZE=snaplen

Captures snaplen bytes of data from each packet rather than the default of 54 bytes (which is adequate for many applications). 96 bytes is adequate for IP, ICMP, TCP, and UDP, but may truncate protocol information from name server and NFS packets.

/TIMESTAMPS

/NOTIMESTAMPS (default)

/NOTIMESTAMPS causes TCPVIEW to suppress printing the timestamp on each output line.

/VERBOSE

Causes TCPVIEW to print more verbose packet descriptions.

DESCRIPTION

TCPVIEW provides a mechanism for tracing packets and interpreting the results. The visual interface provides separate windows for the packet trace, an ASCII interpretation of the results, and a hex dump. In addition, as you select interpretation events, the respective sections of the hex dump are highlighted. TCPVIEW works only with OpenVMS VAX V5.5-2 and later and with all versions of OpenVMS AXp.

TCPVIEW can capture network traffic or read TCPDUMP and Network General Sniffer Version 2 data files. (Version IV does not work with TCPVIEW.) TCPVIEW was derived from TCPDUMP and shares many characteristics with it. It must be run from a privileged account, but should not be installed with privileges. TCPVIEW uses DECwindows/Motif, which must be installed along with DECwindows to permit TCPVIEW to run. (TCPVIEW will not run with DECwindows alone.)

The main display is a window with three resizeable panes.

- The top pane contains a summary line describing each packet. This line is identical to the output of TCPDUMP. Selecting a line in the top pane activates the middle and bottom panes.
- The middle pane contains a detailed decoding of the selected frame. Information is only included here if the appropriate protocol decoders are present. If a line is selected in this pane, the corresponding line will be at the top of this pane for all subsequent frames decoded.
- The bottom pane is a hex dump of the entire frame. Data is highlighted when a line is selected in the middle pane.

TCPVIEW MENUS

The TCPVIEW menu bar allows you to change configuration settings, load and store files, access help, and exit. The menu bar consists of File, Capture, Filter, Options, and Help pulldown entries.

FILE MENU

The File pulldown menu allows you to open (load) a data file, save (store) a data file, print a packet trace, and exit TCPVIEW.

- File Open displays a DECwindows/Motif file dialog box that lists the files in the current

directory. To load a file, click the required file, then click OK. (Double-clicking selects and loads the file in one operation.)

- File Save displays the Save dialog box which allows you to save only the filtered packets or all of the seen packets. This selection also allows you to determine the format of the output file. A text field is provided to assign a file name to the output file.
- File Print displays the Print dialog box which allows you to print all or only filtered packets in either Summary or Detail mode.
 - Summary mode displays a single line, much like the standard TCPDUMP output.
 - Detail mode breaks each packet down, much like the Network General Sniffer output.
- File Exit allows you to exit the TCPVIEW utility.

CAPTURE MENU

The Capture pulldown menu sets capture options and begins capturing packets.

- Capture Set Options specifies the parameters that control how a packet is captured. This selection contains these options:
 - Device Name selects which device interface (MultiNet or Compaq) to use for capturing data.
 - Promiscuous Mode determines if the interface is set to promiscuous mode. If promiscuous mode is not enabled, you can only capture packets using the MultiNet interface (which supports the BPF packet interface).
 - Number of Frames sets a limit on the number of frames that can be captured. Numbers less than or equal to 0 and invalid entries reset the limit to "infinite".
 - Time Limit sets a limit on the number of seconds that data will be captured. Numbers less than or equal to 0 and invalid entries reset the limit to "infinite".
 - Max Bytes Per Frame sets the maximum number of bytes that can be captured per frame (the minimum is 68 bytes); sizes smaller than the minimum are not accepted.
- Capture GO starts the capture of frames. Stop a capture as follows:
 - 1 When the Stop button appears, click it or press **RETURN**.
 - 2 Wait until the maximum time is reached, or until the maximum packets to be captured is reached.

FILTER MENU

The Filter pulldown menu allows you to edit the expression that controls the frame filter. A frame filter is required for a given capture.

The Filter Edit option allows you to set up an expression used to filter the captured frames. (This is similar to the capabilities provided by the TCPDUMP expression syntax.)

There are two address filters. To activate one, click the OFF button. If both filters are activated, the second line toggle button switches to AND. Click it again to change it to OR.

The filters can work on either Data Link Level (DLC) or IP addresses. To change the address:

- 1 Click the ANY button. A request box appears asking for the new DLC or IP address.

- 2 Use the address filter to select the DLC or IP address to apply to the current data or the data to be captured.
- 3 Click any of the buttons to either toggle the button's state or display a request box for new information.

Enter ANY or ALL (case-insensitive) to set a filter back to the ANY state. For a numeric Ethernet address, enter the address in hex format either starting with "0x" or as six bytes separated by colons (for example, 0x08202b000002 or 08:20:2B:00:00:02). For IP addresses, enter a name or numeric address such as 161.44.128.70.

- The Protocol filter allows you to select the protocols you want to capture. You can select all to see any protocol you want, or select one or more of the protocols provided.
- The Port filter allows you to select all packets with that port as a source or destination. You can enter either a port number or a name. Port names are assigned via MULTINET:HOSTS.SERVICES and MULTINET:HOSTS.LOCAL. If the port name cannot be found, the filter is reset to ANY.
- The Clear filter button resets the filter to its initial state (allow all packets).
- The Apply To All applies the filter to all data that is currently captured. Selecting this with no filter in place displays all captured frames.
- Apply To Current applies the filter only to the current selected list of frames, allowing you to re-filter a captured set of packets repeatedly to look for problems or something specific in the data.

OPTIONS MENU

The Options pulldown menu controls how the data is presented, and contains options to control the address, time, and miscellaneous options.

- Address Options allow you to control how the address is presented in the main window. You can display the host name, IP address, or DLC. If you select the host name, you can choose that the Fully Qualified Domain Name (FQDN) is displayed; otherwise, the short name is used.
If you are displaying the DLC, you can use the manufacturer's names instead of the DLC. This information is provided in the file MULTINET:MANUF.CODES. For example, use this option to display PSC_003462 instead of 00000C003462 (00000C is the assigned Ethernet code for Process Software).
- Time Options control how the timestamp associated with a packet is displayed.
 - Absolute prints the arrival time in the format "HH:MM:SS.SS".
 - UNIX displays timestamps in the UNIX format, which is the number of seconds since 00:00:00 GMT (January 1, 1970).
 - Delta prints the timestamp as the number of elapsed seconds between frames.
 - Relative prints the number of seconds from the first frame.
 - None does not print a timestamp.
- Miscellaneous Options specify how each frame is displayed.
 - Verbose provides additional information, such as displaying the time-to-live (TTL) and the type of service information in an IP packet.
 - Brief displays a minimum amount of protocol information.

- Display DLC header displays the DLC source, destination, and protocol type in the summary line.
- Use Relative TCP Sequence Numbers resets each TCP connection's sequence to make it easier to follow.
- Display Line Numbers displays a number for each frame.

HELP MENU

The Help pulldown menu provides access to online help. It provides three options in the pulldown: Overview, About, and Help On Help. It can also provide context-sensitive help by using MB1 and the Help button. For help on context-sensitive help, see the help provided by this widget or see the *DECwindows/Motif User's Guide*.

MULTINET TRACEROUTE

Attempts to trace the route that an IP packet follows to another Internet host.

FORMAT

MULTINET TRACEROUTE *host [data_length]*

DESCRIPTION

TRACEROUTE finds the intermediate hops by sending probe packets with a small TTL (time-to-live), then listening for an ICMP "time exceeded" reply from a gateway. It starts probing with a TTL of one, then increases by one in each successive probe until an ICMP "port unreachable" reply is received (indicating that a probe reached the host) or the TTL exceeded 30 (the default maximum).

By default, three probes are sent at each TTL setting, and a line is printed showing the TTL, the gateway address, and round trip time of each probe. If the probe answers come from different gateways, the address of each responding system is printed. If there is no response within a five-second timeout interval, a "*" is printed for that probe. TRACEROUTE prints a "!" after the time if the TTL is less than or equal to one. The following table shows other possible annotations:

Annotation	Meaning
!H	Host unreachable
!N	Network unreachable
!P	Protocol unreachable
!S	Source route failed
!F	Fragmentation_needed

The !S and !F annotations are rare and indicate that the associated gateway is not working properly. If most of the probes result in "unreachable" annotations, TRACEROUTE stops running and exits.

PARAMETERS

host

Specifies the target host to which you want to determine the route.

data_length

Specifies the amount of data sent in each ICMP Echo Request packet.

QUALIFIERS

/DEBUG

/NODEBUG (default)

Enables socket-level debugging in the MultiNet kernel. This qualifier is used only for debugging the MultiNet kernel.

/MAXIMUM_TTL=maximum_ttl

Specifies the maximum TTL (time-to-live) to explore looking for ICMP Time Exceeded responses. If not specified, the default of 30 hops is used.

/MINIMUM_TTL=minimum_ttl

Specifies the minimum TTL to explore looking for ICMP Time Exceeded responses. If not specified, the default of 1 hop is used.

/NUMBER_OF_PROBES=n

Specifies the number of probe packets sent to each hop (by default, 3).

/OUTPUT=filename

Redirects TRACEROUTE output to a file.

/PORT=udp_port

Specifies a non-standard port number. TRACEROUTE sends data to an unused port and expects an error message. If the default port of 33434 is in use, use /PORT to specify another.

/ROUTE (default)

/NOROUTE

Disables any IP routing of the ICMP packets. The default, /ROUTE, allows IP routing to send the packet to destinations separated by gateways.

/SOURCE=ip_address

Specifies the local IP address from which packets are sent.

/SYMBOLIC_ADDRESSES (default)

/NOSYMBOLIC_ADDRESSES

Specifies that IP addresses are displayed numerically instead of being converted into host names.

/TYPE_OF_SERVICE=tos

Specifies the Type-Of-Service (TOS) field of the IP packet. The default TOS is 0 (no specific type of service).

/VERBOSE

/NOVERBOSE (default)

Displays extra information as ICMP packets are sent or received.

/WAIT_TIME=seconds

Specifies how long TRACEROUTE waits for responses (by default, 5 seconds).

EXAMPLES

This example shows tracing a route to an NSFnet gateway. Note: lines 2 and 3 are the same. This is because the gateway "lilac-dmc.Berkeley.Edu" has a kernel bug that causes the system to forward packets with a TTL of zero.

```
$ MULTINET TRACEROUTE NIS.NSF.NET
traceroute to nis.nsf.net (35.1.1.48), 30 hops max, 38 byte packet
 1  FLOWERS.BARRNET.NET (192.41.228.71)          0 ms    0 ms    0 ms
 2  UCSC.BARRNET.NET (131.119.46.7)              10 ms    0 ms    20 ms
 3  SU1.BARRNET.NET (131.119.1.5)                10 ms    20 ms    20 ms
 4  SU-B.BARRNET.NET (131.119.254.201)           20 ms    20 ms    20 ms
 5  E-NSS.BARRNET.NET (192.31.48.244)            50 ms    10 ms    20 ms
 6  t3-1.cnss9.t3.nsf.net (140.222.9.2)          20 ms    10 ms    20 ms
 7  t3-3.cnss8.t3.nsf.net (140.222.8.4)          20 ms    30 ms    30 ms
 8  t3-0.cnss24.t3.nsf.net (140.222.24.1)        70 ms    60 ms    60 ms
 9  t3-0.cnss40.t3.nsf.net (140.222.40.1)        70 ms    70 ms    60 ms
10  t3-0.cnss41.t3.nsf.net (140.222.41.1)        70 ms    70 ms    60 ms
11  t3-0.enss131.t3.nsf.net (140.222.131.1)       70 ms    80 ms    80 ms
12  nis.nsf.net (35.1.1.48)                      80 ms    80 ms    70 ms
$
```

MULTINET X11DEBUG

The X11DEBUG utility performs four tests that check the most common causes of problems encountered when running X11 clients over MultiNet:

- Checks for the UCX driver.
- Verifies that a DISPLAY has been defined with the SET DISPLAY command.
- Checks TCP/IP connections.
- Verifies that the X11 client can access the server.

If any of these tests fail, MULTINET X11DEBUG recommends a course of action to resolve the problem. Otherwise, MULTINET X11DEBUG displays the message, "%X11DEBUG-S-PASSEDALL, passed all X11 tests."

FORMAT

MULTINET X11DEBUG [*/LOG*]

QUALIFIER

/LOG

/NOLOG (default)

Enables additional debugging information.

Chapter 2

MultiNet Secure/IP DCL Commands

This chapter describes the MULTINET DCL commands system managers use to manage the MultiNet Secure/IP user profile database on MultiNet Secure/IP Servers.

Table 2-1 summarizes the MultiNet Secure/IP DCL commands.

Table 2-1 MultiNet Secure/IP DCL Commands

Command	Description
MULTINET PROFILE /DELETE	Deletes all or a portion of a user profile on the local MultiNet Secure/IP Server.
MULTINET PROFILE /MODIFY	Adds new and modified existing user profiles in the local MultiNet Secure/IP user profile database.
MULTINET PROFILE /SHOW	Displays all or a portion of a user profile on the local MultiNet Secure/IP Server.
MULTINET PROFILE / SUMMARY	Returns the number of user profiles in the local MultiNet Secure/IP Server profile database.
MULTINET SKEY	Calculates an S/KEY response for a particular sequence and seed. This can also be done on any system running Bellcore S/KEY calculator software.
MULTINET TOKEN CRYPTOCARD /CLEAR	Erases the CRYPTOCard key associated with the specified user from the user profile database.
MULTINET TOKEN CRYPTOCARD /LOAD	Generates a series of codes to enter into a CRYPTOCard for the specified user and stores a new key in the user profile database.

Table 2-1 MultiNet Secure/IP DCL Commands (Continued)

Command	Description
MULTINET TOKEN CRYPTOCARD /TEST	Tests the CRYPTOCARD programming by generating a random challenge and verifying the response. This sequence mimics what you would see when login in remotely using the CRYPTOCARD authentication method.
MULTINET TOKEN SKEY /CLEAR	Erases the S/KEY sequence for the specified user from the MultiNet user profile database.
MULTINET TOKEN SKEY /INITIALIZE	Initializes a new S/KEY sequence for the specified user and stores the resulting sequence in the user profile database.
MULTINET TOKEN SKEY /SHOW	Displays the next S/KEY sequence for the specified user.
MULTINET TOKEN SKEY /TEST	Tests S/KEY authentication.
MULTINET TOKEN SNK /CLEAR	Erases the SNK key associated with the specified user from the user profile database.
MULTINET TOKEN SNK /LOAD	Generates a random key, displays the programming sequence for the Compaq Pathways SecureNet (SNK) personal identification token, and stores the new key in the user profile database.
MULTINET TOKEN SNK /TEST	Tests the SNK programming by generating a random challenge and verifying the response. This sequence mimics that what you see when logging in remotely using the SNK authentication method.

MULTINET PROFILE /DELETE

Deletes all or a portion of a user profile on the local MultiNet Secure/IP Server.

Note! You cannot configure the local MultiNet Secure/IP Client to use the local server. To determine which MultiNet Secure/IP Server is being used by the local MultiNet Secure/IP Client, use the ACCESS-CONFIG utility or the SHOW LOGICAL MULTINET_ACCESS_SERVER_ADDRESS command.

FORMAT

MULTINET PROFILE /DELETE [=subtype] [username]

PARAMETERS

username

Specifies a user's login name. You may use the wildcard characters asterisk (*) and percent (%). If you omit the login name, the current user information is cleared.

subtype

Specifies the profile subtype to delete from the username profile. The following are valid subtype values:

- **method**-Deletes the profile data related to the user's default authentication method.
- **cryptocard**-Deletes the CRYPTOCARD authentication data, if any exists.
- **snk**-Deletes the SNK authentication data, if any exists.
- **skey**-Deletes the S/KEY authentication data, if any exists.

If you omit the subtype, the entire user profile is deleted.

QUALIFIERS

/CONFIRM

Specifies that you want a confirmation prompt before the specified user profile data is deleted.

/LOG

Specifies that a message is displayed after a key has been successfully erased from the user profile database. By default, the deletion message is not displayed.

EXAMPLE

```
$ MULTINET PROFILE WHORFIN /DELETE=SNK /LOG
%SECUREIP-S-SNKDELETED, SNK key for principal "WHORFIN" deleted
```

MULTINET PROFILE /MODIFY

Adds new user profiles or modifies existing user profiles in the local MultiNet Secure/IP user profile database.

Note! You cannot configure the local MultiNet Secure/IP Client to use the local server. To determine which MultiNet Secure/IP Server is being used by the local MultiNet Secure/IP Client, use the ACCESS-CONFIG utility or the SHOW LOGICAL MULTINET_ACCESS_SERVER_ADDRESS command.

FORMAT

MULTINET PROFILE /MODIFY=METHOD= *method* [*username*]

PARAMETERS

method

Specifies the authentication method used by username. Specify METHOD data to override the system default authentication method. The following are valid *method* values:

password	snk	skey	cryptocard	securid
----------	-----	------	------------	---------

Note! To remove METHOD data and return to the system default authentication method for username, use the MULTINET PROFILE /DELETE=METHOD username command.

username

Specifies the user’s login name. You may use the wildcard characters asterisk (*) and percent (%). If there is no profile for *username* in the user profile database, the command prompts you to create a new user profile with the specified subtype.

QUALIFIERS

/CONFIRM

Specifies that you want a confirmation prompt before the specified user profile data is modified.

/LOG

Specifies that a message is displayed after a user profile has been successfully modified in the user profile database. By default, modification messages are not displayed.

EXAMPLE

```
$ MULTINET PROFILE WHORFIN /MODIFY=AUTHPREF=SNK004 /LOG
%SECUREIP-S-SNKDELETED, SNK key for principal "WHORFIN" deleted
```

MULTINET PROFILE /SHOW

Displays all or a portion of a user profile on the local MultiNet Secure/IP Server.

Note! You cannot configure the local MultiNet Secure/IP Client to use the local server. To determine which MultiNet Secure/IP Server is being used by the local MultiNet Secure/IP Client, use the ACCESS-CONFIG utility or the SHOW LOGICAL MULTINET_ACCESS_SERVER_ADDRESS command.

FORMAT

MULTINET PROFILE /SHOW *[user]*

QUALIFIER

/FULL

Displays all profile subtypes associated with the specified user.

EXAMPLE

```
$ MULTINET PROFILE /SHOW W*
Username                Preferred Method
-----                -
walter                  <default>
whorfin                 Security Dynamics SecurID
```

```
$ MULTINET PROFILE /SHOW /FULL WHORFIN
Username                Profile(s)
-----                -
whorfin                 SNK004, Method (Security Dynamics SecurID)
```

MULTINET PROFILE /SUMMARY

Returns the number of user profiles in the local MultiNet Secure/IP Server profile database.

Note! You cannot configure the local MultiNet Secure/IP Client to use the local server. To determine which MultiNet Secure/IP Server is being used by the local MultiNet Secure/IP Client, use the ACCESS-CONFIG utility or the SHOW LOGICAL MULTINET_ACCESS_SERVER_ADDRESS command.

FORMAT

MULTINET PROFILE /SUMMARY

EXAMPLE

```
$ MULTINET PROFILE /SUMMARY  
%SECUREIP-I-SUMMARY, 28 user profile records found
```

MULTINET SKEY

Calculates an S/KEY response for a particular sequence and seed. This can also be done on any system running Bellcore S/KEY calculator software. MULTINET SKEY prompts for the S/KEY password unless /PASSWORD is specified.

FORMAT

MULTINET SKEY [*sequence*] [*seed*]

PARAMETERS

sequence

Specifies a sequence value from 1 to 99.

seed

Specifies the S/KEY seed value. This value can be up to 18 characters in length.

QUALIFIERS

/COUNT=number

Specifies the number of S/KEY responses to compute. The default is 1.

/DELETE

Specifies that the S/KEY output file is deleted after printing. The default is /NODELETE. Use /DELETE only with /PRINT.

/OUTPUT=filename

Specifies the name of a file to which the S/KEY sequence is written. The default output file name is SKEY.LIS. If you omit /OUTPUT, MULTINET SKEY displays the sequence on SYS\$OUTPUT.

/PRINT

Specifies that the S/KEY output file is printed. By default, the output file is called SKEY.LIS and is queued to SYS\$PRINT. Use /PRINT only with /COUNT.

/QUEUE=queue

Specifies the name of the queue to which the S/KEY output file is queued. By default, the output file is queued to SYS\$PRINT. Use /QUEUE only with /PRINT.

/SYMBOL=name

Specifies the response to be stored as the value of the symbol name.

EXAMPLE

```
$ MULTINET SKEY 98 BI44244  
Password: *****  
BANK BORG ACT AMOK GIFT OHIO
```

The following example prints a list of 10 passwords on SYS\$PRINT and deletes the output file after printing:

```
$ MULTINET SKEY /COUNT=10 98 BI4424 /PRINT /DELETE  
Password: *****
```

MULTINET TOKEN CRYPTOCARD /CLEAR

Erases the CRYPTOCARD key associated with the specified user from the user profile database. If a username is not specified, MULTINET TOKEN CRYPTOCARD /CLEAR clears the key for the current user. SECURITY privilege is required to clear another user's key. Non-privileged users can erase their own CRYPTOCARD keys by successfully responding to a challenge from MULTINET TOKEN CRYPTOCARD /CLEAR. Once erased, the token must be reprogrammed by the site security administrator.

FORMAT

MULTINET TOKEN CRYPTOCARD /CLEAR *[username]*

PARAMETER

username

Specifies the login name of a user. If omitted, the current user information is cleared.

QUALIFIER

/LOG

Specifies that a confirmation message is displayed after a key has been successfully erased from the user profile database. /LOG is the default. Specify /NOLOG to cancel the message.

EXAMPLE

```
$ MULTINET TOKEN CRYPTOCARD /CLEAR
%SECUREIP-S-CRYPTOCARDDELETED, CRYPTOCARD key for principal "holmes"
deleted
```

MULTINET TOKEN CRYPTOCARD /LOAD

Generates a series of codes to enter into a CRYPTOCard for the specified user and stores a new key in the user profile database. If a user name is not specified, a key for the current user is generated. SECURITY privilege is required to generate a key for another user and to load the initial (first) key.

FORMAT

MULTINET TOKEN CRYPTOCARD *[username]*

PARAMETER

username

Specifies the login name of a user. If omitted, the current user information is initialized.

QUALIFIERS

/CHALLENGE= { FULL | REDUCED }

Enables or disables the CRYPTOCard’s "reduced input" mode. If REDUCED, the CRYPTOCard operates in "reduced input" mode and guesses the next challenge after the user enters the correct PIN. When FULL, the user must enter the challenge manually. The default is REDUCED.

/CONFIRM

Specifies that you are prompted for confirmation before a key is stored in the user profile database. The default is /CONFIRM. If username has already has been initialized, a message appears to this effect, /CONFIRM is ignored, and you are prompted if you want to initialize this user. The following example shows this situation:

```
$ MULTINET TOKEN CRYPTOCARD /LOAD /VERBOSE SYSTEM
%SECUREIP-W-CRYPTOCARDKEYSET, CRYPTOCARD key for principal "system"
already exists
Initialize CRYPTOCARD key for principal "system"? [N]: YES
```

/DISPLAY=*list*

Determines the format of the prompts generated by the CRYPTOCard. list is a comma-separated list that includes any combination of the keywords shown in Table 2-2.

Table 2-2 CRYPTOCard /DISPLAY Keywords

Keyword	Description	Default
DECIMAL	Specifies that all numeric displays appear in decimal format.	NODECIMAL
HEXADECIMAL	Specifies that all numeric displays appear in hexadecimal format.	HEXADECIMAL

Table 2-2 CRYPTOCARD /DISPLAY Keywords (Continued)

Keyword	Description	Default
TELEPHONE	Specifies that numeric prompts appear in telephone-style dashed format (for example, 457-5200). MultiNet Secure/IP accepts responses with or without the telephone-style dashed number, regardless of the format you choose for prompts.	NOTELEPHONE
USERID= <i>name</i>	Determines the user name displayed on the CRYPTOCARD after entering the correct PIN. name must consist of 7 or 8 characters. Short names can be padded with spaces (for example, "john "). Mixed-case names must be in quotes (for example, "Hobbit ").	"Ready"

/KEY=keyword_list

Lets you enter more than one key in the CRYPTOCARD or specify a specific DES key. When you omit the /KEY qualifier, MULTINET TOKEN CRYPTOCARD /LOAD generates a random DES key in the MultiNet Secure/IP Server user profile database (MULTINET_PROFILE.DATA). Use the /KEY qualifier if the CRYPTOCARD will be used with more than one authentication server. keyword is one of those shown in Table 2-3.

Note! MULTINET TOKEN CRYPTOCARD /LOAD only generates the programming instructions and user profile data for the local MultiNet Secure/IP Server; you must obtain other keys from the corresponding authentication servers.

Table 2-3 CRYPTOCARD /KEY Keywords

Keyword	Description
NUMBER= <i>n</i>	<i>n</i> must be an integer between 1 and 3. If <i>n</i> is greater than 1, you must obtain the required additional keys from the corresponding authentication servers. If you program more than one DES key into a CRYPTOCARD, the MultiNet Secure/IP key must be Key1.
OCTAL	Specifies that the values be octal instead of decimal.
SPLIT	Specifies that you want to split the MultiNet Secure/IP key into two keys. You must run MULTINET TOKEN CRYPTOCARD /LOAD /SPLIT twice to generate both keys. For more information about split keys, refer to your CRYPTOCARD documentation.

Table 2-3 CRYPTOCARD /KEY Keywords (Continued)

Keyword	Description
VALUE= <i>des_key</i>	Specifies a particular DES key to be stored in the MultiNet Secure/IP Server user profile database (MULTINET_PROFILE.DATA). <i>des_key</i> is a comma-separated list of eight numbers, enclosed by parentheses. Normally, MULTINET TOKEN CRYPTOCARD /LOAD generates a new random DES key.

You must include all qualifiers (for example /DISPLAY=TELEPHONE) in the first MULTINET TOKEN CRYPTOCARD /LOAD /SPLIT command except for /DISPLAY=USERID, which must be in the second MULTINET TOKEN CRYPTOCARD /LOAD /SPLIT command. You can also specify all qualifiers in both commands; MULTINET TOKEN CRYPTOCARD /LOAD /SPLIT ignores irrelevant qualifiers.

Note! Using MULTINET TOKEN CRYPTOCARD /LOAD /SPLIT only offers security benefits if two individuals each load only one half of the key. Neither individual should have access to the contents of MULTINET:MULTINET_PROFILE.DATA.

/LANGUAGE=*lang*

Specifies the language used in all CRYPTOCARD displays. *lang* is one of the following:

ENGLISH_1	FRENCH	ITALIAN	SWEDISH
ENGLISH_2	GERMAN	PORTUGUESE	SPANISH

For descriptions of these languages, refer to your CRYPTOCARD documentation. The default is ENGLISH_1.

/LOG

Displays a confirmation message after the key has been successfully stored in the user profile database.

/PIN=*list*

Specifies the types of protection to program into your CRYPTOCARD. *list* is a comma-separated list

that includes any combination of the parameters shown in Table 2-4.

Table 2-4 CRYPTOCARD /PIN Parameters

Keyword	Description	Default
{FEEDBACK NOFEEDBACK}	The FEEDBACK keyword programs the token to indicate when an incorrect PIN is entered. The NOFEEDBACK keyword programs the token to not indicate incorrect PIN entries.	FEEDBACK
FIXED	FIXED prevents the token's PIN from being changed by the user. NOFIXED allows users to change their PINs. If the PIN is fixed, the token must be reprogrammed to change the PIN.	NOFIXED
TRIES= <i>n</i>	After <i>n</i> incorrect PIN entries, the CRYPTOCARD locks up.	3
LENGTH= <i>n</i>	Specifies the minimum PIN length.	4

/TIMEOUT= { 30 | 60 }

Specifies the number of seconds of inactivity before the CRYPTOCARD turns itself off. The default is 30 seconds.

/VERBOSE

Displays extended programming instructions for the CRYPTOCARD. By default, MULTINET TOKEN CRYPTOCARD /LOAD displays only minimal programming information. For more information, refer to the CRYPTOCARD documentation for setting up additional options.

EXAMPLES

```
$ MULTINET TOKEN CRYPTOCARD /LOAD /VERBOSE WHORFIN
%SECUREIP-IP-W-KEYEXISTS, CRYPTOCARD key for principal "whorfin" already
exists
Initialize CRYPTOCARD key for principal "whorfin"? [N]: Y
To clear the memory an existing CRYPTOCARD token: ON 225371
```

The initial "2" keystroke must occur no more than one-half second after the "ON" key. The other keys must also be pressed within two of each other. Alternatively, removal of both batteries for a second will clear the memory of an existing token.

To initialize a CRYPTOCard token for principal "whorfin":

Prompt	Enter
Locked	ENT
Options?	<prompt will change to "1" on first key press>
1	100 ->
2	234 ->
3	001 ->
4	ENT
Key1?	<prompt will change to "1" on first key press>
1	346 ->
2	315 ->
3	203 ->
4	105 ->
5	046 ->
6	357 ->
7	121 ->
8	054 ->
<blank>	ENT
45DF6308	ENT

You must now choose an initial PIN for the token. This is an initial PIN. Regardless of the PIN change option selected, the user will be to choose a new PIN the first time they use their token. This PIN must be given to the user along with this token.

```
Prompt          Enter
-----
New PIN?        <pin> ENT          (<pin> = 4-8 digit number)
Verify          <pin> ENT          (<pin> = 4-8 digit number)
Card OK
%SECUREIP-S-KEYLOADED, CRYPTOCard key for principal "whorfin" initialized
$
```

Using the information in this example, program the CRYPTOCard as follows:

- 1 Clear the CRYPTOCARD memory by momentarily removing the batteries or entering the "clear" key sequence:
 - a Turn on the CRYPTOCARD and press **2** within half a second.
 - b Enter **25371**.
 - c Press **ENT**. If you entered the "clear" key sequence correctly, the CRYPTOCARD displays the LOCKED prompt.
- 2 At the LOCKED prompt, press **ENT**.
- 3 At the Options? prompt, enter **100** and press the "right arrow" key. The display changes when you press **1**. The number on the right side of the display indicates which option you are entering. If you enter a wrong number, press **CLR** to return to the Options? prompt.
- 4 At the 2 prompt, enter **234** and press the "right arrow" key.
- 5 At the 3 prompt, enter **001** and press the "right arrow" key.
- 6 At the 4 prompt, press **ENT**. The Key1? prompt appears.
- 7 At the Key1? prompt, enter **302** and press the "right arrow" key. The display changes when you press **3**. The number on the right side of the display indicates which key you are entering. If you enter a wrong number, press **CLR** to return to the Key1? prompt.
- 8 At the 2 prompt, enter **302** and press the "right arrow" key.
- 9 At the 3 prompt, enter **147** and press the "right arrow" key.
- 10 At the 4 prompt, enter **171** and press the "right arrow" key.
- 11 At the 5 prompt, enter **100** and press the "right arrow" key.
- 12 At the 6 prompt, enter **206** and press the "right arrow" key.
- 13 At the 7 prompt, enter **127** and press the "right arrow" key.
- 14 At the 8 prompt, enter **165** and press the "right arrow" key. The CRYPTOCARD screen goes blank.
- 15 Press **ENT**. The CRYPTOCARD displays "24D13FD6".
- 16 Press **ENT**. The NEW PIN? prompt appears.
- 17 Enter your new PIN and press **ENT**. The Verify prompt appears.
- 18 Enter your new PIN and press **ENT**. If you verify the new PIN, the CRYPTOCARD displays "Card OK".

The CRYPTOCARD is now programmed. The next time the CRYPTOCARD's user enters the new PIN, the CRYPTOCARD will force the user to change the PIN.

```
$ MULTINET TOKEN    CRYPTOCARD    /LOAD    /VERBOSE    /SPLIT    WHORFIN
%SECUREIP-W-KEYEXISTS, CRYPTOCARD key for principal "whorfin" already
exists
Initialize CRYPTOCARD key for principal "whorfin"? [N]: y
To clear the memory an existing CRYPTOCARD token: ON 225371
```

To initial "2" keystroke must occur no more than one-half second after the "ON" key. The other keys must also be pressed within two of each other. Alternatively, removal of both batteries for a second will clear the memory of an existing token.

To initialize a CRYPTOCard token for principal "whorfin":

Prompt	Enter
Locked	ENT
Options?	<prompt will change to "1" on first key press>
1	100 ->
2	234 ->
3	000 ->
4	ENT
Key1?	<prompt will change to "1" on first key press>
1	205 ->
2	357 ->
3	142 ->
4	111 ->
5	155 ->
6	142 ->
7	062 ->
8	073 ->
<blank>	ENT
3A23F664	ENT
Key2?	

The first part of split key loading is complete. The token may now be off and given to a second site-security administrator who will the initialization process by generating and loading a second key.

Make sure that you press "ENT" after verifying the checksum but before off the token. Failure to do so will require that you re-enter first key the next time you turn on the token. If the first key was correctly, the token should be displaying "Key2?".

```
%SECUREIP-S-KEYLOADED, CRYPTOCard key for principal "whorfin" initialized
-SECUREIP-I-SPLITKEYINP, CRYPTOCard split key initialization in progress
```

```
$ MULTINET TOKEN CRYPTOCARD /LOAD /VERBOSE /SPLIT WHORFIN
```

```
%SECUREIP-I-SPLITKEYFPD, CRYPTOCard split key initialization for "whorfin"
```

Initialize CRYPTOCARD key for principal "whorfin"? [N]: **Y**
 To complete split key initialization for principal "whorfin":

Prompt	Enter
Key2?	<prompt will change to "1" on first key press>
1	070 ->
2	323 ->
3	200 ->
4	111 ->
5	020 ->
6	057 ->
7	205 ->
8	040 ->
<blank>	ENT
5A4C2B27	ENT
69189BE7	ENT

You must now choose an initial PIN for the token. This is an initial PIN regardless of the PIN change option selected, the user will be to choose a new PIN the first time they use their token. This PIN must be given to the user along with this token.

```

Prompt      Enter
-----
New PIN?    <pin> ENT      (<pin> = 4-8 digit number)
Verify      <pin> ENT      (<pin> = 4-8 digit number)
Card OK
%SECUREIP-S-KEYLOADED, CRYPTOCARD key for principal "whorfin" initialized
$

```

Using the information generated by the commands in this example, program the CRYPTOCARD as follows:

- 1 Clear the CRYPTOCARD's memory and enter the Options and Key1 information (see Example 1). When you press **ENT** after the checksum prompt, the Key2 prompt appears.
- 2 Enter the Key2 information from the second MULTINET TOKEN CRYPTOCARD /LOAD command into the CRYPTOCARD.

MULTINET TOKEN CRYPTOCARD /TEST

Tests the CRYPTOCARD programming by generating a random challenge and verifying the response. This sequence mimics what you would see when logging in remotely using the CRYPTOCARD authentication method.

FORMAT

MULTINET TOKEN CRYPTOCARD /TEST [*username*]

PARAMETER

username

Specifies a user's login name. If you omit the user name, the current user's information is tested.

EXAMPLE

```
$ MULTINET TOKEN CRYPTOCARD /TEST  
CRYPTOCARD authentication for principal "holmes"  
Challenge: 645-3152  
Response: 6D665D62  
Authentication successful
```

To test a CRYPTOCARD token, enter your PIN into the keypad and press **ENT**. When the Challenge prompt appears, enter the displayed number into the keypad and press **ENT**. Enter the generated number at the Response prompt. The response is not case-sensitive; you can enter hexadecimal letters in uppercase or lowercase interchangeably.

MULTINET TOKEN SKEY /CLEAR

Erases the S/KEY sequence for the specified user from the MultiNet user profile database. By default, MULTINET TOKEN SKEY /CLEAR erases the current user's S/KEY sequence. SECURITY privilege is required to erase another user's S/KEY sequence.

FORMAT

MULTINET TOKEN SKEY /CLEAR *[username]*

PARAMETER

username

Specifies the login name of a user. If you omit this parameter, the current user's S/KEY sequence is cleared.

QUALIFIER

/LOG

Displays a confirmation message after the S/KEY sequence has been successfully erased from the user profile database. The default is /LOG. Use /NOLOG to cancel this message.

EXAMPLE

```
$ MULTINET TOKEN SKEY /CLEAR
%SECUREIP-S-DELETED, S/KEY for principal "holmes" deleted
```

MULTINET TOKEN SKEY /INITIALIZE

Initializes a new S/KEY sequence for the specified user and stores the resulting sequence in the user profile database. By default, MULTINET TOKEN SKEY /INITIALIZE initializes a sequence for the current user. MULTINET TOKEN SKEY /INITIALIZE prompts for a password that the user enters when a MULTINET TOKEN SKEY command is invoked. If the username is not in the SYSUAF, the administrator is prompted to confirm.

If the user who enters this command does not have SECURITY privilege, the user is prompted for a VMS password, then for the password that is required when using MULTINET TOKEN SKEY commands.

Note! Do not initialize your S/KEY sequence over an unsecure channel such as the Internet. S/KEY does not require the associated S/KEY password to be divulged to a host (server) system, except for initialization purposes. Do not enter your S/KEY password on any system that you are not logged into directly, that is, over a hard-wired terminal or a local workstation window. In general, you should only enter your S/KEY password into a portable computing device (Macintosh or PC) running an S/KEY client.

See /NOPASSWORD for a mechanism that you may use to initialize an S/KEY sequence over an unsecure link.

FORMAT

MULTINET TOKEN SKEY /INITIALIZE [*username*]

PARAMETER

username

Specifies the login name of a user. If you omit this parameter, S/KEY is initialized for the current user.

QUALIFIERS

/LOG

Displays a confirmation message after the S/KEY sequence has been successfully stored in the user profile database. This qualifier is enabled by default. Use /NOLOG to disable this function.

/PASSWORD

Specifies that MULTINET TOKEN SKEY /INITIALIZE prompts for the S/KEY password. When /NOPASSWORD is specified, MULTINET TOKEN SKEY /INITIALIZE issues an S/KEY challenge and sets the S/KEY sequence to the result of the S/KEY response. Use a new password on the S/KEY client when generating this response. You can use this to reset your S/KEY sequence over an unsecure channel without having to type your password, as normally required.

/SEED=string

Specifies the S/KEY seed associated with the new S/KEY sequence. By default, MULTINET TOKEN SKEY /INITIALIZE generates a new host-specific seed every time. An S/KEY seed is a string of 1 to 18 characters. Use the /SEED qualifier if you need to create an S/KEY sequence that exactly matches another system using the S/KEY authentication algorithm. In general, you should let the system generate a random seed for you.

/SEQUENCE=number

Specifies the length of the new S/KEY sequence. By default, MULTINET TOKEN SKEY /INITIALIZE generates a sequence that is good for 98 logins.

/VERBOSE

Displays the resulting S/KEY sequence for the specified user in a format similar to the skey.init utility under UNIX.

EXAMPLES

In this example, user "brown" has no privileges and is prompted first for his VMS password. The "New Password:" prompt requests a password that is only used with other MULTINET TOKEN SKEY commands. The password has no effect when logging in. After using this command, use the MULTINET TOKEN SKEY command to list the passwords needed to log into a system.

```
$ MULTINET TOKEN SKEY /INITIALIZE
%SECUREIP-E-SKEYNOTFOU, S/KEY not found for principal "brown"
Enter VMS Password: *****
%SECUREIP-I-SKEYINIT, S/KEY initialization for principal "brown"
New Password: *****
Verification: *****
%SECUREIP-S-INITIALIZED, S/KEY for principal "brown" initialized;
current challenge is "99 go34263"
$
```

```
$ MULTINET TOKEN SKEY /INITIALIZE SYSTEM
S/KEY initialization for principal "system"
New Password: *****
Verification: *****
S/KEY for principal "system" initialized; current challenge is "99
bi37243"
```

The following example demonstrates how to create a new S/KEY sequence when you are not logged into the MultiNet Secure/IP Server over a physically secure connection.

```
$ MULTINET TOKEN SKEY/INIT/NOPASSWORD
%SECUREIP-I-SKEYINIT, S/KEY initialization for principal "whorfin"
Challenge: s/key 99 bi301206
Response: ?
Enter results of 's/key 99 bi301206' using a new password
Challenge: s/key 99 bi301206
Response: MEW GARY ERIC LESK HART FOO
```

```
%SECUREIP-S-INITIALIZED, S/KEY for principal "whorfin" initialized;  
current challenge is "99 bi301206"
```

The following example demonstrates what happens if a user does not exist in the SYSUAF.

```
$ MULTINET TOKEN SKEY /INITIALIZE MAYA  
Principal "maya" does not exist in local system authorization file  
(SYSUAF.DAT)  
Initialize S/KEY for principal "maya"? [N]: Y  
S/KEY initialization for principal "maya"  
New Password: *****  
Verification: *****  
S/KEY for principal "maya" initialized; current challenge is "99 ee42420"
```

MULTINET TOKEN SKEY /SHOW

Displays the next S/KEY sequence for the specified user. By default, MULTINET TOKEN SKEY /SHOW displays the current user's S/KEY sequence. You must have SECURITY privilege to display another user's S/KEY sequence.

FORMAT

MULTINET TOKEN SKEY /SHOW *[username]*

PARAMETER

username

Specifies the login name of a user. If you omit the user name, the seed and sequence values appear for the current user.

EXAMPLE

```
$ MULTINET TOKEN SKEY /SHOW
%SECUREIP-I-SKEYNEXT, current S/KEY challenge for principal "holmes" is
"99 go48244"
```

MULTINET TOKEN SKEY /TEST

Tests S/KEY authentication. By default, MULTINET TOKEN SKEY /TEST tests the current user's S/KEY sequence. You must have SECURITY privilege to test another user's S/KEY sequence.

FORMAT

MULTINET TOKEN SKEY /TEST *[username]*

PARAMETER

username

Specifies a user login name. If you omit the user name, the current user information is tested.

EXAMPLE

In this example, Alison tests her passwords by first using MULTINET SKEY to list a password sequence. She then uses MULTINET TOKEN SKEY /TEST to ensure the second sequence works.

```
$ MULTINET SKEY 99 go34263 /COUNT=3
```

```
Password: *****
```

```
97: FIVE FLUB DOVE MIRE ROSS HOE
```

```
98: TROT EASY ROME WING MOB RASH
```

```
99: CUR LIFE HIKE PET SEC BIRD
```

```
$ MULTINET TOKEN SKEY /TEST
```

```
S/KEY authentication for principal "alison"
```

```
Challenge: s/key 98 go34263
```

```
Response: TROT EASY ROME WING MOB RASH
```

```
Authentication successful
```

MULTINET TOKEN SNK /CLEAR

Erases the SNK key associated with the specified user from the user profile database. If you do not specify a user name, MULTINET TOKEN SNK /CLEAR clears the key for the current user. You must have SECURITY privilege to clear another user's key. Users without privileges can erase their own SNK keys by successfully responding to a challenge from MULTINET TOKEN SNK /CLEAR. Once erased, the token must be reprogrammed by the site security administrator.

FORMAT

MULTINET TOKEN SNK /CLEAR [*username*]

PARAMETER

username

Specifies the login name of a user. If you omit the user name, the current user information is cleared.

QUALIFIER

/LOG

Specifies that a confirmation message is displayed after a key has been successfully erased from the user profile database. /LOG is the default. Specify /NOLOG to cancel the message.

EXAMPLE

```
$ MULTINET TOKEN SNK /CLEAR
%SECUREIP-S-KEYDELETED, SNK key for principal "holmes" deleted
```

MULTINET TOKEN SNK /LOAD

Generates a random key, displays the programming sequence for the Compaq Pathways SecureNet (SNK) personal identification token, and stores the new key in the user profile database. If you do not specify a user name, a key for the current user is generated. You must have SECURITY privilege to generate a key for another user or to load the initial (first) key.

FORMAT

MULTINET TOKEN SNK /LOAD [*username*]

PARAMETER

username

Specifies the login name of a user. If you omit the user name, the current user information is initialized.

QUALIFIERS

/CONFIRM

Specifies that you are prompted for confirmation before a key is stored in the user profile database. /CONFIRM is the default. If username has already been initialized, a message appears to this effect, /CONFIRM is ignored, and you are prompted if you want to initialize this user. The following example shows this situation.

```
$ MULTINET TOKEN SNK /LOAD /VERBOSE SYSTEM
%SECUREIP-W-SNKKEYSET, SNK key for principal "system" already exists
Initialize SNK key for principal "system"? [N]: YES
```

/KEY=VALUE=*des_key_list*

Lets you program tokens with specific DES keys. *des_key_list* is a comma-separated list of eight numbers representing the DES key to be stored in the associated user record in the MultiNet Secure/IP Server user profile database (MULTINET_PROFILE.DATA). By default, MULTINET TOKEN SNK /LOAD generates a new random DES key.

Note! The first key must be the MultiNet Secure/IP key.

/LOG

Displays a confirmation message after the key has been successfully stored in the user profile database.

{ [DECIMAL] }

/MODE= { [HEXADECIMAL] } [,ERASE]

Specifies the mode of operation for the SNK personal identification token. The SNK can be set to respond in either decimal or hexadecimal notation. Because the characters for "b" and "6" look similar, DECIMAL mode is preferred. However, DECIMAL mode is slightly less secure in that

information is transformed internally in the token between two possible decimal values and the 16 possible hexadecimal values (0 to F).

The SNK can also be set to erase its memory after five incorrect PINs are entered. When NOERASE is specified, the SNK generates an invalid response when an incorrect PIN is used, but does not clear its memory. By default, MULTINET TOKEN SNK /LOAD sets the operating mode to (HEXADECIMAL,NOERASE).

/VERBOSE

Displays extended programming instructions for the Compaq Pathways' SecureNet Key (SNK) personal identification token. By default, MULTINET TOKEN SNK /LOAD displays only minimal programming information.

EXAMPLES

```
1 $ MULTINET TOKEN SNK /LOAD /VERBOSE SYSTEM
%SECUREIP-W-SNKKEYSET, SNK key for principal "system" already exists
Initialize SNK key for principal "system"? [N]: YES
To clear the memory of an existing SNK key:
    ON 3 ENT 00000000 ENT ON 3 ENT 00000000 ENT
To initialize the SNK key for principal "system":
```

Prompt	Enter
E0	1 ENT
1	147
2	325
3	037
4	076
5	247
6	040
7	013
8	112
	ENT
C A6dE33	ENT

If "system" is present, they may choose their PIN now:

Prompt	Enter
E2	<pin> ENT (<pin> = 4-16 digit Personal) Identification Number
E3	<pin> ENT (<pin> = 4-16 digit Personal) Identification Number
EP	

Using the information in this example, initialize a PIN by following these steps:

- 1 Clear memory with the ON 3 ENT . . . key sequence shown at the top of the example. As you move through this sequence, the token displays information such as EP, Ed, and a response value. This information is displayed as memory is being cleared and can be ignored. Complete this sequence and press **ENT**.
- 2 E0 appears. Enter **1** and press **ENT**. The token displays E1.
- 3 Enter the values listed in the "Enter" column. As you enter each three-number set, the reference number listed in the "Prompt" column indicates which set of numbers was entered. After you have entered all the values, press **ENT**.
- 4 Ensure that the displayed Checksum value is correct. If the number is incorrect, press **ON**. The token prompts again for E0; return to Step 2.
- 5 Press **ENT** at the end of the New Key values. The token displays E2.
- 6 Enter the new PIN and press **ENT**. The token displays E3.
- 7 Enter the new PIN again and press **ENT**. The token displays EP.

Once you start a token initialization procedure, it cannot be stopped. If you make a mistake while entering New Key values, press **ON** to return to E0 (Step 2). If you make a mistake when entering a PIN at the E2 or E3 prompts, press **ON** to re-enter the value.

```
$ MULTINET TOKEN SNK /LOAD /CONFIRM SYSTEM
Initialize SNK key for principal "system"? [N]: YES
Clear:  ON      3 ENT 00000000 ENT ON 3 ENT 00000000 ENT
Mode:   1
Key:    031 177 236 147 160 061 166 007
Checksum:  dEC9E1
%SECUREIP-S-SNKLOADED, SNK key for principal "system" initialized
```

Note! You can give the token to the user when you reach the E2 prompt, but the user is then responsible for entering a PIN.

MULTINET TOKEN SNK /TEST

Tests the SNK programming by generating a random challenge and verifying the response. This sequence mimics that what you see when logging in remotely using the SNK authentication method.

FORMAT

MULTINET TOKEN SNK /TEST *[username]*

PARAMETER

username

Specifies a user's login name. If you omit the user name, the current user's information is tested.

EXAMPLE

```
$ MULTINET TOKEN SNK /TEST  
SNK authentication for principal "holmes"  
Challenge: 645-3152  
Response: 6D665D62  
Authentication successful
```

To test an SNK token, enter your PIN into the keypad and press **ENT**. When the Challenge prompt appears, enter the displayed number into the keypad and press **ENT**. Enter the generated number at the Response prompt. The response is not case-sensitive; you can enter hexadecimal letters in uppercase or lowercase interchangeably.

Chapter 3

DECNET-CONFIG Command Reference

This chapter describes the commands you can run from the DECNET-CONFIG command line. DECNET-CONFIG lets you examine, modify, and save configuration files for DECnet-over-IP circuits.

To invoke DECNET-CONFIG:

```
$ MULTINET CONFIGURE /DECNET
```

At any DECNET-CONFIG prompt, type ? to list the available commands. Use the DECNET-CONFIG HELP command to view online help for each DECNET-CONFIG command.

Changes do not take effect until you do one of the following:

- Restart the DECnet-over-IP driver with the command @MULTINET:DECNET-CIRCUITS.COM.
- Restart your system.

For details on configuring DECnet-over-IP circuits, refer to the *MultiNet for OpenVMS Installation and Administrator's Guide*.

Command Summary

Table 3-1 lists the commands you can use from the DECNET-CONFIG prompt.

Table 3-1 DECNET-CONFIG Command Summary

Command	Description
ADD	Adds a DECnet-over-IP circuit to the current configuration.
ATTACH	Attaches to a subordinate process.
CLEAR	Deletes all DECnet-over-IP circuits from the current configuration; same as ERASE.

Table 3-1 DECNET-CONFIG Command Summary (Continued)

Command	Description
DELETE	Deletes a single DECnet-over-IP circuit from the current configuration.
ERASE	Deletes all DECnet-over-IP circuits from the current configuration; same as CLEAR.
EXIT	Exits DECNET-CONFIG and saves the current configuration.
GET	Reads in a DECnet-over-IP circuit configuration file; same as USE.
HELP	Displays command information.
MODIFY	Changes the parameters in a DECnet-over-IP circuit configuration file.
PUSH	Accesses the DCL command line and pauses DECNET-CONFIG.
QUIT	Exits DECNET-CONFIG, but prompts to save changes before exiting.
SAVE	Writes out the DECNET-CONFIG current configuration file; same as WRITE.
SHOW	Displays the current DECnet-over-IP circuit configuration.
SPAWN	Executes a single DCL command or starts a subprocess.
STATUS	Displays the status of the DECnet-over-IP circuit configuration.
USE	Reads in a DECnet-over-IP circuit configuration file; same as GET.
VERSION	Displays DECNET-CONFIG version and release information.
WRITE	Writes out the current DECNET-CONFIG configuration file; same as SAVE.

ADD

Adds a new DECnet-over-IP circuit to the current MultiNet configuration, and prompts for circuit configuration parameters.

FORMAT

ADD [*circuit_name*]

PARAMETER

circuit_name

Specifies the name of the DECnet circuit to add to the configuration. If not specified in the command, the first unused circuit in the configuration is used by default.

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
DECNET-CONFIG>ADD
[Adding new configuration entry for DECnet circuit "TCP-0-0"]
Destination IP Address: [NONE] 192.0.0.6
DECnet circuit cost: [1] 1
DECnet hello timer (in seconds): [300] 300
[TCP-0-0 => 192.0.0.6 (Cost=1, Hello Timer=300)
DECNET-CONFIG>EXIT
[Writing configuration to MULTINET:DECNET-CIRCUITS.COM]
$
```

ATTACH

Detaches the terminal from the calling process and reattaches it to another process. Use the SPAWN SHOW PROCESS /SUBPROCESSES command to list the names of the subprocesses. Use the DCL LOGOUT command to return to the original process. If the MULTINET_DISABLE_SPAWN logical is enabled, ATTACH does not work.

FORMAT

ATTACH *process-name*

PARAMETER

process-name

Specifies the name of a process to which you want your terminal attached. (Not all subprocesses can be attached; some testing may be required.)

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM
DECNET-CONFIG>SPAWN
$ MM
MM>SPAWN SHOW PROCESS/SUB
...
There are 3 processes in this job:
_TWA42:
PROC_1
PROC_2 (*)
MM>ATTACH _TWA42:
DECNET-CONFIG>ATTACH PROC_1
MM>QUIT
$ LOGOUT
DECNET-CONFIG>
```

This example shows the use and exit of attached subprocesses.

- 1 The first command uses SPAWN to create a subprocess. MM is invoked from the DCL command line. Next, the SPAWN SHOW PROCESS/SUB command is used to list all subprocess names. The display shows that three subprocesses are active. (Process _TWA42: is DECNET-CONFIG, PROC_1 is MM, and PROC_2 is the SPAWN SHOW PROCESS/SUB command.)
- 2 In the next command, the MM ATTACH command returns control to the DECNET-CONFIG process. From this utility, ATTACH returns control to MM. To exit, the QUIT command is invoked from MM, and LOGOUT is invoked at the original spawned DCL command line; control returns to DECNET-CONFIG. (If SPAWN SHOW PROCESS/SUB had been entered, only this command and the configuration processes would be active.)

CLEAR

Deletes all DECnet-over-IP circuits from the current MultiNet configuration.

FORMAT

CLEAR

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>CLEAR
DECNET-CONFIG>EXIT
$
```

DELETE

Deletes the specified DECnet-over-IP circuit from the current MultiNet configuration.

FORMAT

DELETE *circuit_name*

PARAMETER

circuit_name

Specifies the name of the DECnet-over-IP circuit to delete.

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET  
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]  
DECNET-CONFIG>DELETE TCP-0-0  
DECNET-CONFIG>EXIT  
$
```

ERASE

Clears all DECnet-over-IP circuits from the current MultiNet configuration. (Functionally equivalent to CLEAR.)

FORMAT

ERASE

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>ERASE
DECNET-CONFIG>EXIT
$
```

EXIT

Saves the current configuration, if it has been modified, then quits.

FORMAT

EXIT

EXAMPLES

If the configuration has not changed, a message displays indicating that the configuration file is not updated.

```
$ MULTINET CONFIGURE /DECNET  
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]  
DECNET-CONFIG>EXIT  
$
```

If the configuration has changed, a message displays indicating that the configuration file has been updated.

```
$ MULTINET CONFIGURE /DECNET  
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]  
DECNET-CONFIG>CLEAR  
DECNET-CONFIG>EXIT  
[Writing configuration to MULTINET:DECNET-CIRCUITS.COM}  
$
```

GET

Reads in a MultiNet DECnet-over-IP circuit configuration file, which defaults to the highest version number of the MULTINET:DECNET-CIRCUITS.COM file. (Functionally equivalent to USE.) After using GET, you can use other DECNET-CONFIG commands to display and modify the new configuration.

FORMAT

GET *config_file*

PARAMETER

config_file

Specifies the name of the configuration file to read in.

EXAMPLE

This example reads in the highest version number of the MULTINET_ROOT:[MULTINET]DECNET-CIRCUITS.COM configuration file. In this case, the highest version number is ";7". This number is appended to the file name as the value ".7".

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>GET
[Reading in configuration from MULTINET_ROOT:[MULTINET]DECNET-
CIRCUITS.COM.7]
DECNET-CONFIG>EXIT
$
```

HELP

Invokes the help command.

FORMAT

HELP [*topics*]

PARAMETER

topics

Contains a space-delimited list of topics that begins with a topic followed by subtopics. The default topic is **HELP**.

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>HELP ?
ADD          ATTACH  CLEAR    DELETE   ERASE     EXIT      GENERAL   GET
MODIFY      PUSH     QUIT    SAVE     SHOW      SPAWN     STATUS    USE
VERSION     WRITE
DECNET-CONFIG>
```

MODIFY

Changes the parameters of the specified DECnet-over-IP Circuit in the MultiNet configuration.

FORMAT

MODIFY *circuit_name*

PARAMETER

circuit_name

Specifies the name of the DECnet-over-IP circuit whose parameters will be modified.

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
DECNET-CONFIG>MODIFY TCP-0-0
[Adding new configuration entry for DECnet circuit "TCP-0-0"]
Destination IP Address: [192.0.0.6]
DECnet circuit cost: [1] 5
DECnet hello timer (in seconds): [300]
[TCP-0-0 => 192.0.0.6 (Cost=5, Hello Timer=300)]
DECNET-CONFIG>EXIT
$
```

PUSH

Starts and attaches a DCL subprocess. If a parent process exists, attach to it. To return from DCL, use the ATTACH or the LOGOUT command. To switch back from a DCL subprocess, use the ATTACH command.

If the MULTINET_DISABLE_SPAWN logical is set, PUSH does not work.

FORMAT

PUSH

EXAMPLE

In this example, PUSH is used to access the DCL command line to disable broadcasts. The LOGOUT command returns control to DECNET-CONFIG.

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>PUSH
$ SET TERM /NOBROADCAST
$ LOGOUT
DECNET-CONFIG>
```


QUIT

If the configuration file has been edited, QUIT prompts you to save the file before quitting.

FORMAT

QUIT

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>QUIT
Configuration modified, do you want to save it ? [NO]NO
```

SAVE

Writes out the current configuration file. (Functionally equivalent to **WRITE**; see **WRITE** for additional information.)

SHOW

Displays the current MultiNet DECnet-over-IP circuit configuration.

FORMAT

SHOW

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>SHOW
Circuit Name      IP Destination      Cost      Hello Timer
-----
TCP-0-0           192.26.30.1         1         300
DECNET-CONFIG>QUIT
```

SPAWN

Executes a single DCL command, or if entered without options, starts a subprocess with the same effect as PUSH. To return from DCL, use the LOGOUT command. If the MULTINET_DISABLE_SPAWN logical is set, SPAWN does not work.

FORMAT

SPAWN [*command*]

PARAMETER

command

Specifies a command to execute. If you omit *command*, a DCL command line subprocess is created.

QUALIFIERS

/INPUT=file-spec

Specifies an input file to the command you enter with SPAWN.

/LOGICAL_NAMES

/NOLOGICAL_NAMES

Specifies that logical names and logical name tables are not copied to the subprocess.

/SYMBOLS

/NOSYMBOLS

Specifies that global and local names are not passed to the subprocess.

/WAIT

/NOWAIT

Returns control without waiting for the command to complete. Do not use this qualifier with commands that have prompts or screen displays.

/OUTPUT=file-spec

Specifies a file that retains the output of the command invoked with SPAWN. This qualifier only works when a single command is entered without creating a DCL subprocess. In addition, this qualifier is positional; you must enter it immediately after SPAWN or other qualifiers.

EXAMPLES

This example displays terminal information, captures the output in a file, and displays the information with the TYPE command.

```
$ MULTINET CONFIGURE /DECNET
```

```
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
```

```
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>SPAWN/OUTPUT=FOO. SHOW TERM
DECNET-CONFIG>SPAWN TYPE FOO.
...
```

This example invokes a command procedure.

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>SPAWN @COMPROC
...
```

This example displays help information about DECNET-CONFIG. Use the LOGOUT command to return control to DECNET-CONFIG.

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>SPAWN
$ HELP MULTINET CONFIGURE /DECNET ...
$ LOGOUT
DECNET-CONFIG>
```

STATUS

Displays the status of the MultiNet DECnet-over-IP circuit configuration.

FORMAT

STATUS

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>STATUS
This is the MultiNet DECnet circuit configuration program Version 4.4
(nnn)
There are 1/100 circuits in the current configuration.
The configuration MULTINET:DECNET-CIRCUITS.COM is not modified.
DECNET-CONFIG>QUIT
$
```

USE

Reads in a configuration file. (Functionally equivalent to GET; see GET for additional information.)

FORMAT

USE *config_file*

PARAMETER

config_file

Specifies the name of the configuration file to read in.

VERSION

Displays the version and release information of the MultiNet DECnet-over-IP circuit configuration program.

FORMAT

VERSION

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>VERSION
This is the MultiNet DECnet circuit configuration program Version 4.4
(nnn)
DECNET-CONFIG>QUIT
$
```


WRITE

Writes the current MultiNet DECnet-over-IP circuit configuration to a file. (Functionally equivalent to SAVE.)

FORMAT

WRITE [*config_file*]

PARAMETER

config_file

Specifies the name of the DECnet-over-IP circuit configuration file to write out (by default, the same file from which the configuration was read).

EXAMPLE

```
$ MULTINET CONFIGURE /DECNET
MultiNet DECNET Circuit Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:DECNET-CIRCUITS.COM]
DECNET-CONFIG>WRITE
[Writing configuration to MULTINET_ROOT:[MULTINET]DECNET CIRCUITS.COM.2]
DECNET-CONFIG>EXIT
```


Chapter 4

MAIL-CONFIG Command Reference

This chapter describes the commands you can run from the MAIL-CONFIG command line. MAIL-CONFIG lets you examine, modify, and save configuration files for the MultiNet SMTP mail system.

To invoke MAIL-CONFIG:

```
$ MULTINET CONFIGURE /MAIL
```

At any MAIL-CONFIG prompt, type ? to list the available commands. Use the MAIL-CONFIG HELP command to view online help for each MAIL-CONFIG command.

Changes do not take effect until you do one of the following:

- Restart the SMTP service with the @MULTINET:START_SMTP.COM or @MULTINET:START_SMTP_LOCAL.COM commands.
- Restart your system.

For details on configuring electronic mail, refer to the *MultiNet for OpenVMS Installation and Administrator's Guide*.

Command Summary

Table 4-1 lists the commands you can run from the MAIL-CONFIG prompt.

Table 4-1 MAIL-CONFIG Command Summary

MAIL-CONFIG Command	Description
ADD GATEWAY	Adds a mail gateway to another domain.

Table 4-1 MAIL-CONFIG Command Summary (Continued)

MAIL-CONFIG Command	Description
ADD LOCAL-DOMAIN	Adds a domain to a list of domains that the MultiNet SMTP symbiont considers to be local. If users send mail to hosts beyond the local domains, MultiNet forwards the mail to the mail hub specified by the FORWARDER parameter. The local domain list affects mail forwarding only when the FORWARD-REMOTE-MAIL parameter is TRUE.
ADD QUEUE-GROUP	Forms a mail queue grouping of nodes in a cluster, or adds new nodes to an existing queue group.
ATTACH	Attaches your terminal to another process.
CLEAR	Erases all information from the current configuration; same as ERASE.
DELETE GATEWAY	Deletes a mail gateway.
DELETE LOCAL-DOMAIN	Deletes a domain from MultiNet's list of local domains.
DELETE QUEUE-GROUP	Deletes a queue group or removes a node from a queue group. When a node is removed from a named queue group, it becomes part of the default queue group.
ERASE	Erases all information from the current configuration; same as CLEAR.
EXIT	Saves the configuration file and exits from MAIL-CONFIG.
GET	Reads in a MultiNet SMTP configuration file. (Functionally equivalent to USE.)
HELP	Invokes MAIL-CONFIG command help.
PUSH	Accesses the DCL command interpreter.
QUIT	Prompts you to save the configuration file if it has been modified, then exits MAIL-CONFIG.
REMOVE GATEWAY	Functionally equivalent to DELETE GATEWAY.
REMOVE QUEUE-GROUP	Functionally equivalent to DELETE QUEUE-GROUP.
SAVE	Saves the current configuration file.

Table 4-1 MAIL-CONFIG Command Summary (Continued)

MAIL-CONFIG Command	Description
SET ACCOUNTING-HOST	Sets the host that SMTP accounting information should be sent to.
SET ACCOUNTING-PORT	Sets the port that the accounting logger is to listen on.
SET ALIAS-FILE	Identifies the file that holds mail aliases.
SET DECNET-DOMAIN	Sets the domain name for DECnet mail.
SET DELIVERY-RECEIPTS	Specifies whether mail receipts are sent when incoming mail containing Delivery-Receipt-To: or Return-Receipt-To: headers is submitted to the SMTP queue.
SET DISABLE-PSMAIL	When TRUE, the MultiNet SMTP symbiont looks for messages addressed through PSImail, usually of the form PSI%address::user, and returns them to the sender marked user unknown.
SET DISALLOW-USER-REPLY-TO	When set to TRUE, prevents VMS MAIL users from setting a Reply-To: header address with the logical name MULTINET_SMTP_REPLY_TO.
SET FORWARDER	Specifies the host that will forward mail messages to other hosts.
SET FORWARD-LOCAL-MAIL	Forwards mail addressed to users on the local host to a central mail hub specified by the FORWARDER parameter.
SET FORWARD-REMOTE-MAIL	Forwards mail addressed to users on non-local hosts to a central mail hub specified by the FORWARDER parameter.
SET HEADER-CONTROL	Specifies which RFC-822 message headers should be included in messages delivered to local VMS MAIL users.
SET HOST-ALIAS-FILE	Specifies a file from which MultiNet obtains a list of hosts aliases.
SET LOCAL-MAIL-FORWARDER	Forwards local mail to a specific host.
SET POSTMASTER	Identifies the user responsible for mail on the system.
SET QUEUE-COUNT	Specifies the number of mail processing queues that should be created on a particular system.

Table 4-1 MAIL-CONFIG Command Summary (Continued)

MAIL-CONFIG Command	Description
SET REPLY-CONTROL	Specifies how Internet mail headers should be mapped to the VMS MAIL "From" header.
SET RESENT-HEADERS	When FALSE, the MultiNet SMTP symbiont omits the Resent-From, Resent-To, and Resent-Date headers that are usually included when a message is forwarded using a VMS MAIL forwarding address.
SET RETRY-INTERVAL	Specifies the amount of time that elapses before another attempt is made to send a message after a failed attempt.
SET RETURN-INTERVAL	Specifies the amount of time that a message can remain in the processing queue before it is returned to sender.
SET RFC2789	Enables the start up of the Mail Monitoring MIB (RFC 2789). Requires SNMP AGENTX to be set.
SET SEND-BROADCAST-CLASS	Specifies the broadcast class to use to deliver immediate SEND messages.
SET SMTP-HOST-NAMES	Sets the host name from which all outgoing mail appears to be sent and aliases for which this host accepts incoming mail.
SET START-QUEUE-MANAGER	Determines whether START_SMTP.COM starts the VMS queue manager if it is not already running.
SHOW	Displays the current configuration.
SPAWN	Executes a single DCL command.
STATUS	Indicates whether the SMTP configuration has been modified.
USE	Reads in a non-standard configuration file.
VERSION	Displays the MAIL-CONFIG version and release information.
WRITE	Saves the current configuration file.

ADD GATEWAY

Adds a mail gateway to another domain. Specifies a gateway host to which mail for the specified host or domain will be forwarded.

Note! To define a mail gateway to an IP address (instead of a host name), you must enclose the IP address in square brackets.

FORMAT

ADD GATEWAY *domain_name hostname*

PARAMETERS

domain_name

Specifies the name of the domain for which the new gateway will handle mail. This can be a fully qualified host name (for example, WHORFIN.FLOWERS.COM) or a domain tag beginning with a dot (for example, .BITNET).

hostname

Specifies the name of the host that acts as a gateway for mail addressed to domain_name.

ADD LOCAL-DOMAIN

Adds a domain to a list of domains that the MultiNet SMTP symbiont considers to be local. If users send mail to hosts beyond the local domains, MultiNet forwards the mail to the mail hub specified by the FORWARDER parameter. The local domain list affects mail forwarding only when the FORWARD-REMOTE-MAIL parameter is TRUE.

FORMAT

ADD LOCAL-DOMAIN *domain_name*

PARAMETER

domain_name

Specifies the name of a domain (for example, LOT-49.FLOWERS.COM) that MultiNet considers to be local.

ADD QUEUE-GROUP

Forms a mail queue grouping of nodes in a cluster, or adds new nodes to an existing queue group. The SMTP queues on the nodes in the group you create will share responsibility for handling mail messages generated on nodes within the group. If a node is not placed in a named queue group, it is made part of the default queue group.

FORMAT

ADD QUEUE-GROUP *groupname [node_name_list]*

PARAMETERS

groupname

Specifies the name of the queue group to add, or the name of an existing group to which nodes will be added.

node_name_list

Contains a list of names of VMScluster (SCS) nodes to add to the queue group.

ATTACH

Detaches the terminal from the calling process and reattaches it to another process. Use the SPAWN SHOW PROCESS /SUBPROCESSES command to list the names of the subprocesses. Use the DCL LOGOUT command to return to the original process. If the MULTINET_DISABLE_SPAWN logical is enabled, ATTACH does not work.

FORMAT

ATTACH *process-name*

PARAMETER

process_name

Specifies the name of a process to which you want your terminal attached. (Not all subprocesses can be attached; some testing may be required.)

CLEAR

Clears all information from the current configuration. (Functionally equivalent to ERASE.)

FORMAT

CLEAR

DELETE GATEWAY

Deletes a mail gateway.

FORMAT

DELETE GATEWAY *domain_name*

PARAMETER

domain_name

Specifies the name of the domain whose gateway will be deleted.

DELETE LOCAL-DOMAIN

Deletes a domain from MultiNet's list of local domains.

FORMAT

DELETE LOCAL-DOMAIN *domain_name*

PARAMETER

domain_name

Specifies the name of the domain to delete from the list of local domains.

DELETE QUEUE-GROUP

Deletes a queue group or removes a node from a queue group. When a node is removed from a named queue group, it becomes part of the default queue group.

FORMAT

DELETE QUEUE-GROUP *group_name* [*node_names*]

PARAMETERS

group_name

Specifies the name of the group to delete or the name of the group from which to remove the specified nodes.

node_names

Specifies the VMScluster (SCS) node name to remove from the specified queue group.

ERASE

Erases all information from the current configuration. (Functionally equivalent to CLEAR.)

FORMAT

ERASE

EXIT

Saves the current configuration, if it has been modified, then quits.

FORMAT

EXIT

GET

Reads in a MultiNet SMTP configuration file. (Functionally equivalent to USE.) After a GET, you can use the various configuration commands to modify the SMTP configuration.

FORMAT

GET *config_file*

PARAMETER

config_file

Specifies the name of the SMTP configuration file to read in.

HELP

Invokes command help.

FORMAT

HELP [*topics*]

PARAMETER

topics

Contains a space-delimited list of topics that begins with a topic followed by subtopics. The default topic is **HELP**.

PUSH

Starts and attaches a DCL subprocess. If a parent process exists, attach to it. To return from DCL, use the ATTACH or the LOGOUT command. To switch back from a DCL subprocess, use the ATTACH command.

If the MULTINET_DISABLE_SPAWN logical is set, PUSH does not work.

FORMAT

PUSH

QUIT

If the configuration file has been edited, QUIT prompts you to save the file before quitting.

FORMAT

QUIT

REMOVE GATEWAY

Functionally equivalent to DELETE GATEWAY.

FORMAT

REMOVE GATEWAY *domain_name*

PARAMETER

domain_name

Specifies the name of the gateway to remove.

REMOVE QUEUE-GROUP

Functionally equivalent to DELETE QUEUE-GROUP.

FORMAT

REMOVE QUEUE-GROUP *group_name [node_names]*

PARAMETERS

group_name

Specifies the name of the group to remove or the name of the group from which to remove the specified nodes.

node_names

Specifies the VMScluster (SCS) node name to remove from the specified queue group.

SAVE

Writes the current MultiNet SMTP configuration to SMTP configuration files. (Functionally equivalent to WRITE.)

FORMAT

SAVE *config_file*

PARAMETER

config_file

Specifies the name of the file to which to write the current MultiNet SMTP configuration (by default, the same file from which it was read).

SET ACCOUNTING-HOST

Sets the host that SMTP accounting information should be sent to.

FORMAT

SET ACCOUNTING-HOST *hostname*

PARAMETER

hostname

Specifies the name of the host that SMTP accounting information should be sent to. Accounting-Port must be specified also.

SET ACCOUNTING-PORT

Sets the port that the accounting logger is to listen on.

FORMAT

SET ACCOUNTING-PORT *port number*

PARAMETER

port number

Specifies the port number that the accounting logger is listening on. Accounting-Host must be specified also.

SET ALIAS-FILE

Identifies the file that holds system-wide mail aliases.

FORMAT

SET ALIAS-FILE [*file-spec*]

PARAMETER

file-spec

Specifies the name of the file that contains system-wide mail aliases (by default, MULTINET:SMTP_ALIASES).

SET DECNET-DOMAIN

Sets the domain name for DECnet mail.

FORMAT

SET DECNET-DOMAIN *domain_name*

PARAMETER

domain_name

Specifies the domain name for DECnet mail. For information on the SMTP-DECnet gateway, see the *MultiNet for OpenVMS Installation and Administrator's Guide*.

SET DELIVERY-RECEIPTS

Specifies whether mail receipts are sent when incoming mail containing Delivery-Receipt-To: or Return-Receipt-To: headers is submitted to the SMTP queue. If TRUE, mail receipts are sent.

FORMAT

SET DELIVERY-RECEIPTS { TRUE | FALSE }

SET DISALLOW-USER-REPLY-TO

When set to TRUE, prevents VMS MAIL users from setting a Reply-To: header address with the MULTINET_SMTP_REPLY_TO logical name.

FORMAT

SET DISALLOW-USER-REPLY-TO { TRUE | FALSE }

SET DISABLE-PSIMAIL

When TRUE, the MultiNet SMTP symbiont looks for messages addressed through PSImail, usually of the form PSI%address::user, and returns them to the sender marked user unknown. The default is FALSE. This parameter does not affect mail delivery to local users who have set up forwarding entries to PSImail addresses with the VMS MAIL SET FORWARD command.

FORMAT

SET DISABLE-PSIMAIL { TRUE | FALSE }

SET FORWARDER

Specifies the host that will forward mail messages to other hosts.

FORMAT

SET FORWARDER *[host_name]*

PARAMETER

host_name

Specifies the name of the host to which mail is forwarded when attempts by the local system to send mail to a remote system fail because of a host name lookup failure.

If no host name is specified, no forwarder is used, and failed messages are tried repeatedly (based on the RETRY-INTERVAL setting) until they are returned to sender (based on the RETURN-INTERVAL setting).

SET FORWARD-LOCAL-MAIL

When TRUE, MultiNet forwards mail addressed to users on the local host to a central mail hub specified by the FORWARDER parameter.

FORMAT

SET FORWARD-LOCAL-MAIL { TRUE | FALSE }

DESCRIPTION

To configure MultiNet to direct mail to a central mail hub, you must specify the IP address of the mail hub with the FORWARDER parameter, and define the scope of addresses that you want the mail hub to handle.

By default, when users on the same MultiNet host send mail to each other, MultiNet does not route the messages through the mail hub. When FORWARD-LOCAL-MAIL is TRUE, MultiNet forwards local mail to the mail hub.

To exclude a specific user from the local mail-forwarding system, add the following type of mail alias to MULTINET:SMTP_ALIASES:

```
username : *;
```


SET FORWARD-REMOTE-MAIL

When TRUE, MultiNet forwards mail addressed to non-local users on a central mail hub specified by the FORWARDER parameter.

FORMAT

SET FORWARD-REMOTE-MAIL { TRUE | FALSE }

DESCRIPTION

To configure MultiNet to direct mail to a central mail hub, you must specify the IP address of the mail hub with the FORWARDER parameter, and define the scope of addresses that you want the mail hub to handle.

By default, when MultiNet users send mail to users on other hosts, MultiNet does not route the messages through the mail hub. When FORWARD-REMOTE-MAIL is TRUE, MultiNet forwards non-local mail to the mail hub.

By default MultiNet considers all remote hosts non-local. You can add hosts in other domains to the local-domain list with the ADD LOCAL-DOMAIN command.

SET HEADER-CONTROL

Specifies which RFC-822 message headers are included in messages delivered to local VMS MAIL users.

FORMAT

SET HEADER-CONTROL *header_type*

PARAMETER

header_type

Either NONE, MAJOR, or ALL.

- NONE eliminates the RFC-822 message headers from locally delivered VMS MAIL messages.
- MAJOR (the default) includes all but Received and Return Path headers.
- ALL includes all headers.

SET HOST-ALIAS-FILE

Specifies a file from which MultiNet obtains a list of host aliases. A common use for SMTP host names is when your system is a member of a homogeneous VMScluster, and you want all mail from any cluster member to appear to be from the same host (for example, the cluster alias).

Unlike the MAIL-CONFIG SET SMTP-HOST-NAMES command which has a limit of 16 host names, SET HOST-ALIAS-FILE lets you specify a host alias file containing as many host aliases as needed.

Note! The host name or alias you specify should be registered in the Domain Name System or in the host tables of any system to which you send mail; otherwise, the recipients of your mail will be unable to reply to it.

If this logical name is not defined, the SMTP software looks for the file MULTINET:SMTP_HOST_ALIASES by default.

FORMAT

SET HOST-ALIAS-FILE *file_spec*

PARAMETER

file_spec

Specifies the file that contains a list of SMTP host names.

SET LOCAL-MAIL-FORWARDER

Forwards failed local mail to a specific host.

FORMAT

SET LOCAL-MAIL-FORWARDER *hostname*

PARAMETER

hostname

Specifies the name of the host to which failed local mail is directed.

SET POSTMASTER

Identifies the user responsible for mail on the system.

FORMAT

SET POSTMASTER *[username]*

PARAMETER

username

Specifies the name of the user who will receive messages addressed to Postmaster on the local host. If omitted, the user name POSTMASTER is used.

To assign multiple users as the postmaster, enter POSTMASTER, then create an alias for postmaster in the alias file. For example, to make both "username1" and "username2" postmasters, enter the following line in the alias file:

```
postmaster:      username1, username2;
```

SET QUEUE-COUNT

Specifies the number of mail processing queues that should be created on a system.

FORMAT

SET QUEUE-COUNT *node_name* [*count*]

PARAMETER

node_name

Specifies the VMScluster (SCS) node name of the node whose queue count you wish to set, or specifies DEFAULT to set the default for all nodes not specifically set. In a non-cluster environment, only the DEFAULT setting is used.

count

Specifies the number of queues to create on the specified node. If a count is omitted, the queue-count setting for the specified node is removed.

SET REPLY-CONTROL

Specifies how Internet mail headers are mapped to the VMS MAIL "From" header.

FORMAT

SET REPLY-CONTROL *[hdr_types]*

PARAMETER

hdr_types

Specifies a comma-delimited list of SMTP headers (ENVELOPE-FROM, FROM, or REPLY-TO) that are mapped to the VMS MAIL "From" header. The default is "ENVELOPE-FROM, FROM, REPLY-TO."

SET RESENT-HEADERS

When FALSE, the MultiNet SMTP symbiont omits the Resent-From, Resent-To, and Resent-Date headers that are usually included when a message is forwarded using a VMS MAIL forwarding address. The default is TRUE.

Use this option if mail user agents at your site cannot properly distinguish between normal "From" headers and "Resent-From" headers.

FORMAT

SET RESENT-HEADERS { TRUE | FALSE }

SET RETRY-INTERVAL

Specifies the amount of time that elapses before another attempt is made to send a message after a failed attempt.

FORMAT

SET RETRY-INTERVAL *[interval]*

PARAMETER

interval

Specifies the interval, in minutes (by default, 30 minutes).

SET RETURN-INTERVAL

Specifies the amount of time that a message can remain in the processing queue before it is returned to the sender.

FORMAT

SET RETURN-INTERVAL *[interval]*

PARAMETER

interval

Specifies the interval, in hours; by default, 96 (four days). A message typically only remains in the processing queue if it cannot be sent over the network to a remote host. When such a message is returned to its sender, the returned message includes the reason why it could not be sent.

SET RFC2789

Enables the start up of the Mail Monitoring MIB (RFC 2789). Requires SNMP AGENTX to be set.

FORMAT

SET RFC2789

SET SEND-BROADCAST-CLASS

Specifies the broadcast class to use to deliver immediate (SEND) messages.

FORMAT

SET SEND-BROADCAST-CLASS [*class_number*]

PARAMETER

class_number

Specifies the class-number in a range from 1 to 16, corresponding to the VMS USER1 through USER16 broadcast classes (by default, 16).

SET SMTP-HOST-NAMES

Sets the host name from which all outgoing mail appears to be sent and the aliases for which this host accepts incoming mail.

A common use for SMTP HOST NAME is when your system is a member of a homogeneous VMScluster, and you want all mail from any cluster member to appear to be from the same host.

FORMAT

SET SMTP-HOST-NAMES *host_names*

PARAMETER

host_names

Contains a comma-delimited list of host names. The first name in the list specifies the host name from which all outgoing mail appears to be sent. The remaining host names in the list specify the aliases for which this host accepts incoming mail.

Note! The specified host name or alias should be registered in the Domain Name System or in the host tables of any system that you send mail to; otherwise, the recipients of your mail will be unable to reply to it.

SET START-QUEUE-MANAGER

Determines whether START_SMTP.COM starts the VMS queue manager if it is not already running. The default is TRUE.

FORMAT

SET START-QUEUE-MANAGER { TRUE | FALSE }

SHOW

Displays the current configuration.

FORMAT

SHOW

SPAWN

Executes a single DCL command, or if entered without options, starts a subprocess with the same effect as PUSH. To return from DCL, use the LOGOUT command. If the MULTINET_DISABLE_SPAWN logical is set, SPAWN does not work.

FORMAT

SPAWN [*command*]

PARAMETER

command

Specifies a command to execute. If you omit command, a DCL command line subprocess is created.

QUALIFIERS

/INPUT=file-spec

Specifies an input file to the command you enter with SPAWN.

/LOGICAL_NAMES

/NOLOGICAL_NAMES

Specifies that logical names and logical name tables are not copied to the subprocess.

/SYMBOLS

/NOSYMBOLS

Specifies that global and local names are not passed to the subprocess.

/WAIT

/NOWAIT

Returns control without waiting for the command to complete. Do not use this qualifier with commands that have prompts or screen displays.

/OUTPUT=file-spec

Specifies a file that retains the output of the command invoked with SPAWN. This qualifier only works when a single command is entered without creating a DCL subprocess. In addition, this qualifier is positional; you must enter it immediately after SPAWN or other qualifiers.

STATUS

Indicates whether the SMTP configuration has been modified.

FORMAT

STATUS

USE

Reads in a MultiNet SMTP configuration file. After a USE, you can use the various configuration commands to modify the SMTP configuration. (Functionally equivalent to GET.)

FORMAT

USE *config_file*

PARAMETER

config_file

Specifies the name of the SMTP configuration file to read in.

VERSION

Displays the MAIL-CONFIG version and release information.

FORMAT

VERSION

WRITE

Writes the current MultiNet SMTP configuration to SMTP configuration files. (Functionally equivalent to SAVE.)

FORMAT

WRITE *config_file*

PARAMETER

config_file

Specifies the name of the file to which to write the current MultiNet SMTP configuration. By default, the configuration is saved to the same file from which it was read.

Chapter 5

NET-CONFIG Command Reference

This chapter describes the commands you can run from the NET-CONFIG command line. NET-CONFIG lets you examine, modify, and save configuration files for MultiNet network interfaces.

To invoke NET-CONFIG:

```
$ MULTINET CONFIGURE /INTERFACES
```

At any NET-CONFIG prompt, you can list the available commands by typing "?". Online help for each NET-CONFIG command is available through the NET-CONFIG HELP command.

Of the SET commands, the SET LOAD-EXOS-DRIVER and SET WINS-COMPATIBILITY commands require that you reboot the system after you use the command; all other SET commands can be executed without rebooting the system.

For details on configuring network interfaces, refer to the *MultiNet for OpenVMS Installation and Administrator's Guide*.

NET-CONFIG Command Summary

Table 5-1 lists the commands you can run from the NET-CONFIG prompt.

Table 5-1 NET-CONFIG Command Summary

NET-CONFIG Command	Description
ADD	Adds a device to the network configuration.
ATTACH	Attaches a terminal to a process.
CHECK	Performs a check on the current configuration.
CLEAR	Deletes all devices from the network configuration.
DELETE	Deletes a single device from the network configuration.

Table 5-1 NET-CONFIG Command Summary (Continued)

NET-CONFIG Command	Description
DISABLE	Disables a device and deletes it from the configuration.
ENABLE	Enables a device.
ERASE	Deletes all devices from the network configuration.
EXIT	Exits NET-CONFIG and saves the configuration if it changed.
GET	Reads in a nonstandard configuration file.
HELP	Displays command help information.
MODIFY	Changes a device configuration.
PUSH	Accesses the DCL command interpreter.
QUIT	Exits NET-CONFIG and prompts to save the configuration if it changed.
SAVE	Writes configuration parameters to a file.
SET ANONYMOUS-FTP-DIRECTORY	Restricts anonymous FTP directory access.
SET CLUSTER-SERVICE-ADDRESS	Identifies the IP address to use when responding to address queries from hosts specified by CLUSTER-SERVICE-NAMES.
SET CLUSTER-SERVICE-NAMES	Lists the host names to use for load balancing.
SET DEFAULT-RMT-TAPE-DEVICE	Defines the default RMT server tape device.
SET DEFAULT-ROUTE	Defines the default IP route.
SET DOMAIN-NAMESERVERS	Configures the DNS domain resolver.
SET HOST-NAME	Defines the local host name and domain.
SET IP-CLUSTER-ALIASES	Specifies a list of cluster-wide Internet addresses to which this node responds.
SET LOAD-EXOS-DRIVER	Enables automatic loading of the Novell EXOS-compatible \$QIO driver when MultiNet starts.

Table 5-1 NET-CONFIG Command Summary (Continued)

NET-CONFIG Command	Description
SET LOCAL-DOMAIN	Overrides the default local domain derived from previous use of the SET HOST-NAME command.
SET LPD-DEFAULT-USERNAME	Specifies a default user name for print jobs received from a remote machine via the LPD protocol.
SET NAMESERVER-RETRANSMISSION	Specifies a time between and the number of name server requests that are made before the system stops sending name server requests to a nonresponding server.
SET SPOOL-DIRECTORY	Sets the default spool directory name.
SET TFTP-DIRECTORY	Sets the default directory for the TFTP server.
SET TIMEZONE	Sets the local timezone.
SET TIMEZONE-RULES	Specifies the timezone rules file name.
SET WHOIS-DEFAULT-SERVER	Sets the default WHOIS server.
SET WINS-COMPATIBILITY	Defines the logical names used with the WIN/TCP and Pathway products from The Wollongong Group.
SHOW	Displays the current configuration or device names.
SPAWN	Executes a DCL command.
STATUS	Displays the device count in the configuration.
USE	Reads in a nonstandard configuration file.
VERSION	Displays the NET-CONFIG and VMS versions.
WRITE	Writes the current configuration.

ADD

Adds a device to the network configuration.

FORMAT

ADD *interface*

PARAMETERS

interface

Specifies the name of the device interface to add.

Refer to Table 5-2 for a list of supported network interfaces and the corresponding interface parameters for which you are prompted. For descriptions of interface parameters, refer to Table 5-3.

Table 5-2 Interfaces and Parameters

Type	Description										
dn	<p>Interface name: dn0, dn1, dn2, ... Device type: IP-over-DECnet link</p> <table><tr><th>Parameter Prompt</th><th>Example Value</th></tr><tr><td>IP Over DECnet Peer Host's DECnet Name:</td><td>YOYODY</td></tr><tr><td>IP Address:</td><td>192.41.228.70</td></tr><tr><td>Point-To-Point Device IP Destination Address:</td><td>192.41.228.71</td></tr><tr><td>IP SubNet Mask:</td><td>225.225.225.0</td></tr></table> <p>The dn interface encapsulates IP datagrams inside a DECnet connection. This encapsulation allows you to make an IP point-to-point connection across an arbitrary DECnet network. Rather than sending the IP packets to a hardware device for transmission, MultiNet forwards them through the DECnet network.</p> <p>Configure one of these interfaces on each side of the link. The DECnet link is established automatically during the boot process.</p>	Parameter Prompt	Example Value	IP Over DECnet Peer Host's DECnet Name:	YOYODY	IP Address:	192.41.228.70	Point-To-Point Device IP Destination Address:	192.41.228.71	IP SubNet Mask:	225.225.225.0
Parameter Prompt	Example Value										
IP Over DECnet Peer Host's DECnet Name:	YOYODY										
IP Address:	192.41.228.70										
Point-To-Point Device IP Destination Address:	192.41.228.71										
IP SubNet Mask:	225.225.225.0										
nsip	<p>Interface name: nsip0, nsip1, ... nsip9 Device type: IPX-over-IP tunnel</p> <table><tr><th>Parameter Prompt</th><th>Example Value</th></tr><tr><td>NETWARE Network Number:</td><td>12B4</td></tr><tr><td>IP address of remote system:</td><td>192.41.228.70</td></tr></table> <p>The nsip interface provides access to IPX-over-IP for connecting to Novell's IP tunnel feature.</p>	Parameter Prompt	Example Value	NETWARE Network Number:	12B4	IP address of remote system:	192.41.228.70				
Parameter Prompt	Example Value										
NETWARE Network Number:	12B4										
IP address of remote system:	192.41.228.70										

Table 5-2 Interfaces and Parameters (Continued)

Type	Description												
pd	<p>Interface name: pd0 Device type: Secondary Ethernet Address</p> <table> <tr> <th>Parameter Prompt</th><th>Example Value</th></tr> <tr> <td>TCP/IP</td><td>161.44.128.21</td></tr> <tr> <td>Hardware-Device</td><td>se0</td></tr> <tr> <td>IP SubNet Mask</td><td>None</td></tr> <tr> <td>Non-Standard IP Broadcast Address:</td><td>None</td></tr> <tr> <td>pd0 (Secondary Ethernet Address):</td><td>Csr=None, Flags=%X0</td></tr> </table> <p>Careless assignment of a secondary address can cause network problems. In general, you should assign pseudo devices (pd) addresses on the same network or subnet as the se device to which the pd device is linked.</p> <p>If the pd interface is not in the same IP network as its associated se interface, some TCP/IP packages (such as early versions of SunOS) retransmit broadcast packets for the other IP network back to the network segment from which they were transmitted. This can cause network storms.</p> <p>Note! Some services listen to traffic on se interfaces only and ignore traffic on pd interfaces. One such service is the RIP listener in GATED.</p>	Parameter Prompt	Example Value	TCP/IP	161.44.128.21	Hardware-Device	se0	IP SubNet Mask	None	Non-Standard IP Broadcast Address:	None	pd0 (Secondary Ethernet Address):	Csr=None, Flags=%X0
Parameter Prompt	Example Value												
TCP/IP	161.44.128.21												
Hardware-Device	se0												
IP SubNet Mask	None												
Non-Standard IP Broadcast Address:	None												
pd0 (Secondary Ethernet Address):	Csr=None, Flags=%X0												

Table 5-2 Interfaces and Parameters (Continued)

Type	Description																																		
ppp	<p>Interface name: ppp0, ... Device type: Any supported PPP terminal interface</p> <table> <tr> <th>Parameter Prompt</th><th>Example Value</th></tr> <tr> <td>VMS Device:</td><td>TTA0:</td></tr> <tr> <td>Baud Rate:</td><td>19200</td></tr> <tr> <td>PPP ACCM Mask:</td><td>0</td></tr> <tr> <td>PPP Authentication Method:</td><td>None</td></tr> <tr> <td>PPP Protocol Compression:</td><td>OFF</td></tr> <tr> <td>PPP Address and Control Field Compression:</td><td>OFF</td></tr> <tr> <td>PPP Retry Count:</td><td>0</td></tr> <tr> <td>PPP Idle Timeout:</td><td>0</td></tr> <tr> <td>PPP MRU Size:</td><td>0</td></tr> <tr> <td>PPP ICMP:</td><td>ENABLED</td></tr> <tr> <td>PPP TCP Compression:</td><td>OFF</td></tr> <tr> <td>PPP Termination Retry Count:</td><td>0</td></tr> <tr> <td>PPP Timeout:</td><td>0</td></tr> <tr> <td>IP Address:</td><td>0.0.0.0</td></tr> <tr> <td>Point-to-Point Device IP Destination Address:</td><td>0.0.0.0</td></tr> <tr> <td>IP Subnet Mask:</td><td>255.0.0.0</td></tr> </table>	Parameter Prompt	Example Value	VMS Device:	TTA0:	Baud Rate:	19200	PPP ACCM Mask:	0	PPP Authentication Method:	None	PPP Protocol Compression:	OFF	PPP Address and Control Field Compression:	OFF	PPP Retry Count:	0	PPP Idle Timeout:	0	PPP MRU Size:	0	PPP ICMP:	ENABLED	PPP TCP Compression:	OFF	PPP Termination Retry Count:	0	PPP Timeout:	0	IP Address:	0.0.0.0	Point-to-Point Device IP Destination Address:	0.0.0.0	IP Subnet Mask:	255.0.0.0
Parameter Prompt	Example Value																																		
VMS Device:	TTA0:																																		
Baud Rate:	19200																																		
PPP ACCM Mask:	0																																		
PPP Authentication Method:	None																																		
PPP Protocol Compression:	OFF																																		
PPP Address and Control Field Compression:	OFF																																		
PPP Retry Count:	0																																		
PPP Idle Timeout:	0																																		
PPP MRU Size:	0																																		
PPP ICMP:	ENABLED																																		
PPP TCP Compression:	OFF																																		
PPP Termination Retry Count:	0																																		
PPP Timeout:	0																																		
IP Address:	0.0.0.0																																		
Point-to-Point Device IP Destination Address:	0.0.0.0																																		
IP Subnet Mask:	255.0.0.0																																		
psi	<p>Interface name: psi0, psi1, psi2, ... Device type: IP-over-PSI link</p> <table> <tr> <th>Parameter Prompt</th><th>Example Value</th></tr> <tr> <td>IP Over PSI peer DTE address:</td><td>0505233433000308</td></tr> <tr> <td>IP Over PSI local DTE address:</td><td>0505233433000309</td></tr> <tr> <td>IP Address:</td><td>192.41.228.70</td></tr> <tr> <td>Point-To-Point Device IP Destination Address:</td><td>192.41.228.71</td></tr> <tr> <td>IP SubNet Mask:</td><td>255.255.255.0</td></tr> </table> <p>The psi interface encapsulates IP datagrams inside a PSI connection. This encapsulation allows you to make an IP point-to-point connection across an arbitrary X.25 network. Rather than sending the IP packets to a hardware device for transmission, MultiNet forwards them through VMS PSI.</p> <p>Configure one of these interfaces on each side of the link. The X.25 link is established automatically during the boot process.</p>	Parameter Prompt	Example Value	IP Over PSI peer DTE address:	0505233433000308	IP Over PSI local DTE address:	0505233433000309	IP Address:	192.41.228.70	Point-To-Point Device IP Destination Address:	192.41.228.71	IP SubNet Mask:	255.255.255.0																						
Parameter Prompt	Example Value																																		
IP Over PSI peer DTE address:	0505233433000308																																		
IP Over PSI local DTE address:	0505233433000309																																		
IP Address:	192.41.228.70																																		
Point-To-Point Device IP Destination Address:	192.41.228.71																																		
IP SubNet Mask:	255.255.255.0																																		

Table 5-2 Interfaces and Parameters (Continued)

Type	Description														
rp	<p>Interface name: rp0, rp1, rp2, ... Device type: Raw packet</p> <table> <tr> <th>Parameter Prompt</th><th>Example Value</th></tr> <tr> <td>IP Address:</td><td>192.41.228.70</td></tr> <tr> <td>IP SubNet Mask:</td><td>255.255.255.0</td></tr> </table> <p>The rp interface allows IP packets that are normally destined for transmission to be directed instead to a user process by way of an AF_RAWPACKET socket.</p>	Parameter Prompt	Example Value	IP Address:	192.41.228.70	IP SubNet Mask:	255.255.255.0								
Parameter Prompt	Example Value														
IP Address:	192.41.228.70														
IP SubNet Mask:	255.255.255.0														
se	<p>Interface name: se0, se1, se2, ... Device type: Any Compaq VMS Ethernet, FDDI, or Token-Ring Alpha controller</p> <table> <tr> <th>Parameter Prompt</th><th>Example Value</th></tr> <tr> <td>VMS Device:</td><td>XEA0</td></tr> <tr> <td>Link Level Encapsulation Mode:</td><td>ETHERNET</td></tr> <tr> <td>BSD Trailer Encapsulation:</td><td>DISABLED</td></tr> <tr> <td>IP Address:</td><td>192.41.228.70</td></tr> <tr> <td>IP SubNet Mask:</td><td>255.255.255.0</td></tr> <tr> <td>Non-Standard IP Broadcast Address:</td><td>192.41.228.71</td></tr> </table> <p>The se interface uses any Compaq Ethernet controller to provide access to a 10 Mb/s Ethernet network, any Compaq FDDI controller to provide access to a 100 Mb/s FDDI network, and a Compaq Token-Ring Alpha controller to provide access to a 4 Mb/s or 16 Mb/s Alpha Token-Ring.</p> <p>The se interface uses the standard VMS Ethernet driver to allow MultiNet to share the Ethernet devices with other protocols such as LAT, LAVC, and DECnet.</p>	Parameter Prompt	Example Value	VMS Device:	XEA0	Link Level Encapsulation Mode:	ETHERNET	BSD Trailer Encapsulation:	DISABLED	IP Address:	192.41.228.70	IP SubNet Mask:	255.255.255.0	Non-Standard IP Broadcast Address:	192.41.228.71
Parameter Prompt	Example Value														
VMS Device:	XEA0														
Link Level Encapsulation Mode:	ETHERNET														
BSD Trailer Encapsulation:	DISABLED														
IP Address:	192.41.228.70														
IP SubNet Mask:	255.255.255.0														
Non-Standard IP Broadcast Address:	192.41.228.71														

Table 5-2 Interfaces and Parameters (Continued)

Type	Description														
sl	<p>Interface name: sl0, sl1, sl2, ...</p> <p>Device type: Any VMS-supported terminal interface</p> <table> <tr> <th>Parameter Prompt</th><th>Example Value</th></tr> <tr> <td>VMS Device:</td><td>TTA0</td></tr> <tr> <td>Baud Rate:</td><td>19200</td></tr> <tr> <td>Header Compression Mode:</td><td>DISABLED</td></tr> <tr> <td>IP Address:</td><td>192.41.228.70</td></tr> <tr> <td>Point-To-Point Device IP Destination Address:</td><td>192.41.228.71</td></tr> <tr> <td>IP SubNet Mask:</td><td>255.255.255.0</td></tr> </table> <p>The MultiNet software supports SLIP with Van Jacobson's header compression algorithm, reducing the size of the headers and increases the bandwidth available to data. Header compression mode is determined by what both sides can support.</p>	Parameter Prompt	Example Value	VMS Device:	TTA0	Baud Rate:	19200	Header Compression Mode:	DISABLED	IP Address:	192.41.228.70	Point-To-Point Device IP Destination Address:	192.41.228.71	IP SubNet Mask:	255.255.255.0
Parameter Prompt	Example Value														
VMS Device:	TTA0														
Baud Rate:	19200														
Header Compression Mode:	DISABLED														
IP Address:	192.41.228.70														
Point-To-Point Device IP Destination Address:	192.41.228.71														
IP SubNet Mask:	255.255.255.0														

Table 5-3 NET-CONFIG Prompts

NET-CONFIG Prompts	Function
ACCM Mask	Asynchronous Control Character Map Mask. A 32-bit mask that indicates the set of ASCII control characters to be mapped into two-character sequences for transparent transmission over the line. The default is %x00000000.
Address and Control Field Compression (ACFC)	When ON, PPP eliminates the address and control fields when they are identical over a series of frames. The default is OFF.
Authentication Method	Determines the type of remote peer authentication required to allow network-layer protocol packets to be exchanged. Accepted values are "PAP" (Password Authentication Protocol) and "NONE" (the default).
Baud Rate	Indicates the baud rate of transmission. Possible values are: 110, 300, 1200, 2400, 4800, 9600, 19200, and UNSPECIFIED.

Table 5-3 NET-CONFIG Prompts (Continued)

NET-CONFIG Prompts	Function
BSD Trailer Encapsulation	For 10Mb/sec Ethernet controllers only. Can be used to enable Berkeley Trailer encapsulation of IP packets on those Ethernets. There are two possible settings: NEGOTIATED or DISABLED . The default, DISABLED , prevents the use of trailer encapsulation.
Hardware Device	The name of the real Ethernet device; for example, se0.
Header Compression Mode	For PPP and SLIP devices, indicates whether to use Van Jacobson's TCP header compression algorithm. The parameter has three possible settings: DISABLED , ENABLED , or NEGOTIATED . DISABLED indicates that headers should never be compressed. ENABLED indicates that headers should always be compressed. The default is DISABLED . NEGOTIATED indicates that headers should not be compressed until a compressed header is received from the other side. At least one side of a link must be ENABLED for compression to be used; that is, both sides of a link cannot be set to NEGOTIATED for compression to be used.
ICMP	When ENABLED (the default), PPP allows ICMP packets over the PPP connection. Administrators may want to disable ICMP packets if they are concerned with "service attacks" from dial-up connections.
Idle Timeout	Determines how long (in seconds) the connection must be idle before PPP attempts to close it with "Terminate-Request" packets. The default is 0.
IP Address	Indicates the Internet address, in dotted decimal notation, associated with the interface. For PPP interfaces, you can specify 0.0.0.0 to indicate that the local IP address will be specified by the remote peer when a serial connection is established. The default is 0.0.0.0.
IP Address of remote system	Indicates the Internet address associated with the remote system.

Table 5-3 NET-CONFIG Prompts (Continued)

NET-CONFIG Prompts	Function
IP Broadcast Address	For devices that support broadcasts, allows the setting of a non-standard IP broadcast address. The parameter defaults to an address whose host portion is all ones.
IP Over DECnet Peer Host's DECnet Name	For IP-over-DECnet links, indicates the name of the DECnet node on the other end of the connection.
IP Over PSI Local DTE Address	For IP-over-PSI links, indicates the DTE (Data Terminal Equipment) address of your local connection.
IP Over PSI Peer DTE Address	For IP-over-PSI links, indicates the DTE address of the PSI node to which you are connecting.
IP Subnet Mask	The subnet mask of the local interface in dotted decimal format. The default depends on the local interface IP address. For example, a class A address results in a default subnet mask of 255.0.0.0.
Link Level Encapsulation Mode	For Ethernet devices, indicates whether to use the standard Ethernet encapsulation of IP datagrams, or extended 802.2 encapsulation as specified in RFC1042. Enter either "ETHERNET" or "802.2" as the value.
Maximum Receive Unit (MRU) Size	Determines the maximum number of 8-bit bytes for the PPP Information field, including Padding, but not including the Protocol field. Because opposite ends of a PPP connection may have different MRU values, PPP negotiates a suitable MRU for both systems. The default is 500.
NetWare Link Level Encapsulation	Indicates which Ethernet encapsulation mode to use for IPX datagrams. Enter either "ETHERNET", "EXTENDED-802.2", "RAW-802.3", or "STANDARD-802.2". Enter the encapsulation mode used by the NetWare hosts with which this interface is going to communicate.

Table 5-3 NET-CONFIG Prompts (Continued)

NET-CONFIG Prompts	Function
NetWare Network Number	Defines the NetWare network number for this interface. This number, expressed in hexadecimal, must be unique among all NetWare hosts and networks.
Point-To-Point Device IP Destination Address	For point-to-point interfaces, indicates the IP address of the peer system on the other side of the connection. The default is 0.0.0.0.
Protocol Compression	When ON, PPP negotiates with the peer to use one byte instead of two for the Protocol fields to improve transmission efficiency on low-speed lines. Default is OFF.
Retry Count	Determines the number of attempts PPP makes to configure a connection with "Configure-Request" packets. The default is 0.
Termination Retry Count	Determines the number of attempts PPP makes to terminate a connection with "Terminate-Request" packets. The default is 0.
Timeout	Determines the time (in seconds) between successive Configure-Request or Terminate-Request packets. The default is 0.
VMS Device	For devices that use a VMS device driver to interface with the hardware, indicates the name of the VMS device that MultiNet will use. This parameter is used with Compaq Ethernet, PPP, and SLIP interfaces.

EXAMPLE

```

$ MULTINET CONFIGURE /NETWORK
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG> ADD PPP2
[Adding new configuration entry for device "PPP2"]
VMS Device: [TTA0]RETURN
Baud Rate: [UNSPECIFIED] 9600
PPP ACCM Mask: [%x0] RETURN
PPP Authentication Method: [NONE] PAP
PPP Protocol Compression: [OFF] ? ON

```

```
PPP Address and Control Field Compression: [OFF] ON
PPP Retry Count: [0] 10
PPP Idle Timeout: [0] 10
PPP MRU Size: [0] RETURN
PPP ICMP: [ENABLED] RETURN
PPP TCP Compression: [OFF] RETURN
PPP Termination Retry Count: [0] 10
PPP Timeout: [0] 10
IP Address: [NONE] 123.45.67.00
Point-to-Point Device IP Destination Address: [NONE] RETURN
IP Subnet Mask: [NONE] RETURN
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
```


ATTACH

Detaches the terminal from the calling process and reattaches it to another process. Use the SPAWN SHOW PROCESS /SUBPROCESSES command to list the names of subprocesses. Use the DCL LOGOUT command to return to the original process. If the MULTINET_DISABLE_SPAWN logical is enabled, ATTACH does not work.

FORMAT

ATTACH *process-name*

PARAMETER

process_name

Specifies the name of a process to which you want our terminal attached. (Not all subprocesses can be attached; some testing may be required.)

EXAMPLE

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SPAWN
$ MM
MM>SPAWN SHOW PROCESS /SUB
...
There are 3 processes in this job:
_TWA42:
  PROC_1
  PROC_2 (*)
MM>ATTACH _TWA42:
NET-CONFIG>ATTACH PROC_1
MM>QUIT
$ LOGOUT
NET-CONFIG>
```

This example shows the use and exit of attached subprocesses.

- 1 The first command uses SPAWN to create a subprocess. MM is invoked from the DCL command line. Next, the SPAWN SHOW PROCESS/SUB command is used to list all the subprocess names. The display shows that three subprocesses are active. (Process _TWA42: is NET-CONFIG, PROC_1 is MM, and PROC_2 is the SPAWN SHOW PROCESS/SUB command.)
- 2 In the next command, the MM ATTACH command returns control to the NET-CONFIG process. From this utility, ATTACH returns control to MM. To exit, QUIT is invoked from MM, and LOGOUT is invoked at the original spawned DCL command line; control returns back to NET-CONFIG. (If SPAWN SHOW PROCESS/SUB had been entered, only this command and the configuration processes would be active.)

CHECK

Checks the configuration parameters to ensure all required information is provided. If a problem is found, an error message displays; otherwise, if the check is successful, no information displays.

FORMAT

CHECK

DESCRIPTION

CHECK provides a check of the current configuration. The following messages can display:

Message	Description
ERROR: <i>device_name</i> can't \$ASSIGN to FFI device: <i>value</i>	The specified X device does not exist, or a lack of privileges made opening the device impossible.
ERROR: <i>device_name</i> can't \$ASSIGN to SLIP device: <i>value</i>	The specified device does not exist, or a lack of privileges made opening the device impossible.
ERROR: <i>device_name</i> : Default route cannot be the local machine: <i>default_route</i>	The default route is the gateway that connects this system to the Internet; it cannot be the local system.
ERROR: <i>device_name</i> : Default route route must be directly connected	The IP address specified in the SET DEFAULT-ROUTE command must be for a system connected to the Internet.
ERROR: <i>device_name</i> : Illegal value for IP Address: <i>address</i>	The specified IP address either has an octet above 255, or contains an illegal character such as a space, an alphabetical character, or a control character. Use the MODIFY command to specify a new value.
ERROR: <i>device_name</i> : Illegal value for IP Broadcast Address: <i>address</i>	The specified IP broadcast address either has an octet above 255, or contains an illegal character such as a space, an alphabetical character, or a control character. Use the MODIFY command to specify a new value.
ERROR: <i>device_name</i> : Illegal value for IP SubNet Mask: <i>mask</i>	The specified IP subnet mask value either has an octet above 255, or contains an illegal character such as a space, an alphabetical character, or a control character. Use the MODIFY command to specify a new value.
ERROR: <i>device_name</i> is slave to nonexistent device <i>hardware_device</i>	The MultiNet device points to a device that does not exist for the local system.

Message	Description
ERROR: <i>device_name</i> 's DECnet peer must be DECnet node name, not address	DECnet node names are alphanumeric strings of six characters or less; specify the correct value.
ERROR: <i>device_name</i> 's point-to-point destination is unspecified	A destination address was not specified for a point-to-point device, such as a SLIP line.
ERROR: <i>device_name</i> 's PSI peer must be PSI DTE, not node.	The "IP Over PSI Peer Host's DTE" prompt is requesting the DTE destination name; specify the correct value.
ERROR: <i>device_name</i> 's PSI local must be PSI DTE, not node.	The "IP Over PSI Local Host's DTE" prompt is requesting the DTE source name; specify the correct value.
ERROR: The host name is not a domain-style host name and domain name service is enabled.	The domain name did not contain dot separators.
ERROR: There is no Host Name specified.	A host name value was not entered either in the configuration file you are creating or in a read-in configuration file.
WARNING: <i>device_name</i> has no FFI device specified	The added or modified device requires that an FFI device be specified.
WARNING: <i>device_name</i> has no protocol addresses specified	The added or modified device requires that protocol addresses be specified.
WARNING: <i>device_name</i> 's DECnet peer is unspecified (link will not come up)	Both ends of a point-to-point DECnet link must be specified.
WARNING: <i>device_name</i> 's hardware device is unspecified	A device name must be entered for this device.
WARNING: <i>device_name</i> 's PSI peer is unspecified (link will not come up)	Both ends of a point-to-point PSI link must be specified.
WARNING: <i>device_name</i> 's PSI local DTE is unspecified (link will not come up)	Both ends of a point-to-point PSI link must be specified.

EXAMPLE

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>ADD PPP1
[Adding new configuration entry for device "ppp1"]
VMS Device: [TTA0] TTA1
Baud Rate: [UNSPECIFIED] 9600
PPP ACCM Mask: [%x0] RETURN
PPP Authentication Method: [NONE] PAP
PPP Protocol Compression: [OFF] ON
PPP Address and Control Field Compression: [OFF] ON
PPP Retry Count: [0] 10
PPP Idle Timeout: [0] 10
PPP MRU Size: [0] 10
PPP ICMP: [ENABLED] RETURN
PPP TCP Compression: [OFF] RETURN
PPP Termination Retry Count: [0] RETURN
PPP Timeout: [0] RETURN
IP Address: [NONE] RETURN
Point-to-Point Device IP Destination Address: [NONE] 155.35.24.13
IP Subnet Mask: [NONE] RETURN
[ppp] (Point-to-Point Protocol): Csr=NONE, Flags=%X0]
NET-CONFIG>CHECK
WARNING: ppp1 has no protocol addresses specified
NET-CONFIG>EXIT
$
```

CLEAR

Deletes all devices from the current network configuration.

FORMAT

CLEAR

EXAMPLE

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>CLEAR
```

DELETE

Removes a single device from the network configuration.

FORMAT

DELETE *interface*

PARAMETER

interface

Specifies the name of the interface for the device being removed.

EXAMPLE

This example deletes a SLIP device, SL0, from the current configuration.

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>DELETE SL0
```

DISABLE

Disables a device. A disabled device is deleted from the configuration and is not configured at network boot.

FORMAT

DISABLE *interface*

PARAMETER

interface

Specifies the name of the interface for the device being disabled.

EXAMPLE

This example disables a SLIP device, SL0.

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>DISABLE SL0
```

ENABLE

Enables a device.

FORMAT

ENABLE *interface*

PARAMETER

interface

Specifies the name of the interface for the device being enabled.

EXAMPLE

This example enables a SLIP device, SL0.

```
$ MULTINET CONFIGURE /NETWORK_DEVICES  
MultiNet Network Configuration Utility 4.4 (nnn)  
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]  
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]  
NET-CONFIG>ENABLE SL0
```


ERASE

Erases all configured devices from the current configuration. (Functionally equivalent to `CLEAR`; see `CLEAR` for additional information.)

EXIT

Saves the current configuration, if it has been modified, and exits the configuration program.
(Use the STATUS command to display whether the configuration was modified.)

FORMAT

EXIT

EXAMPLES

When the configuration has not been changed, a message displays indicating that the configuration file is not updated.

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>EXIT
[Configuration not modified, so no update needed]
$
```

When the configuration has changed, a message displays indicating that the configuration file has been updated.

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>CLEAR
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$
```

GET

Reads in a nonstandard configuration file.

FORMAT

GET *filename*

PARAMETER

filename

Specifies the name of the configuration file to read; by default, NETWORK_DEVICES.CONFIGURATION in the current working directory.

EXAMPLE

This example retrieves the configuration file MULTINET:TEST.CONFIGURATION into the NET-CONFIG workspace.

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>GET MULTINET:TEST.CONFIGURATION
```

HELP

Displays help information by listing either the command names or information about specific commands. You can also display help information by adding a question mark to other NET-CONFIG commands.

FORMAT

HELP *command*

PARAMETER

command

Specifies the command for which to list help information. Use a question mark (?) to list all command names. Entering a question mark on the NET-CONFIG command line has the same effect as using the "HELP ?" command.

EXAMPLE

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
```

```
MultiNet Network Configuration Utility 4.4 (nnn)
```

```
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
```

```
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
```

```
NET-CONFIG>HELP ?
```

```
ADD      ATTACH  CHECK   CLEAR   DELETE  DISABLE  ENABLE  ERASE
```

```
EXIT     GET      HELP    MODIFY  PUSH    QUIT     SAVE    SET
```

```
SHOW     SPAWN   STATUS  USE      ERSION  WRITE
```

```
NET-CONFIG>
```

MODIFY

Modifies an existing device configuration. If the device has not already been configured, an error message displays.

Use MODIFY to modify configuration parameters for an existing network interface. MODIFY produces the same sequence of prompts for network interface parameter values as the ADD command, but uses the current settings for default values.

FORMAT

MODIFY *interface*

PARAMETER

interface

Specifies the name of the interface for the device being modified.

EXAMPLE

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>MODIFY se0
[Modifying configuration entry for device "se0"]
VMS Device: [EZA0] RETURN
Link Level Encapsulation Mode: [ETHERNET] ? EXTENDED-802.2
BSD Trailer Encapsulation: [DISABLED] RETURN
IP Address: [123.45.678.90] RETURN
IP Subnet Mask: [255.255.255.0] RETURN
Non-Standard IP Broadcast Address: [NONE] RETURN
se0 (Shared VMS Ethernet/FDDI): Csr=NONE, flags=%x0)
NET-CONFIG>
```

PUSH

Starts and attaches a DCL subprocess. If a parent process exists, attach to it. To return from DCL, use the ATTACH or the LOGOUT command. To switch back from a DCL subprocess, use the ATTACH command.

If the MULTINET_DISABLE_SPAWN logical is set, PUSH does not work.

FORMAT

PUSH

QUIT

Prompts you to save the current configuration if it was modified, and then exits.

FORMAT

QUIT

EXAMPLE

```
$ MULTINET CONFIGURE /NETWORK_DEVICES
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>DISABLE SL0
NET-CONFIG>QUIT
Configuration modified, do you want to save it? [NO] RETURN
```

SAVE

Saves the configuration parameters.

FORMAT

SAVE [/STARTUP] [*filename*]

PARAMETER

filename

Specifies the file name for the configuration file or the startup command procedure. The default for filename when saving the configuration data is the file from which the configuration was read. The default for filename when saving the MultiNet startup command procedure is MULTINET:START_MULTINET.COM.

QUALIFIER

/STARTUP

Specifies that NET-CONFIG saves the MultiNet startup commands in filename.

SET ANONYMOUS-FTP-DIRECTORY

Restricts directory tree access of an anonymous FTP account.

If your configuration permits users to make anonymous file transfers via the VMS ANONYMOUS account, use the ANONYMOUS-FTP-DIRECTORY parameter to restrict access for that account to a specific directory tree.

You can change the value of ANONYMOUS-FTP-DIRECTORY without rebooting by also defining or redefining the system-wide MULTINET_ANONYMOUS_FTP_DIRECTORY logical name.

FORMAT

SET ANONYMOUS-FTP-DIRECTORY [*directory*]

PARAMETER

directory

Specifies the name of the directory tree to which the account is restricted. To cancel the restriction, enter the command without a directory name.

EXAMPLE

This example sets the ANONYMOUS-FTP-DIRECTORY parameter to USERS:[ANONYMOUS], then sets the system-wide MULTINET_ANONYMOUS_FTP_DIRECTORY logical name. By setting the system-wide logical name, ANONYMOUS-FTP-DIRECTORY can be set without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET ANONYMOUS-FTP-DIRECTORY USERS:[ANONYMOUS]
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE -
_$ MULTINET_ANONYMOUS_FTP_DIRECTORY "USERS:[ANONYMOUS]"
$
```

SET CLUSTER-SERVICE-ADDRESS

Identifies the IP address to be used when responding to address queries for hosts specified by CLUSTER-SERVICE-NAMES.

If your host is configured with more than one interface, the DOMAINNAME service is enabled, and you are using cluster load balancing, use the CLUSTER-SERVICE-ADDRESS parameter to identify the IP address that this host will return in response to address queries for any host specified by CLUSTER-SERVICE-NAMES.

If you do not specify an address, an interface is chosen at random.

FORMAT

SET CLUSTER-SERVICE-ADDRESS *[ip_address]*

PARAMETER

ip_address

Specifies the IP address returned when responding to address queries from hosts identified by CLUSTER-SERVICE-NAMES.

EXAMPLE

This example sets the CLUSTER-SERVICE-ADDRESS parameter to 191.43.154.10 and then sets the system-wide MULTINET_CLUSTER_SERVICE_ADDRESS logical name. By setting the system-wide logical name, the CLUSTER-SERVICE-ADDRESS can be set without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET CLUSTER-SERVICE-ADDRESS 191.43.154.10
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE -
_$ MULTINET_CLUSTER_SERVICE_ADDRESS "191.43.154.10"
$ @MULTINET:START_SERVER
$
```

SET CLUSTER-SERVICE-NAMES

Lists host names to which cluster load balancing applies, and allows you to configure hosts so that TCP-based connections are directed to the host with the lightest load at the time of the request. The DOMAINNAME service must be enabled on each host. To establish this environment:

- 1 Configure the primary name server for the parent domain so that it delegates authority for each host specified with the CLUSTER-SERVICE-NAMES parameter to this host.
- 2 Use the CLUSTER-SERVICE-NAMES parameter to identify the hosts for which this host will accept connections.

For example, if authority for CLUSTER.FLOWERS.COM is delegated to NODE1, NODE2, and NODE3 on the primary name servers, each node must include CLUSTER.FLOWERS.COM in its CLUSTER-SERVICE-NAMES list. When a TCP service request is made to CLUSTER.FLOWERS.COM, DNS returns the IP addresses of the nodes NODE1, NODE2, or NODE3, ordered by load rating.

If the host is configured with more than one interface, specify the desired interface with the CLUSTER-SERVICE-ADDRESS parameter.

FORMAT

SET CLUSTER-SERVICE-NAMES *hostlist*

PARAMETER

hostlist

Specifies a comma-separated list of fully qualified host names for which cluster load balancing is implemented.

EXAMPLE

This example sets the CLUSTER-SERVICE-NAMES parameter to CLUSTER.FLOWERS.COM, then sets the system-wide MULTINET_CLUSTER_SERVICE_NAMES logical. By setting the system-wide logical, CLUSTER-SERVICE-NAMES can be set without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET CLUSTER-SERVICE-NAMES CLUSTER.FLOWERS.COM
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE/SYSTEM/EXECUTIVE
_$ MULTINET_CLUSTER_SERVICE_NAMES "CLUSTER.FLOWERS.COM"
$ @MULTINET:START_SERVER
$
```

SET DEFAULT-RMT-TAPE-DEVICE

Defines the default VMS tape drive that the RMT server uses. (This drive is the VMS equivalent of the UNIX /dev/rmt0 interface, and is the drive used by the rdump and rrestore programs.) If the parameter is not set, the server searches for interface types in the following order and uses the first interface it finds: MU, MK, MF, MT, and MS.

You can change the value of DEFAULT-RMT-TAPE-DEVICE without rebooting by also defining or redefining the system-wide logical name MULTINET_RMT_TAPE_DEVICE.

FORMAT

SET DEFAULT-RMT-TAPE-DEVICE *drive_name*

PARAMETER

drive_name

Specifies the name of the default drive.

EXAMPLE

This example sets DEFAULT-RMT-TAPE-DEVICE to HSC001\$MUA1:, then sets the MULTINET_RMT_TAPE_DEVICE system-wide logical name. By setting this logical name, the tape device can be given a new value without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET DEFAULT-RMT-TAPE-DEVICE HSC001$MUA1:
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE MULTINET_RMT_TAPE_DEVICE "HSC001$MUA1:"
$
```

SET DEFAULT-ROUTE

Defines the default IP route—that is, the IP address of the gateway that MultiNet uses for all packets sent from the local network.

You can specify more complex routing information by either:

- Creating a MULTINET:LOCAL_ROUTES.COM file that contains a list of MULTINET SET/ROUTE commands that set up the routing tables on a per-network basis.
- Running a dynamic-routing protocol such as RIP, HELLO, EGP, or BGP by configuring the GATED service.

Note! Any GATED configuration overrides a default IP route set with NET-CONFIG. Once started, GATED takes complete control of your routing.

You can change the default route without rebooting by using the MULTINET SET/ROUTE command to delete the old default route and add the new default route.

FORMAT

SET DEFAULT-ROUTE *ip_address*

PARAMETER

ip_address

Specifies the IP address of the gateway.

EXAMPLE

This example sets the gateway DEFAULT-ROUTE to 192.41.228.100, then performs the commands that change DEFAULT-ROUTE without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET DEFAULT-ROUTE 192.41.228.100
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ MULTINET SET/ROUTE -
_$ /DELETE=(DESTINATION=0.0.0.0, GATEWAY=192.41.228.100)
$ MULTINET SET/ROUTE -
_$ /ADD=(DESTINATION=0.0.0.0, GATEWAY=192.41.228.100)
```

SET DOMAIN-NAMESERVERS

Configures the DNS domain resolver, the portion of MultiNet called when a host name must be translated into an Internet address. If you are using DNS, use this parameter to define the Internet addresses of the Domain Name Servers to which the resolver will send requests.

The usual setting for the parameter is the loopback address (127.0.0.1), which directs the resolver to send inquiries to the server on the local system.

To disable DNS and use the host tables instead of the service, enter the SET DOMAIN-NAMESERVERS command with no options.

You can change the value of DOMAIN-NAMESERVERS without rebooting by also defining or redefining the system-wide logical name MULTINET_NAMESERVERS and restarting the MULTINET_SERVER (@MULTINET:START_SERVER) and SMTP_SYMBIONT (@MULTINET:START_SMTP) processes.

FORMAT

SET DOMAIN-NAMESERVERS [*address* [,*address* . . .]]

PARAMETER

address

Specifies the IP address of a name server. When you list multiple addresses, the resolver successively attempts to send a packet to the addresses, in the listed order, until it receives a response.

RESTRICTION

The resolver nameserver list can only include three IP addresses. This list is controlled by the MULTINET_NAMESERVERS logical (which is controlled by the DOMAIN-NAMESERVERS parameter).

EXAMPLES

This example tells the resolver to try only the local nameserver. The subsequent DCL commands change domain nameservers without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET DOMAIN-NAMESERVERS 127.0.0.1
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXEC MULTINET_NAMESERVERS "127.0.0.1"
```

```
$ DEFINE /SYSTEM /EXEC UCX$BIND_SERVER000 "127.0.0.1"
$ DEFINE /SYSTEM /EXEC UCX$BIND_DOMAIN "FLOWERS.COM"
$ @MULTINET:START_SERVER
$ @MULTINET:START_SMTP
$
```

This example configures the resolver to try the local name server and, if it fails, to try 192.0.0.1.

```
NET-CONFIG>SET DOMAIN-NAMESERVERS 127.0.0.1,192.0.0.1
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$
$ DEFINE /SYSTEM /EXEC MULTINET_NAMESERVERS "127.0.0.1", "192.0.0.1"
$ DEFINE /SYSTEM /EXEC UCX$BIND_SERVER000 "127.0.0.1"
$ DEFINE /SYSTEM /EXEC UCX$BIND_SERVER001 "192.0.0.1"
$ DEFINE /SYSTEM /EXEC UCX$BIND_DOMAIN "FLOWERS.COM"
$ @MULTINET:START_SERVER
$ @MULTINET:START_SMTP
$
```

The SET DOMAIN-NAMESERVERS disables the local DNS domain server; only host tables are used to translate names and addresses.

```
MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET DOMAIN-NAMESERVERS
NET-CONFIG>EXIT
$
$ DEASSIGN /SYSTEM /EXEC MULTINET_NAMESERVER
$ DEASSIGN /SYSTEM /EXEC UCX$BIND_SERVER000
$ DEASSIGN /SYSTEM /EXEC UCX$BIND_SERVER001
$ DEASSIGN /SYSTEM /EXEC UCX$BIND_DOMAIN
$ @MULTINET:START_SERVER
$ @MULTINET:START_SMTP
$
```

SET HOST-NAME

Specifies the local computer's host name and defines the default local domain. If your configuration includes Domain Name Service (DNS), you must specify the host name in dotted format, for example, HAMLET.CALTECH.EDU or JETSON.SPROCKETS.COM.

The default local domain is derived from the HOST-NAME parameter. For example, with a host name of HAMLET.CALTECH.EDU, the default local domain is .CALTECH.EDU. MultiNet uses the default local domain to complete abbreviated host names. For example, with the default of CALTECH.EDU, if you entered the command:

```
$ TELNET ROMEO
```

TELNET would attempt to connect to a ROMEO.CALTECH.EDU host.

You can change the value of HOST-NAME without rebooting by also defining or redefining the system-wide logical name MULTINET_HOST_NAME and restarting the MULTINET_SERVER (@MULTINET:START_SERVER) and SMTP_SYMBIONT (@MULTINET:START_STMP) processes.

FORMAT

SET HOST-NAME *host*

PARAMETER

host

Specifies the name of your host.

EXAMPLE

This example sets the HOST-NAME to HAMLET.CALTECH.EDU, then issues the commands that change the parameter without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET HOST-NAME HAMLET.CALTECH.EDU
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXEC MULTINET_HOST_NAME "HAMLET.CALTECH.EDU"
$ DEFINE /SYSTEM /EXEC ARPANET_HOST_NAME "HAMLET.CALTECH.EDU"
$ DEFINE /SYSTEM /EXEC UCX$INET_HOST "HAMLET.CALTECH.EDU"
$ DEFINE /SYSTEM /EXEC UCX$BIND_DOMAIN "FLOWERS.COM"
$ @MULTINET:START_SERVER
$ @MULTINET:START_STMP
$
```


SET IP-CLUSTER-ALIASES

Specifies a list of cluster-wide Internet addresses to which this node should respond.

In a VMSccluster, the nodes coordinate among themselves so that only one node responds to the cluster-wide addresses at any one time. Should that node fail or be shut down, another node immediately takes over this task.

You can use this parameter with connectionless protocols (such as NFS) for automatic failover. IP-CLUSTER-ALIASES specifies a list of IP addresses to which this node should respond in addition to the address(es) that are configured for the interfaces you define.

Disable IP-CLUSTER-ALIASES by entering the value without specifying an address.

You can change the value of IP-CLUSTER-ALIASES without rebooting by also defining or redefining the system-wide logical name MULTINET_IP_CLUSTER_ALIASES and restarting the MULTINET_SERVER (@MULTINET:START_SERVER) process.

FORMAT

SET IP-CLUSTER-ALIASES [*address* [,*address* . . .]]

PARAMETER

address

Specifies the Internet address to which to respond.

EXAMPLE

This example sets IP-CLUSTER-ALIASES to 192.1.1.2, then executes the commands that change this parameter without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET IP-CLUSTER-ALIASES 192.1.1.2
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE MULTINET_IP_CLUSTER_ALIASES "192.1.1.2"
$ @MULTINET:START_SERVER
```

SET LOAD-EXOS-DRIVER

Enables automatic loading of the Novell EXOS-compatible \$QIO driver when MultiNet starts. The driver allows MultiNet to support Novell's EXOS programming interface.

Reboot your system after setting LOAD-EXOS-DRIVER so that the change is recognized by the operating system.

FORMAT

SET LOAD-EXOS-DRIVER { TRUE | FALSE }

PARAMETERS

TRUE

Enables the EXOS \$QIO programming interface.

FALSE

Disables the EXOS \$QIO programming interface (the default setting).

EXAMPLE

```
$ MULTNET CONFIGURE /INTERFACE  
MultiNet Network Configuration Utility 4.4 (nnn)  
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]  
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]  
NET-CONFIG>SET LOAD-EXOS-DRIVER TRUE
```

SET LOAD-PWIP-DRIVER

Enables automatic loading of the version 5 PATHWORKS server interface (PWIP) driver when MultiNet starts. You must enable the PWIP driver to use version 5 PATHWORKS.

Note! Earlier versions of PATHWORKS use the UCX interface.

Reboot your system after setting LOAD-PWIP-DRIVER so that the change is recognized by the operating system.

* Formerly VMS/ULTRIX Connection (UCX). Referred to generically throughout the this documentation as UCX.

FORMAT

SET LOAD-PWIP-DRIVER { TRUE | FALSE }

PARAMETERS

TRUE

Enables the PWIP driver.

FALSE

Disables the PWIP driver (the default setting).

SET LOCAL-DOMAIN

Overrides the default local domain derived from a previous SET HOST-NAME command.

If your configuration includes a Domain Name System (DNS) domain server, you can use the LOCAL-DOMAIN parameter to override the default local domain derived from the HOST-NAME parameter.

You can change the value of LOCAL-DOMAIN without rebooting by also defining or redefining the system-wide logical name MULTINET_LOCALDOMAIN and restarting the MULTINET_SERVER (@MULTINET:START_SERVER) and SMTP_SYMBIONT (@MULTINET_START_SMTP) processes.

FORMAT

SET LOCAL-DOMAIN *domain*

PARAMETER

domain

Specifies the default domain name.

EXAMPLE

This example sets LOCAL-DOMAIN to TREEFROG.COM, then invokes the commands that change this parameter without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET LOCAL-DOMAIN TREEFROG.COM
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE MULTINET_LOCALDOMAIN "TREEFROG.COM"-
$ DEFINE /SYSTEM /EXECUTIVE UCX$BIND_DOMAIN "TREEFROG.COM"
$ @MULTINET:START_SERVER
$ @MULTINET:START_SMTP
$
```

SET LPD-DEFAULT-USERNAME

Specifies a default user name for print jobs received from a remote system via the LPD protocol.

The LPD-DEFAULT-USERNAME parameter allows all print jobs requested by remote users to be processed, regardless of whether each user has a local VMS user name. The parameter defines a default user name for users without local user names.

You can change the value of LPD-DEFAULT-USERNAME without rebooting by also defining or redefining the system-wide logical name MULTINET_LPD_DEFAULT_USERNAME.

FORMAT

SET LPD-DEFAULT-USERNAME *user*

PARAMETER

user

Specifies the default user name, which must be an existing name in the OpenVMS system.

EXAMPLE

This example sets LPD-DEFAULT-USERNAME to PYWACKET, then executes the commands that change this parameter without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from
MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET LPDD-DEFAULT-USERNAME PYWACKET
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE MULTINET_FPD_DEFAULT_USERNAME "PYWACKET"
```

SET NAMESERVER-RETRANSMISSION

Controls the time between requests and the number of name server requests made before the system stops sending requests to a nonresponding server. The first argument is the time in seconds; the optional second argument is the number of tries to make.

You can change the value of NAMESERVER-RETRANSMISSION without rebooting by also defining or redefining the system-wide logical names MULTINET_NAMESERVER_RETRANS and MULTINET_NAMESERVER_RETRY and restarting the MULTINET_SERVER (@MULTINET:START_SERVER) and SMTP_SYMBIONT (@MULTINET_START_SMTP) processes.

FORMAT

SET NAMESERVER-RETRANSMISSION *seconds retries*

PARAMETERS

seconds

Specifies the time between retransmissions, in seconds (by default, 4 seconds).

retries

Specifies the number of retransmissions to make before giving up (by default, 4 tries).

EXAMPLE

This example specifies that the name server waits eight seconds between retries, and makes up to four retries before the system stops sending requests to the nonresponding server. The commands after setting this parameter allow the parameter to take effect immediately without rebooting the system.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET NAMESERVER-RETRANSMISSION 8 4
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE MULTINET_NAMESERVER_RETRANS 8
$ DEFINE /SYSTEM /EXECUTIVE MULTINET_NAMESERVER_RETRY 4
$ @MULTINET:START_SERVER
$ @MULTINET:START_SMTP
```

SET SPOOL-DIRECTORY

Changes the MultiNet spool directory from its default of MULTINET_COMMON_ROOT:[MULTINET.SPOOL]. The spool directory is used to store transient mail and print files.

You can change the value of SPOOL-DIRECTORY without rebooting by also defining or redefining the system-wide logical name MULTINET_SPOOL.

FORMAT

SET SPOOL-DIRECTORY *directory*

PARAMETER

directory

Specifies the new spool directory.

EXAMPLE

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET SPOOL-DIRECTORY SYS$SYSROOT:[TMP]
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE MULTINET_SPOOL "SYS$SYSROOT:[TMP]"
```

SET TFTP-DIRECTORY

Defines the TFTP server's default directory.

FORMAT

SET TFTP-DIRECTORY *directory*

PARAMETER

directory

Specifies the name of the new default directory.

DESCRIPTION

Use the TFTP-DIRECTORY parameter to define the TFTP server's default directory. When the parameter is not set, there is no default directory.

You can change the value of TFTP-DIRECTORY without rebooting by also defining or redefining the system-wide logical name MULTINET_TFTP_DEFAULT_DIRECTORY, then issuing the MULTINET NETCONTROL TFTP RELOAD command.

EXAMPLE

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET TFTP-DIRECTORY USERS:[TFTP-FILES]
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE -
_$ MULTINET_TFTP_DEFAULT_DIRECTORY "USERS:[TFTP-FILES]"
$ MULTINET NETCONTROL TFTP RELOAD
$
```


SET TIMEZONE

Although VMS does not keep track of timezones, MultiNet requires this information. The TIMEZONE parameter sets the timezone for your system and indirectly specifies the offset from GMT (and UTC) at which the local VMS clock is run. MultiNet automatically adjusts for Daylight Savings Time (DST) if appropriate for the rules in effect.

If your VMS clock time and your local time differ, set the TIMEZONE parameter to correspond to the VMS clock.

You can change the value of TIMEZONE without rebooting by using the MULTINET SET/TIMEZONE command.

FORMAT

SET TIMEZONE *timezone*

PARAMETER

timezone

Specifies the abbreviation for the timezone, for example, PST.

EXAMPLE

This example sets the timezone to PST (Pacific Standard Time), then uses SET/TIMEZONE to assign the same value to the system-wide variable.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET TIMEZONE PST
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ MULTINET SET/TIMEZONE PST
$
```

SET TIMEZONE-RULES

Sets the timezone rules in effect for your system.

The normal timezone rules in MultiNet include zones for the United States and a number of other countries around the world. Certain countries, such as Canada, have their own Daylight Savings Time rules for timezones such as PST, Pacific Standard Time. The TIMEZONE-RULES parameter is used to override the default rules.

You can change the value of TIMEZONE-RULES without rebooting by using the MULTINET SET/TIMEZONE command.

FORMAT

SET TIMEZONE-RULES *zonelist*

PARAMETER

zonelist

Specifies a comma-separated list of countries and timezones for which to load rules. These can be found in MULTINET:TIMEZONES.DAT.

EXAMPLE

This example sets the TIMEZONE-RULES to US/ARIZONA, then sets the system-wide variable to the same value so that the system does not have to be rebooted for the new rules to take effect.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET TIMEZONE-RULES US/ARIZONA
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ MULTINET SET/TIMEZONE MST/SELECT="US/ARIZONA"
$
```

SET WHOIS-DEFAULT-SERVER

Sets the default server for the WHOIS command. The WHOIS command displays host information obtained from the RS.INTERNIC.NET host server.

By default, WHOIS connects to the server on the host RS.INTERNIC.NET, but can be overridden using the /HOST qualifier. Use this command to change the default server.

You can change the value of WHOIS-DEFAULT-SERVER without rebooting by also defining or redefining the system-wide logical name MULTINET_WHOIS_DEFAULT_SERVER.

FORMAT

SET WHOIS-DEFAULT-SERVER *host*

PARAMETER

host

Specifies the name of the server to which to connect. If not specified, the host defaults to RS.INTERNIC.NET.

EXAMPLE

This example sets WHOIS-DEFAULT-SERVER to FNORD.FOO.COM, then sets the system-wide logical name MULTINET_WHOIS_DEFAULT_SERVER to the same value to avoid rebooting the system after changing the WHOIS default server parameter.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET WHOIS-DEFAULT-SERVER FNORD.FOO.COM
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$ DEFINE /SYSTEM /EXECUTIVE -
_ $ MULTINET_WHOIS_DEFAULT_SERVER "FNORD.FOO.COM"
```

SET WINS-COMPATIBILITY

Enables automatic definition of the logical names required for compatibility with applications developed for the WIN/TCP and Pathway for OpenVMS products from The Wollongong Group. The logical names allow MultiNet to support applications that run under those products. You must also generate a UNIX-format host table using the MULTINET HOST_TABLE COMPILE/UNIX command.

FORMAT

SET WINS-COMPATIBILITY { TRUE | FALSE }

PARAMETERS

TRUE

Enables the definition of the WIN/TCP and Pathway for OpenVMS compatibility logical names.

FALSE

Disables the definition of the WIN/TCP and Pathway for OpenVMS compatibility logical names.

EXAMPLES

1 \$ MULTINET CONFIGURE /INTERFACE

```
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SET LOCAL-DOMAIN TREEFROG.COM
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
```

Use the following DCL commands to enable WINS compatibility mode without a reboot:

```
2 $ DIRECTORY = F$TRNLNM("MULTINET_SPECIFIC_ROOT") - "]"
DEFINE/SYSTEM/EXEC/TRANSLATION_ATTRIBUTES=CONCEAL TWG$ETC -
'DIRECTORY'MULTINET.], 'DIRECTORY'SYSCOMMON.MULTINET.]
DEFINE/SYSTEM/EXEC/TRANSLATION_ATTRIBUTES=CONCEAL TWG$TCP -
DEFINE/SYSTEM/EXEC INET_DOMAIN_NAME 'FLOWERS.COM"
DEFINE/SYSTEM/EXEC INET_NAMESERVER_LIST "127.0.0.1"
DEFINE/SYSTEM/EXEC WINS_MAILSHR MULTINET:SMTP_MAILSHR
DEFINE/SYSTEM/EXEC DECW$TRANSPORT_WINTCP DECW$TRANSPORT_TCIP
```

Whether you choose to reboot or not, use the following commands to create a UNIX-format host table:

```
3 $ SET DEFAULT MULTINET_COMMON_ROOT:[MULTINET]
$ MULTINET HOST_TABLE COMPILE /UNIX
$
```

SHOW

Displays the current MultiNet device configuration.

FORMAT

SHOW *command*

PARAMETER

command

Specifies the type of display. Accepted values are **CURRENT** (the default) or **MAXIMUM**. If a command is not entered, the default is **CURRENT**.

EXAMPLE

This example lists the current configuration.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SHOW
```

Interface	Adapter	CSR Address	Flags/ Vector
se0 (Shared VMS Ethernet) [TCP/IP: 192.41.228.78] [VMS Device: ESA0]	-NONE-	-NONE-	-NONE-
s10 (Serial Line IP) [TCP/IP: 192.41.228.78==>192.41.228.80] [VMS Terminal: TTA2, 9600 Baud] [Header Compression DISABLED]	-NONE-	-NONE-	-NONE-
*s11 (Serial Line IP) [VMS Terminal: TXA0] [Header Compression DISABLED]	-NONE-	-NONE-	-NONE-

```
Official Host Name:      BANANA.SLUG.COM
Default IP Route:       192.41.228.71
Domain Nameservers:    127.0.0.1
Local Domain:          slug.com
Timezone:              PST
SMTP Host Name:         SLUG.COM
Default RMT Tape:       MKB100:
Default TFTP Directory: MULTINET_ROOT:[MULTINET.TFTP]
```

```
Anonymous FTP Directory:   USERS:[ANONYMOUS]
Load EXOS $QIO driver:     TRUE
Load UCX $QIO driver:      TRUE
WINS Compatibility:        TRUE
NET-CONFIG>QUIT
$
```

SPAWN

Executes a single DCL command, or if entered without options, starts a subprocess with the same effect as PUSH. To return from DCL, use the LOGOUT command. If the MULTINET_DISABLE_SPAWN logical is set, SPAWN does not work.

FORMAT

SPAWN [*command*]

PARAMETER

command

Specifies a command to execute. If you omit command, a DCL command line subprocess is created.

QUALIFIERS

/INPUT=file-spec

Specifies an input file to the command you enter with SPAWN.

/LOGICAL_NAMES

/NOLOGICAL_NAMES

Specifies that logical names and logical name tables are not copied to the subprocess.

/SYMBOLS

/NOSYMBOLS

Specifies that global and local names are not passed to the subprocess.

/WAIT

/NOWAIT

Returns control without waiting for the command to complete. Do not use this qualifier with commands that have prompts or screen displays.

/OUTPUT=file-spec

Specifies a file that retains the output of the command invoked with SPAWN. This qualifier only works when a single command is entered without creating a DCL subprocess. In addition, this qualifier is positional; you must enter it immediately after SPAWN or other qualifiers.

EXAMPLES

This example displays terminal information, captures the output in a file, then displays the information with the TYPE command.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
```

```
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SPAWN/OUTPUT=FOO. SHOW TERM
NET-CONFIG>SPAWN TYPE FOO.
...
```

This example invokes a command procedure.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SPAWN @COMPROC
...
```

This example displays help information about the NET-CONFIG utility. Use the LOGOUT command to return control to NET-CONFIG.

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>SPAWN RETURN
$ HELP MULTINET CONFIGURE /NETWORK_DEVICES
...
$ LOGOUT
NET-CONFIG>
```


STATUS

Displays the status of the current configuration.

FORMAT

STATUS

EXAMPLE

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>STATUS
There is the MultiNet network configuration program Version 4.4 (nnn)
There are 3/1024 devices in the current configuration.
There are 190/1024 devices in the MAXIMUM configuration.
The configuration MULTINET:NETWORK_DEVICES.CONFIGURATION is not modified.
The startup file MULTINET:START_MULTINET.COM is not modified.
NET-CONFIG>QUIT
$
```

USE

Reads in a configuration file. (Functionally equivalent to GET; see GET for additional information.)

FORMAT

USE *config_file*

PARAMETER

config_file

Specifies the name of the configuration file to read in.

VERSION

Displays the NET-CONFIG version and release information.

FORMAT

VERSION

EXAMPLE

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>VERSION
This is the MultiNet network configuration program Version 4.4 (nnn)
NET-CONFIG>QUIT
$
```

WRITE

Writes the current configuration to a file. (Functionally equivalent to SAVE.)

FORMAT

WRITE [*config_file*]

PARAMETER

config_file

Specifies the name of the configuration file to write out (by default, the same file from which the configuration was read).

EXAMPLE

```
$ MULTINET CONFIGURE /INTERFACE
MultiNet Network Configuration Utility 4.4 (nnn)
[Reading in MAXIMUM configuration from MULTINET:MULTINET.EXE]
[Reading in configuration from MULTINET:NETWORK_DEVICES.CONFIGURATION]
NET-CONFIG>WRITE
[Writing configuration to
MULTINET_ROOT:[MULTINET]NETWORK_DEVICES.CONFIGURATION.7]
NET-CONFIG>EXIT
[Writing configuration to MULTINET:NETWORK_DEVICES.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$
```

Chapter 6

NFS-CONFIG Command Reference

This chapter describes the commands you can run from the NFS-CONFIG command line. NFS-CONFIG lets you examine, modify, and save configuration files for the MultiNet NFS system.

To invoke NFS-CONFIG, enter:

```
$ MULTINET CONFIGURE /NFS
```

At any NFS-CONFIG prompt, you can list the available commands by typing "?". Online help for each NFS-CONFIG command is available through the NFS-CONFIG HELP command.

Changes do not take effect until you reload the configuration with the NFS-CONFIG RELOAD command. You can also reload the MultiNet NFS Server configuration with the MULTINET NETCONTROL NFS RELOAD and MULTINET NETCONTROL RPCMOUNT RELOAD commands, or by restarting the server with the RESTART command.

For details on configuring MultiNet NFS Client and MultiNet NFS Server, refer to the *MultiNet for OpenVMS Installation and Administrator's Guide*.

Command Summary

Table 6-1 lists the commands you can run from the NFS-CONFIG prompt.

Table 6-1 NFS-CONFIG Command Summary

NFS-CONFIG Command	Description
ADD DECSTATION-MOUNT-POINT	Adds a particular directory or file to the list of DECstation mount points.
ADD EXPORT	Adds a device or directory to the list of exported mount points.
ADD MOUNT-RESTRICTION	Adds to the list of clients authorized to mount a file system.

Table 6-1 NFS-CONFIG Command Summary (Continued)

NFS-CONFIG Command	Description
ADD NFS-GROUP	Adds systems to a particular NFS group.
ADD NFS-PASSWD-FILE	Specifies the name of a UNIX-style /etc/ password file that provides username-to-UID translation information.
ADD UID-TRANSLATION	Creates an individual mapping between an OpenVMS user name and a UID/GID pair.
APPEND	Appends configuration changes to a configuration file.
ATTACH	Detaches the terminal from the calling process and reattaches it to another process.
CURRENT	Selects the mount point to be acted on by the ADD and DELETE commands.
EXIT	Exits the configuration program after saving the current configuration, if it has been modified.
DELETE DECSTATION-POINT	Removes a file or directory from the list of DECstation mount points.
DELETE EXPORTED-FILE-SYSTEM	Removes a device or directory from the list of exported mount points.
DELETE MOUNT-RESTRICTION	Removes a client from the mount restrictions list.
DELETE NFS-GROUP	Removes systems from a particular NFS group.
DELETE NFS-PASSWD-FILE	Deletes an NFS password file entry.
DELETE UID-TRANSLATION	Deletes an OpenVMS username-to-UID/GID translation.
GET	Reads in a configuration file.
HELP	Invokes command help.
NETCONTROL	Transfers control to an NFS configuration manager subsystem that contacts the NETCONTROL server at local or remote sites.

Table 6-1 NFS-CONFIG Command Summary (Continued)

NFS-CONFIG Command	Description
PUSH	Creates a subprocess or attaches to a parent process.
QUIT	Prompts you to save the file before quitting.
RELOAD	Reloads the NFS Client, NFS Server, and RPCMOUNT server databases.
RESTART	Restarts the NFS and RPCMOUNT servers. (Same as WRITE.)
SAVE	Saves the configuration parameters.
SELECT	Selects a mount point.
SET APPROXIMATE-TEXT-SIZE-THRESHOLD	Permits UNIX ls commands to execute faster.
SET DIRECTORY-INFO-FLUSH-AGE	Controls how long cached headers and data buffers for a directory can remain in the cache.
SET DIRECTORY-INFO-IDLE-FLUSH-AGE	Controls how long cached headers and data buffers for a directory which is not being accessed by any client can remain in the cache.
SET FILE-CACHE-TIMER-INTERVAL	Determines how often the MultiNet NFS Server scans the cache, checking other parameters to see if their timers have expired, and processes those that have.
SET FILE-INFO-FLUSH-AGE	Controls how long cached headers and data buffers for a file can remain in the cache.
SET FILE-INFO-IDLE-FLUSH-AGE	Controls how long cached headers and data buffers for a file which is not being accessed by any client can remain in the cache.
SET MAXIMUM-CACHEBUFFERS	Determines the maximum number of cached file headers and data buffers allowed simultaneously for the cache as a whole.
SET MAXIMUM-CACHE-FILES	Determines the maximum number of cached file headers and data buffers allowed simultaneously for the cache as a whole.

Table 6-1 NFS-CONFIG Command Summary (Continued)

NFS-CONFIG Command	Description
SET MAXIMUM-DIRTY-BUFFERS	Specifies the maximum number of modified buffers in the writeback cache.
SET MAXIMUM-FILESYSTEM-BUFFERS	Determines the maximum number of cached file headers and data buffers allowed simultaneously for single file systems on a per-mount-point basis.
SET MAXIMUM-FILESYSTEM-CHANNELS	Determines the maximum number of open channels allowed simultaneously for single file systems on a per-mount-point basis.
SET MAXIMUM-FILESYSTEM-FILES	Determines the maximum number of cached file headers and data buffers allowed simultaneously for single file systems on a per-mount-point basis.
SET MAXIMUM-OPEN-CHANNELS	Determines the maximum number of open channels allowed simultaneously for the cache as a whole.
SET MAXIMUM-QUEUED-REMOVES	Limits the number of remove operations that may be queued in the delete-behind cache.
SET MAXIMUM-WRITE-JOBS	Limits the number of simultaneous write operations that can occur when the writeback cache is enabled.
SET NUMBER-OF-DUPLICATE-REQUESTS-CACHED	Limits the number of requests that can be retained in the NFS Server's duplicate-request detection cache.
SET NUMBER-OF-RPC-TRANSPORTS	Limits the number of simultaneous requests that the NFS Server can process.
SET READ-ONLY-FLUSH-AGE	Limits how long idle channels can remain assigned to a file.
SET READ-WRITE-FLUSH-AGE	Limits how long idle channels can remain assigned to a file.
SET SECONDS-BEFORE-WRITEBACK	Sets the length of time that write operations are deferred before the data is written to disk.

Table 6-1 NFS-CONFIG Command Summary (Continued)

NFS-CONFIG Command	Description
SET USE-DIRECTORY-BLOCKING-ASTS	Determines whether the server flushes the cache whenever an OpenVMS user attempts to access a directory from which cached information came.
SET USE-FILE-BLOCKING-ASTS	Determines whether the server flushes the cache whenever an OpenVMS user attempts to access a file from which cached information came.
SHOW	Displays information about the configuration of the NFS Server and NFS Client.
SPAWN	Executes a single DCL command, or if entered without options, starts a subprocess with the same effect as PUSH.
STATUS	Displays the status of the current configuration.
USE	Reads in a configuration file.
VERSION	Displays the NFS-CONFIG version and release information.
WRITE	Writes the current configuration to a file. (Same as SAVE.)

ADD DECSTATION-MOUNT-POINT

Adds a directory or file to the list of DECstations mount points using special DECstation-style file handles. You must do this for the root directory and swap or page files used to boot diskless DECstation systems.

FORMAT

ADD DECSTATION-MOUNT-POINT *filename*

PARAMETER

filename

Specifies the file name of the DECstation mount point.

EXAMPLE

This example shows adding a DECSTATION-MOUNT-POINT.

```
NFS-CONFIG>ADD DECSTATION-MOUNT-POINT DECSTATION:[000000]MAXWELL_ROOT.DIR  
[Added new DECstation Mount Point "DECSTATION:[000000]MAXWELL_ROOT.DIR;1"]  
NFS-CONFIG>
```

ADD EXPORT

Adds a device or directory to the list of exported mount points.

FORMAT

ADD EXPORT *mount_point_name*

PARAMETER

mount_point_name

Specifies the name of the file system's mount point.

EXAMPLE

This example shows how to add SYS\$SYSDEVICE: to the list of exported file systems.

```
NFS-CONFIG>ADD EXPORT SYS$SYSDEVICE:
[Added new Exported file system "SYS$SYSDEVICE:"]
[Current Exported File System set to "SYS$SYSDEVICE:"]
NFS-CONFIG>
```

ADD MOUNT-RESTRICTION

Adds a client to the list of authorized clients permitted to mount the specified mount point. If no clients are specified, anyone can access the mount point.

FORMAT

ADD MOUNT-RESTRICTION *mount_point_name client_name*

PARAMETERS

mount_point_name

Specifies the name of the mount point to which to add the restriction.

client_name

Specifies the name of the client, in full domain form (for example, SALES.FLOWERS.COM), in abbreviated form (for example, SALES), in IP address form (for example, 192.168.32.4), or NFS group.

Note! Some clients use the UNIX automount facility, and may require you to use the non-domain form of the host name. Before requesting access to a file system, these clients check the mount restriction list and refuse to attempt the mount request if it is not listed in the recognized format (as opposed to trying the request and letting it fail or succeed).

QUALIFIER

-ro (read only)

Use this qualifier to prevent writing to the disk specified by the mount point. This restriction affects any NFS group associated with that particular mount point.

EXAMPLE

This example shows how to add the client system "sales" to the list of clients authorized to mount SYS\$SYSDEVICE:.

```
NFS-CONFIG>ADD MOUNT-RESTRICTION SYS$SYSDEVICE: SALES
[Added Mount restriction to "SYS$SYSDEVICE:" allowing host "SALES"]
NFS-CONFIG>
```

ADD NFS-GROUP

Adds NFS client systems to a particular NFS group. NFS groups can be used to group together client systems that share common UID/GID spaces. When you specify a UID/GID-to-OpenVMS username mapping with the ADD UID-TRANSLATION command, you can optionally specify an NFS group to associate the translation. This allows you to have different OpenVMS username-to-UID/GID translations for different client hosts (or groups of hosts).

FORMAT

ADD NFS-GROUP *group_name* [*host_list*]

PARAMETERS

group_name

Specifies the NFS group name.

host_list

Contains a comma-delimited list of names of hosts to add to the specified NFS group.

Note! Some clients utilize the UNIX automount facility and may require you to use the non-domain form of the host name. Before requesting access to a file system, these clients check the mount restriction list, and refuse to attempt the mount request if it is not listed in the recognized format (as opposed to trying the request and letting it fail or succeed).

EXAMPLE

This example shows how to add two client systems to the NFS group ENGINEERING.

```
NFS-CONFIG>ADD NFS-GROUP ENGINEERING KAOS.COGS.COM, FANG.COGS.COM
[Current NFS Group set to "ENGINEERING"]
NFS-CONFIG>
```

ADD NFS-PASSWD-FILE

Specifies the name of a UNIX-style /etc/password file that provides username-to-UID translation information.

To create a multi-user mapping, use FTP (or another file transfer utility) to copy each applicable /etc/password file from the UNIX system to the OpenVMS system running the server. Then, run the NFS-CONFIG utility, and use the ADD NFS-PASSWD-FILE command to create the mapping.

FORMAT

ADD NFS-PASSWD-FILE *file_name* [*group_name*]

PARAMETERS

file_name

Specifies the OpenVMS name of the copied /etc/password file.

group_name

Specifies the NFS group name with which the translations specified by the password file will be associated. If not specified, it defaults to the default NFS group (all translations that are not explicitly in a group).

EXAMPLES

This example shows how to add the file MULTINET:NFS.PASSWD to the configuration for the default NFS group.

```
NFS-CONFIG>ADD NFS-PASSWD-FILE MULTINET:NFS.PASSWD
[Added new NFS Password File "MULTINET:NFS.PASSWD"]
NFS-CONFIG>
```

This example shows how to add the file MULTINET:NFS.PASSWD to the configuration for the NFS group ENGINEERING.

```
NFS-CONFIG>ADD NFS-PASSWD-FILE MULTINET:NFS.PASSWD ENGINEERING
[Added new NFS Password File "ENGINEERING/MULTINET:NFS.PASSWD"]
NFS-CONFIG>
```

ADD UID-TRANSLATION

Creates an individual mapping between an OpenVMS user name and a UID/GID pair.

FORMAT

ADD UID-TRANSLATION *username uid gid [group_name]*

PARAMETERS

username

Specifies the name of the user's OpenVMS account.

uid

Specifies the user's UID.

gid

Specifies the user's GID.

group_name

Specifies the NFS group name into which this translation is placed (by default, the default NFS group-all translations not explicitly in a group).

EXAMPLES

This example shows how to add a translation between the OpenVMS user JOHN and the UNIX UID 10 and GID 15.

```
NFS-CONFIG>ADD UID-TRANSLATION JOHN 10 15
[Added UID Translation "JOHN" = 10, 15]
NFS-CONFIG>
```

This example shows how to add a translation between the OpenVMS user JETSON and the UNIX UID 101 and GID 20 in the NFS group ENGINEERING.

```
NFS-CONFIG>ADD UID-TRANSLATION JETSON 101 20 ENGINEERING
[Added UID Translation "ENGINEERING/JETSON" = 101, 20]
NFS-CONFIG>
```

APPEND

Adds to or changes the current configuration parameters. The information you want to append is in a text file whose name you specify as an argument. The appended parameters are in effect as long as the current configuration parameters are in memory. When you RELOAD or RESTART NFS, the parameters are reset to those specified in the NFS.CONFIGURATION file.

For the appended changes to become permanent, use the WRITE or EXIT commands, or enter YES when prompted by the RELOAD or RESTART command to save the current configuration.

APPEND is similar to GET, except that it does not reset any unspecified parameters.

FORMAT

APPEND *filename*

PARAMETER

filename

Specifies the name of the file you want to append.

EXAMPLE

This example shows how to append the contents of MULTINET:NFS_ALT.CONFIGURATION to the configuration information in the MULTINET:NFS.CONFIGURATION file, then save the enhanced configuration in the MULTINET:NFS.CONFIGURATION file.

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in NFS file server configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>APPEND MULTINET:NFS_ALT.CONFIGURATION
[Reading in NFS file server configuration from
MULTINET:NFS_ALT.CONFIGURATION]
NFS-CONFIG>SAVE
[Writing configuration to MULTINET:NFS.CONFIGURATION]
$ QUIT
```


ATTACH

Detaches the terminal from the calling process and reattaches it to another process. Use the SPAWN SHOW PROCESS /SUBPROCESSES command to list the names of subprocesses. Use the DCL LOGOUT command to return to the original process. If the MULTINET_DISABLE_SPAWN logical is enabled, ATTACH does not work.

FORMAT

ATTACH *process-name*

PARAMETER

process-name

Specifies the name of a process to which you want your terminal attached. (Not all subprocesses can be attached; some testing may be required.)

EXAMPLE

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>SPAWN
$ MM
MM>SPAWN SHOW PROCESS/SUB
...
There are 3 processes in this job:
_TWA42:
  PROC_1
  PROC_2 (*)
MM>ATTACH PROC_1
MM>QUIT
$ LOGOUT
NFS-CONFIG>
```

This example shows the use and exit of attached subprocesses.

- 1 The first command uses SPAWN to create a subprocess. MM is invoked from the DCL command line. Next, the SPAWN SHOW PROCESS/SUB command is used to list all the subprocess names. The display shows that three subprocesses are active. (Process _TWA42: is NFS-CONFIG, PROC_1 is MM, and PROC_2 is the SPAWN SHOW PROCESS/SUB command.)
- 2 In the next command, the MM ATTACH command returns control to the NFS-CONFIG process. From this utility, ATTACH returns control to MM. To exit, the QUIT command is invoked from MM, and LOGOUT is invoked at the original spawned DCL command line; control returns to NFS-CONFIG. (If SPAWN SHOW PROCESS/SUB had been entered, only this command and the configuration processes would be active.)

CURRENT

Selects the mount point to be acted on by the ADD and DELETE commands if the mount point is not explicitly specified. (Functionally equivalent to SELECT.)

FORMAT

CURRENT *mount_point_name / none*

PARAMETER

mount_point_name

Specifies the name of a mount point. A value of NONE unselects the current mountpoint.

EXAMPLE

This example shows how to select the mount point SYS\$SYSDEVICE:

```
NFS-CONFIG>CURRENT SYS$SYSDEVICE:  
[Current Exported File System set to "SYS$SYDEVICE:]"  
NFS-CONFIG>
```

DELETE DECSTATION-MOUNT-POINT

Removes a file or directory from the list of DECstation mount points.

FORMAT

DELETE DECSTATION-MOUNT-POINT *filename*

PARAMETER

filename

Specifies the name of the file or directory to delete from the DECstation mount point list.

EXAMPLE

This example shows how to delete a DECstation mount point.

```
NFS-CONFIG>DELETE DECSTATION-MOUNT-POINT RETURN  
Name: DECSTATION:[000000]MAXWELL_ROOT.DIR  
NFS-CONFIG>
```

DELETE EXPORTED-FILE-SYSTEM

Removes a device or directory from the list of exported mount points.

FORMAT

DELETE EXPORT *mount_point_name*

PARAMETER

mount_point_name

Specifies the name of the file system's mount point.

EXAMPLE

This example shows how to remove SYS\$SYSDEVICE: from the list of exported file systems.

```
NFS-CONFIG>DELETE EXPORT SYS$SYSDEVICE:  
NFS-CONFIG>
```

DELETE MOUNT-RESTRICTION

Removes systems from the mount restrictions list.

FORMAT

DELETE MOUNT-RESTRICTION *mount_point_name name*

PARAMETERS

mount_point_name

Specifies the name of the file system's mount point.

name

Specifies the name of the client or NFS group to remove from the restriction list.

EXAMPLE

This example shows how to delete the client "sales" from the mount restriction list for SYS\$SYSDEVICE:.

```
NFS-CONFIG>DELETE MOUNT-RESTRICTION SYS$SYSDEVICE: SALES  
[Deleted Mount restriction "SALES"]  
NFS-CONFIG>
```

DELETE NFS-GROUP

Removes NFS systems from a particular NFS group. When the last client in a group is deleted, the group itself is also deleted from the configuration.

FORMAT

DELETE NFS-GROUP *group_name* [*host_names*]

PARAMETERS

group_name

Specifies the NFS group name.

host_names

Contains a comma-delimited list of host names to delete from the specified NFS group. If no client is specified, or if an asterisk (*) is specified, the group itself will be deleted.

Note! Some clients utilize the UNIX automount facility, and may require you to use the non-domain form of the host name. Before requesting access to a file system, these clients check the mount restriction list and refuse to attempt the mount request if it is not listed in the recognized format (as opposed to trying the request and letting it fail or succeed).

EXAMPLES

This example shows how to delete the system FANG.COGS.COM from the NFS group ENGINEERING.

```
NFS-CONFIG>DELETE NFS-GROUP ENGINEERING FANG.COGS.COM  
NFS-CONFIG>
```

This example shows how to delete the NFS group MARKETING.

```
NFS-CONFIG>DELETE NFS-GROUP MARKETING *  
NFS-CONFIG>
```

DELETE NFS-PASSWD-FILE

Deletes an NFS password file entry.

FORMAT

DELETE NFS-PASSWD-FILE *file_name* [*group_name*]

PARAMETERS

file_name

Specifies the OpenVMS name of the copied /etc/password file.

group_name

Specifies the NFS group name with which the translations specified by the password file are associated (by default, the default NFS group-all translations that are not explicitly in a group).

EXAMPLE

This example shows how to delete the file MULTINET:NFS.PASSWD from the NFS password file list for the default NFS group.

```
NFS-CONFIG>DELETE NFS-PASSWD-FILE MULTINET:NFS.PASSWD  
NFS-CONFIG>
```

DELETE UID-TRANSLATION

Deletes an OpenVMS user name-to-UID/GID translation.

FORMAT

DELETE UID-TRANSLATION *[group_name/]username*

PARAMETER

[group_name/]username

Specifies the name for the user's OpenVMS account. To delete a UID translation in a group other than the default, specify the group name, a slash, then the OpenVMS user name.

EXAMPLES

This example shows how to delete the user name JOHN from the configuration.

```
NFS-CONFIG>DELETE UID-TRANSLATION JOHN  
NFS-CONFIG>
```

This example shows how to delete the user name JETSON in the NFS group ENGINEERING from the configuration.

```
NFS-CONFIG>DELETE UID-TRANSLATION ENGINEERING/JETSON  
NFS-CONFIG>
```


EXIT

Saves the current configuration, if it has been modified, then exits the configuration program. Use the STATUS command to display whether the configuration was modified.

FORMAT

EXIT

EXAMPLES

When the configuration has not changed, a message displays indicating that the configuration file is not updated.

```
$ MULTINET CONFIGURE /NFS
NFSS-CONFIG>EXIT
$
```

When the configuration has changed, a message displays indicating that the configuration file has been updated.

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4(76)
[Reading in NFS file server configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>GET MULTINET:NFS.CONFIGURATION
NFS-CONFIG>EXIT
$
```

GET

Reads in a configuration file.

FORMAT

GET *filename*

PARAMETER

filename

Specifies the file name of the configuration to be read (by default, NETWORK_DEVICES.CONFIGURATION in the current working directory). GET resets any unspecified parameters. To augment the existing configuration, use the APPEND command.

EXAMPLE

This example retrieves the configuration file MULTINET:TEST.CONFIGURATION into the NFS-CONFIG workspace.

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>GET MULTINET:TEST.CONFIGURATION
```

HELP

Invokes command help.

FORMAT

HELP [*topics*]

PARAMETER

topics

Contains a space-delimited list of topics that begins with a topic followed by subtopics. The default topic is **HELP**.

NETCONTROL

Transfers control to an NFS configuration manager subsystem that contacts the NETCONTROL server at local or remote sites.

After invoking NETCONTROL, you can issue commands to the NETCONTROL server to affect MULTINET_SERVER operations at that site.

FORMAT

NETCONTROL [*host*]

RESTRICTION

The NETCONTROL server is normally protected from unauthorized access by a restriction list.

PARAMETER

host

Specifies the name of the host to which to connect (by default, the local host).

EXAMPLE

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>NETCONTROL
Connected to NETCONTROL server on "127.0.0.1"
<FLOWERS.COM Network Control 4.4 (nnn) at Mon 13-Mar-2002 7:42am-EST
NFS>
```

PUSH

Starts and attaches a DCL subprocess. If a parent process exists, attach to it. To return from DCL, use the ATTACH or the LOGOUT command. To switch back from a DCL subprocess, use the ATTACH command.

If the MULTINET_DISABLE_SPAWN logical is set, PUSH does not work.

FORMAT

PUSH

QUIT

Prompts you to save the current configuration if it was modified, and then exits.

FORMAT

QUIT

EXAMPLE

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>GET MULTINET:NFS.CONFIGURATION
NFS-CONFIG>QUIT
Configuration modified, do you want to save it ? [NO]RETURN
$
```

RELOAD

Reloads the NFS and RPCMOUNT server databases, the NFS Client UID/GID translation table, and the NFS group configuration.

If the configuration has been modified since the last save, RELOAD prompts you to save it before reloading. RELOAD allows you to update the NFS UID-translations and exported mount points without flushing the file cache and causing a temporary performance degradation.

FORMAT

RELOAD

RESTART

Restarts the MultiNet NFS Server process and reloads the RPCMOUNT server's databases. If the configuration has been modified since the last save, RESTART prompts you to save it before restarting. In general, you should use RELOAD instead of RESTART.

FORMAT

RESTART

EXAMPLE

```
NFS-CONFIG>RESTART
Connected to NETCONTROL server on "127.0.0.1"
< TGV.COM Network Control 4,1 (nnn) at Mon 13-Mar-2002 7:42am-EST
< NFS Server Started
< RPCMOUNT database reloaded
NFS-CONFIG>
```


SAVE

Saves the configuration parameters.

FORMAT

SAVE [*filename*]

PARAMETER

filename

Specifies the file name for the configuration file being saved (by default, the file from which the configuration was read).

SELECT

Selects the mount point to be acted on by the ADD and DELETE commands if the mount point is not explicitly specified. (Functionally equivalent to CURRENT.)

FORMAT

SELECT *mount_point_name / none*

PARAMETER

mount_point_name

Specifies the name of the mount point. A value of NONE unselects the current mountpoint.

EXAMPLE

This example shows how to select the mount point SYS\$SYSDEVICE:.

```
NFS-CONFIG>SELECT SYS$SYSDEVICE:  
[Current Exported File System set to "SYS$SYDEVICE:"]  
NFS-CONFIG>
```

SET APPROXIMATE-TEXT-SIZE-THRESHOLD

When set to a positive value, the MultiNet NFS Server permits UNIX **ls** commands to execute faster by approximating file sizes when the OpenVMS file length exceeds the specified threshold.

Note! The NFS specification requires that NFS servers return exact file sizes.

FORMAT

SET APPROXIMATE-TEXT-SIZE-THRESHOLD *threshold*

PARAMETER

threshold

Specifies the minimum OpenVMS file length (in bytes) required before the NFS Server approximates the file size.

The client must use the /APPROXIMATE_TEXT_SIZE qualifier as a mount point option for the threshold to take effect.

SET DIRECTORY-INFO-FLUSH-AGE

Controls how long cached headers and data buffers for a directory can remain in the cache.

Unless the cache-interrupt parameters are on, cached headers and buffers are not automatically discarded when an OpenVMS user attempts to access their directories on disk. The **DIRECTORY-INFO-FLUSH-AGE** parameter specifies a period after which the server discards cached information (requiring rereads from disk if the information is needed again).

This parameter is a trade-off between response time and concurrency between information stored in the cache and on the disk.

You can raise or lower the default setting; however, if you set this parameter below 15 seconds, the server cannot complete any directory operations.

FORMAT

SET DIRECTORY-INFO-FLUSH-AGE *seconds*

PARAMETER

seconds

Specifies the length of time, in seconds (by default, 300).

EXAMPLE

This example shows how to set the **DIRECTORY-INFO-FLUSH-AGE** interval to 600 seconds.

```
NFS-CONFIG>SET DIRECTORY-INFO-FLUSH-AGE 600  
NFS-CONFIG>
```

SET DIRECTORY-INFO-IDLE-FLUSH-AGE

This parameter controls how long cached headers and data buffers can remain in the cache for a directory that is not being accessed by any client.

Unless the cache-interrupt parameters are on, cached headers and buffers are not automatically discarded when an OpenVMS user attempts to access their directories on disk. The **DIRECTORY-INFO-IDLE-FLUSH-AGE** parameter specifies a period after which the server discards cached information unless a client is actively accessing it (requiring rereads from disk if the information is needed again).

This parameter is a trade-off between response time and concurrency between information stored in the cache and on the disk.

You can raise or lower the default setting; however, if you set this parameter below 15 seconds, the server cannot complete any directory operations.

FORMAT

SET DIRECTORY-INFO-IDLE-FLUSH-AGE *seconds*

PARAMETER

seconds

Specifies the length of time, in seconds (by default, 150).

EXAMPLE

This example shows how to set the **DIRECTORY-INFO-IDLE-FLUSH-AGE** interval to 300 seconds.

```
NFS-CONFIG>SET DIRECTORY-INFO-IDLE-FLUSH-AGE 300
NFS-CONFIG>
```

SET FILE-CACHE-TIMER-INTERVAL

Determines how often the MultiNet NFS Server scans the cache, checking the other parameters to see if their timers have expired, and processes those that have.

FORMAT

SET FILE-CACHE-TIMER-INTERVAL *seconds*

PARAMETER

seconds

Specifies the length of time, in seconds (by default, 30).

Note! The default setting for the FILE-CACHE-TIMER-INTERVAL parameter, 30 seconds, is normally not changed during configuration.

EXAMPLE

This example shows how to set the FILE-CACHE-TIMER-INTERVAL interval to 15 seconds.

```
NFS-CONFIG>SET FILE-CACHE-TIMER-INTERVAL 15  
NFS-CONFIG>
```

SET FILE-INFO-FLUSH-AGE

Controls how long cached headers and data buffers for a file can remain in the cache.

Unless the cache-interrupt parameters are on, cached headers and buffers are not automatically discarded when an OpenVMS user attempts to access their files on disk. The FILE-INFO-FLUSH-AGE parameter specifies a period after which the server discards cached information (requiring rereads from disk if the information is needed again).

This parameter is a trade-off between response time and concurrency of information stored in the cache and on the disk.

You can raise or lower the default setting; however, if you set this parameter below 15 seconds, the server cannot complete any file operations.

FORMAT

SET FILE-INFO-FLUSH-AGE *seconds*

PARAMETER

seconds

Specifies the length of time, in seconds (by default, 1200).

EXAMPLE

This example shows how to set the FILE-INFO-FLUSH-AGE interval to 2400 seconds.

```
NFS-CONFIG>SET FILE-INFO-FLUSH-AGE 2400
NFS-CONFIG>
```

SET FILE-INFO-IDLE-FLUSH-AGE

Controls how long cached headers and data buffers for a file that is not being accessed by a client can remain in the cache.

Unless the cache-interrupt parameters are on, cached headers and buffers are not automatically discarded when an OpenVMS user attempts to access their files on disk. The FILE-INFO-IDLE-FLUSH-AGE parameter specifies a period after which the server discards cached information unless a client is actively accessing it (requiring rereads from disk if the information is needed again).

This parameter is a trade-off between response time and the concurrency between information stored in the cache and on the disk.

You can raise or lower the default setting; however, if you set this parameter below 15 seconds, the server cannot complete any file operations.

FORMAT

SET FILE-INFO-IDLE-FLUSH-AGE *seconds*

PARAMETER

seconds

Specifies the length of time, in seconds (by default, 600).

EXAMPLE

This example shows how to set the FILE-INFO-IDLE-FLUSH-AGE interval to 1200 seconds.

```
NFS-CONFIG>SET FILE-INFO-IDLE-FLUSH-AGE 1200  
NFS-CONFIG>
```


SET MAXIMUM-CACHE-BUFFERS

Determines the maximum number of cached data buffers allowed simultaneously for the cache as a whole.

FORMAT

SET MAXIMUM-CACHE-BUFFERS *buffers*

PARAMETER

buffers

Specifies the number of data buffers. Each data buffer holds 16 disk blocks; the default is 3000.

Note! Unless the setting for MAXIMUM-CACHE-BUFFERS is large enough to allow the cache to hold the largest files the client will access, performance will be severely degraded for those files. Each cached data buffer holds 16 disk blocks.

EXAMPLE

This example shows how to set the MAXIMUM-CACHE-BUFFERS parameter to 250 buffers.

```
NFS-CONFIG>SET MAXIMUM-CACHE-BUFFERS 250  
NFS-CONFIG>
```

SET MAXIMUM-CACHE-FILES

Determines the maximum number of cached file headers allowed simultaneously for the cache as a whole.

FORMAT

SET MAXIMUM-CACHE-FILES *files*

PARAMETER

files

Specifies the maximum number of files.

EXAMPLE

This example shows how to set the MAXIMUM-CACHE-FILES parameter to 1500 files.

```
NFS-CONFIG>SET MAXIMUM-CACHE-FILES 1500  
NFS-CONFIG>
```

SET MAXIMUM-DIRTY-BUFFERS

Controls the functions of the optional writeback feature of the directory and file cache. If the writeback cache is enabled by setting the SECONDS-BEFORE-WRITEBACK parameter to a non-zero value, and the number of modified buffers in the cache exceeds this limit, a write operation is started immediately. A value of zero means that there is no limit to the number of buffers the NFS Server can create.

FORMAT

SET MAXIMUM-DIRTY-BUFFERS *buffers*

PARAMETER

buffers

Specifies the number of buffers (by default, 0).

EXAMPLE

This example shows how to set the MAXIMUM-DIRTY-BUFFERS parameter to 10 buffers.

```
NFS-CONFIG>SET MAXIMUM-DIRTY-BUFFERS 10
NFS-CONFIG>
```

SET MAXIMUM-FILESYSTEM-BUFFERS

Determines the maximum number of cached data buffers allowed simultaneously for a single file system on a per-mount-point basis.

FORMAT

SET MAXIMUM-FILESYSTEM-BUFFERS *buffers*

PARAMETER

buffers

Specifies the number of data buffers. Each data buffer holds 16 disk blocks; the default is 500.

Note! Unless the setting for MAXIMUM-FILESYSTEM-BUFFERS is large enough to allow the cache to hold the largest files the client will access, performance will be severely degraded for those files. Each cached data buffer holds 16 disk blocks.

EXAMPLE

This example shows how to set the MAXIMUM-FILESYSTEM-BUFFERS parameter to 250 buffers.

```
NFS-CONFIG>SET MAXIMUM-FILESYSTEM-BUFFERS 250  
NFS-CONFIG>
```

SET MAXIMUM-FILESYSTEM-CHANNELS

Determines the maximum number of open channels allowed simultaneously for a single file system on a per-mount-point basis.

FORMAT

SET MAXIMUM-FILESYSTEM-CHANNELS *channels*

PARAMETER

channels

Specifies the maximum number of open channels (by default, 50).

EXAMPLE

This example shows how to set the MAXIMUM-FILESYSTEM-CHANNELS to 10 channels.

```
NFS-CONFIG>SET MAXIMUM-FILESYSTEM-CHANNELS 10
NFS-CONFIG>
```

SET MAXIMUM-FILESYSTEM-FILES

Determines the maximum number of cached file headers allowed simultaneously for single file systems on a per-mount-point basis.

FORMAT

SET MAXIMUM-FILESYSTEM-FILES *files*

PARAMETER

files

Specifies the maximum number of cached files (by default, 3000).

EXAMPLE

This example shows how to set the MAXIMUM-FILESYSTEM-FILES to 1500 files.

```
NFS-CONFIG>SET MAXIMUM-FILESYSTEM-FILES 1500  
NFS-CONFIG>
```

SET MAXIMUM-OPEN-CHANNELS

Determines the maximum number of open channels allowed simultaneously for the cache as a whole.

FORMAT

SET MAXIMUM-OPEN-CHANNELS *channels*

PARAMETER

channels

Specifies the maximum number of open channels (by default, 50).

EXAMPLE

This example shows how to set the MAXIMUM-OPEN-CHANNELS to 100 channels.

```
NFS-CONFIG>SET MAXIMUM-OPEN-CHANNELS 100  
NFS-CONFIG>
```

SET MAXIMUM-QUEUED-REMOVES

Sets a limit on the number of remove operations that can be queued in the delete-behind cache.

This parameter affects how client users perceive the speed at which directories and files are deleted. The OpenVMS file deletion operation is very slow. The MultiNet NFS Server uses its delete-behind queue to hide some of the deletion delay from the client user. When a request to delete a directory or file arrives, the request is answered immediately, but usually the delete request is only enqueued to the OpenVMS file system.

The MAXIMUM-QUEUED-REMOVES parameter limits the number of requests that can be enqueued. When that number is reached, the next delete request must wait until the next enqueued request has completed.

Note! This delay can be significant if the next request is to delete a large directory; directory deletions always occur synchronously, and each file in a directory must be deleted before the directory itself is deleted.

Therefore, the parameter setting defines when, in a series of deletions, the client user will perceive the OpenVMS deletion delay.

FORMAT

SET MAXIMUM-QUEUED-REMOVES *value*

PARAMETER

value

Specifies the maximum number of queued operations. A value of 0 disables the delete-behind cache, making all delete operations synchronous. The default is 25.

EXAMPLE

This example shows how to set the MAXIMUM-QUEUED-REMOVES parameter to 10 files.

```
NFS-CONFIG>SET MAXIMUM-QUEUED-REMOVES 10  
NFS-CONFIG>
```


SET MAXIMUM-WRITE-JOBS

Limits the number of simultaneous write operations that can occur when the writeback cache is enabled.

FORMAT

SET MAXIMUM-WRITE-JOBS *limit*

PARAMETER

limit

Specifies the maximum number of simultaneous write operations. A value of zero (the default) means there is no limit.

EXAMPLE

This example shows how to set the MAXIMUM-WRITE-JOBS parameter to 5 simultaneous write operations.

```
NFS-CONFIG>SET MAXIMUM-WRITE-JOBS 5  
NFS-CONFIG>
```

SET NUMBER-OF-DUPLICATE-REQUESTS-CACHED

Limits the number of requests that can be retained in the NFS Server's duplicate-request detection cache. The NFS Server uses this cache to store the most recent responses it has sent to clients that request directory and file access.

The duplicate-request detection cache operates with the cache that the RPC protocol module keeps of the transaction IDs (XIDs) of the last 400 requests it has seen. The RPC layer uses its cache to detect duplicate requests.

For example, if the network layer dropped a UDP packet containing a response to a client, the client would repeat the request after an interval, and the RPC protocol would notify the MultiNet NFS Server that the request was a duplicate. The server would look in its duplicate-request detection cache for the response to resend without repeating the original operation.

Note! Too low a value causes the following error message to display frequently on the OpenVMS console: "Duplicate Detected but not in cache." Too low a value can also cause an incorrect answer to be sent. A value above 400 has the same effect as 400 (400 is the maximum number of XIDs stored by the RPC protocol).

FORMAT

SET NUMBER-OF-DUPLICATE-REQUESTS-CACHED *value*

PARAMETER

value

Specifies the size of the duplicate request cache. By default, the cache stores the last 250 responses sent.

EXAMPLE

This example shows how to set the NUMBER-OF-DUPLICATE-REQUESTS-CACHED parameter to 300.

```
NFS-CONFIG>SET NUMBER-OF-DUPLICATE-REQUESTS-CACHED 300
NFS-CONFIG>
```

SET NUMBER-OF-RPC-TRANSPORTS

Limits the number of client requests that the MultiNet NFS Server can process simultaneously. When the set limit is reached, no new requests are processed until one of the requests in progress completes. Processing multiple requests simultaneously prevents a single client from locking out other clients while it is performing a slow operation.

FORMAT

SET NUMBER-OF-RPC-TRANSPORTS *value*

PARAMETER

value

Specifies the number of simultaneous operations. You can change this value to adjust the trade-off between concurrency and memory requirements. The default setting (10) allows the server to process 10 requests simultaneously.

EXAMPLE

This example shows how to set the NUMBER-OF-RPC-TRANSPORTS to 100 transports.

```
NFS-CONFIG>SET NUMBER-OF-RPC-TRANSPORTS 100  
NFS-CONFIG>
```

SET READ-ONLY-FLUSH-AGE

Limits how long idle channels can remain assigned to a file.

Applies to files that have been opened for read operations only; the READ-WRITE-FLUSH-AGE parameter applies to files that have been opened for both read and write operations. Closing a channel does not discard the data in the file headers and data buffers, and clients can continue to access the cached data without requiring that the file be reopened.

You can shorten or lengthen the timer interval to adjust trade-offs between improved response time and the overhead of keeping channels assigned.

FORMAT

SET READ-ONLY-FLUSH-AGE *seconds*

PARAMETER

seconds

Specifies the length of time, in seconds (by default,180).

EXAMPLE

This example shows how to set the READ-ONLY-FLUSH-AGE interval to 60 seconds.

```
NFS-CONFIG>SET READ-ONLY-FLUSH-AGE 60  
NFS-CONFIG>
```

SET READ-WRITE-FLUSH-AGE

Limits how long idle channels can remain assigned to a file.

Applies to files that have been opened for read operations only; the READ-WRITE-FLUSH-AGE parameter applies to files that have been opened for both read and write operations. Closing a channel does not discard the data in the file headers and data buffers, and clients can continue to access the cached data without requiring that the file be reopened. However, the file is locked from access via OpenVMS until the NFS Server releases the channel.

You can shorten or lengthen the timer interval to adjust trade-offs between improved response time and the overhead of keeping channels assigned.

FORMAT

SET READ-WRITE-FLUSH-AGE *seconds*

PARAMETER

seconds

Specifies the length of time, in seconds (by default, 60).

EXAMPLE

This example shows how to set the READ-WRITE-FLUSH-AGE interval to 15 seconds.

```
NFS-CONFIG>SET READ-WRITE-FLUSH-AGE 15
NFS-CONFIG>
```

SET SECONDS-BEFORE-WRITEBACK

Sets the length of time write operations are deferred before the data is written to disk.

FORMAT

SET SECONDS-BEFORE-WRITEBACK *seconds*

PARAMETER

seconds

Specifies the length of time in seconds. The default (0) disables the writeback cache.

DESCRIPTION

The directory and file cache normally function as a write-through cache. In this case, whenever a client is notified that a write request has completed, the data has been stored on the disk, and data integrity is guaranteed.

The optional writeback feature greatly increases the speed of write operations, as perceived by the user, by notifying the client that write operations are complete when the data is stored in cache memory on the server, but before it is written to disk. This increase in perceived write performance is achieved at the risk of data loss if the OpenVMS server crashes while a write operation is in progress or if, during a write operation, the server encounters an error such as insufficient disk space, insufficient disk quota, or a hardware write error.

When the server is unable to complete a writeback write operation, it discards the write operation, flags the file's cached header to indicate the error, and sends an error message in response to the next request for the file. However, if there is no new request before the affected header is discarded, or if the next request is from another user, data can be lost.

The SECONDS-BEFORE-WRITEBACK parameter determines whether the writeback feature is enabled and specifies how long the server will delay initiating a write operation after receiving data for a write request. The longer the delay, the greater the chance that the server can merge multiple small write operations into fewer, larger, and more efficient operations.

The default setting (0) disables the writeback feature. Any other value enables the feature. The recommended value for writeback delay is 5 seconds; little performance is gained from longer delays.

EXAMPLE

This example shows how to set the SECONDS-BEFORE-WRITEBACK interval to 5 seconds.

```
NFS-CONFIG>SET SECONDS-BEFORE-WRITEBACK 5  
NFS-CONFIG>
```

SET USE-DIRECTORY-BLOCKING-ASTS

Determines whether the server flushes the cache when an OpenVMS user attempts to access a directory from which cached information came.

Enabling blocking ASTs causes the server to discard the cached file header and all data buffers for a directory when an OpenVMS user attempts to access it on disk.

You must enable this parameter to allow PC clients to use the PC-NFSD remote printing function. Enabling this parameter also ensures that client users almost always receive the directory as it exists on disk. This concurrency is at the expense of the overhead of the additional interrupts and disk reads.

FORMAT

SET USE-DIRECTORY-BLOCKING-ASTS *value*

PARAMETER

value

Specify this parameter as 1 to enable blocking ASTs on directories (the default), or 0 to disable blocking ASTs.

EXAMPLE

This example shows how to turn off the USE-DIRECTORY-BLOCKING-ASTS parameter.

```
NFS-CONFIG>SET USE-DIRECTORY-BLOCKING-ASTS 0
NFS-CONFIG>
```

SET USE-FILE-BLOCKING-ASTS

Determines whether the server flushes the cache when an OpenVMS user attempts to access a file from which cached information came.

Enabling blocking ASTs causes the server to discard the cached file header and all data buffers for a file when an OpenVMS user attempts to access it on disk.

You must enable this parameter to allow PC clients to use the PC-NFSD remote printing function. Enabling this parameter also ensures that client users almost always receive the file as it exists on disk. This concurrency is at the expense of the overhead of the additional interrupts and disk reads.

FORMAT

SET USE-FILE-BLOCKING-ASTS *value*

PARAMETER

value

Specify this parameter as 1 to enable blocking ASTs on files (the default), or 0 to disable blocking ASTs.

EXAMPLE

This example shows how to turn off the USE-FILE-BLOCKING-ASTS parameter.

```
NFS-CONFIG>SET USE-FILE-BLOCKING-ASTS 0
NFS-CONFIG>
```


SHOW

Displays information about the configuration of the NFS Server and NFS Client.

FORMAT

SHOW *[mount_point_name]* / *[option]*

PARAMETERS

mount_point_name

Specifies the name of a specific file system's mount point. If not specified, SHOW displays:

- The file system export list—A list of the file systems available to the network. A mount restrictions list appears next to the entry for each file system, showing the clients that can access the file system (unless all clients can access it).
- The UID/GID-to-OpenVMS user name translation list.
- The global parameter list—The names and settings of the server's global parameters.

option

Specifies the set of configuration parameters to be viewed. Accepted values are "exported-file-systems", "nfs-groups", "nfs-passwd-files", "parameters", and "uid-translations".

QUALIFIER

/FULL

Displays information in greater detail. Without /FULL, SHOW truncates the mount restriction list at 80 columns and displays ellipses (. . .) to indicate there are more entries. With /FULL, SHOW displays the full mount restriction list and the settings of each global parameter.

SPAWN

Executes a single DCL command, or if entered without options, starts a subprocess with the same effect as PUSH. To return from DCL, use the LOGOUT command. If the MULTINET_DISABLE_SPAWN logical is set, SPAWN does not work.

FORMAT

SPAWN [*command*]

PARAMETER

command

Specifies a command to execute. If you omit command, a DCL command line subprocess is created.

QUALIFIERS

/INPUT=file-spec

Specifies an input file to the command you enter with SPAWN.

/LOGICAL_NAMES

/NOLOGICAL_NAMES

Specifies that logical names and logical name tables are not copied to the subprocess.

/SYMBOLS

/NOSYMBOLS

Specifies that global and local names are not passed to the subprocesses.

/WAIT

/NOWAIT

Returns control without waiting for the command to complete. Do not use this qualifier with commands that have prompts or screen displays.

/OUTPUT=file-spec

Specifies a file that retains the output of the command invoked with SPAWN. This qualifier only works when a single command is entered without creating a DCL subprocess. In addition, this qualifier is positional; you must enter it immediately after SPAWN or other qualifiers.

EXAMPLES

This example displays terminal information, captures the output in a file, then displays the information with the TYPE command.

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
```

```
NFS-CONFIG>SPAWN/OUTPUT=FOO. SHOW TERM
NFS-CONFIG>SPAWN TYPE FOO.
```

```
. .
```

This example invokes a command procedure.

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
NFS-CONFIG>SPAWN @COMPROC
```

```
. .
```

This example displays help information about NFS-CONFIG. Use the LOGOUT command to return control to NFS-CONFIG.

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
NFS-CONFIG>SPAWN
$ HELP MULTINET CONFIGURE /NFS
. .
$ LOGOUT
NFS-CONFIG>
```

STATUS

Displays the status of the current configuration.

FORMAT

STATUS

EXAMPLE

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in NFS file server configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>STATUS
This is the MultiNet NFS configuration program Version 4.4(76)
There are 19/1024 entries in the exported NFS filesystem list.
There are 1/100 entries in the NFS passwd file list.
There are 10/5000 entries in the UID translation list.
There is NO selected FILESYSTEM entry.
The configuration MULTINET:NFS.CONFIGURATION has not been modified.
NFS-CONFIG>QUIT
$
```

USE

Reads in a configuration file. (Functionally equivalent to GET; see GET for additional information.)

FORMAT

USE *config_file*

PARAMETER

config_file

Specifies the name of the configuration file to read.

VERSION

Displays the NFS-CONFIG version and release information.

FORMAT

VERSION

EXAMPLE

```
$ MULTINET CONFIGURE /NFS  
MultiNet NFS Configuration Utility 4.4(76)  
[Reading in NFS file server configuration from MULTINET:NFS.CONFIGURATION]  
NFS-CONFIG>VERSION  
This is the MultiNet NFS configuration program Version 4.4 (nnn)  
NFS-CONFIG>QUIT
```

WRITE

Writes the current configuration to a file. (Functionally equivalent to SAVE.)

FORMAT

WRITE [*config_file*]

PARAMETER

config_file

Specifies the name of the configuration file to write, by default, the file from which the configuration was read.

EXAMPLE

```
$ MULTINET CONFIGURE /NFS
MultiNet NFS Configuration Utility 4.4 (nnn)
[Reading in NFS file server configuration from MULTINET:NFS.CONFIGURATION]
NFS-CONFIG>WRITE
[Writing configuration to MULTINET_ROOT:[MULTINET]NFS.CONFIGURATION.7]
NFS-CONFIG>EXIT
[Writing configuration to MULTINET:NFS.CONFIGURATION]
[Writing Startup file MULTINET:START_MULTINET.COM]
[Changes take effect after the next VMS reboot]
$
```


Chapter 7

NTYCP Command Reference

This chapter describes the Network Terminal Device Control Program (NTYCP) commands you can use to create terminal devices.

To invoke NTYCP as an OpenVMS "foreign" command:

```
$ NTYCP := $MULTINET:NTYCP
```

To invoke NTYCP interactively:

```
$ RUN MULTINET:NTYCP
NTYCP> CREATE PORT NTYnnnn /NODE=host-name /PORT=port-number
NTYCP> EXIT
```

To set up the terminal characteristics:

```
$ SET TERMINAL NTYnnn:/PERMANENT/NOBROADCAST/NOTYPEAHEAD/NOWRAP
```

To set up spooling:

```
$ SET DEVICE/SPOOLED=(queue-name,SYS$SYSDEVICE:) NTYnnnn:
```

To initialize and start the queue:

```
$ INITIALIZE/QUEUE/ON=NTYnnnn: queue-name /PROCESSOR=MULTINET_NTYSMB/START
```

This example shows how to set up a print queue connected to an HP LaserJet printer with a JetDirect card:

```
$ NTYCP := $MULTINET:NTYCP
$ NTYCP CREATE PORT NTY1001/NODE=hp-laserjet/PORT=9100
%NTYCP-S-CREPORT, device _NTY1001: created to host 192.1.1.5, port 9100
$ SET TERMINAL/PERMANENT NTY1001:/NOBROADCAST/NOTYPEAHEAD/NOWRAP
$ INITIALIZE/QUEUE/ON=NTY1001: HP_LASERJET/PROCESSOR=MULTINET_NTYSMB/
START
```

Command Summary

Table 7-1 lists the NTYCP commands.

Table 7-1 NTYCP Command Summary

NTYCP Command	Description
CREATE_PORT	Creates a new network terminal port device.
DELETE_PORT	Deletes an NTY device created by the CREATE_PORT command.
EXIT	Exits from NTYCP to DCL command mode.
HELP	Displays help text about NTYCP commands.
MODIFY_PORT	Modifies (changes) an existing network terminal port device.

CREATE PORT

Creates a new network terminal port device. The device links the VMS terminal driver to a TCP/IP network connection directed to the destination address specified by the /HOST qualifier and the /PORT or /SERVICE qualifier.

You can use network terminal (NTY) devices with the MULTINET_NTYSMB print symbiont to provide VMS print queue support for network-connect printers. You can also use them with user-written applications that need a simple terminal-style I/O interface to a remote terminal, plotter, etc.

FORMAT

CREATE PORT *device-name*

Command Qualifiers	Defaults
/[NO]LOG /LOGICAL=(logical-name-options...) /NODE=node-name-or-address /PORT=port-number /SERVICE=service-name	/LOG

PARAMETER

device-name

Name of the NTY port device to be created. If specified, the device name must be of the form NTY*n*, where *n* is a device unit number, which must be in the range 1-9999. The specified device must not already exist. If omitted, the next available unit number will be used.

QUALIFIERS

/LOG

Controls whether a log message is generated on successful completion of the command. The default is /LOG.

/LOGICAL=(logical-name-options...)

Causes NTYCP to create a logical name for the created NTY device. This qualifier takes one or more of the keyword options specified in Table 7-2. If you specify multiple options, separate them by commas. You must have access to the specified logical name table and sufficient privilege to

create the logical name.

Table 7-2 NTYCP CREATE PORT /LOGICAL Keyword Options

Keyword	Description
NAME = <i>logical-name</i>	The logical name to be created. You must specify this option if you use /LOGICAL.
TABLE = <i>table-name</i>	Specifies the logical name table in which the logical name should be created. This can be the actual name of a table, or one of the key-words PROCESS, GROUP, SYSTEM. The default is TABLE=PROCESS.
MODE = <i>mode-name</i>	Specifies the access mode in which the logical name should be created. The keywords are EXECUTIVE, SUPERVISOR, USER. The default is MODE=SUPERVISOR.

/NODE=node-name-or-address

Specifies the name or numeric IP address of the remote node. You must specify this qualifier.

If you specify a node name, it is translated into an IP address. Only one IP address may be configured per NTY device. If the destination system is a host with multiple IP addresses, and not all addresses are directly reachable from your local system, you should specify the IP address numerically to ensure that a reachable address is configured.

/PORT=port-number

Specifies a TCP port number on the remote node to which the connection will be made. You must specify either the /PORT qualifier or the /SERVICE qualifier with the command.

/SERVICE=service-name

Specifies the name of a TCP service that translates to a port number to which the connection will be made. You may specify any TCP service name present in the local hosts/services table. You must specify either the /PORT qualifier or the /SERVICE qualifier with the command.

DELETE PORT

Deletes an NTY device created by the NTYCP CREATE PORT command.

FORMAT

DELETE PORT *device-name*

Command Qualifiers	Defaults
/[NO]LOG	/LOG

PARAMETER

device-name

Name of the NTY port device to be deleted.

QUALIFIER

/LOG

Controls whether a log message is generated on successful completion of the command. The default is /LOG.

EXIT

Causes NTYCP to exit back to DCL command mode.

FORMAT

EXIT

HELP

Displays help text about NTYCP commands.

FORMAT

HELP *[topic]*

PARAMETER

topic

A command name or other topic in the NTYCP help library. If omitted, a list of topics displays.

MODIFY PORT

Modifies (changes) an existing network terminal port device. The device links the VMS terminal driver to a TCP/IP network connection directed to the destination address specified by the /HOST qualifier and the /PORT or /SERVICE qualifier.

FORMAT

MODIFY_PORT *device-name*

Command Qualifiers	Defaults
/[NO]LOG /LOGICAL=(logical-name-options...) /NODE=node-name-or-address /PORT=port-number /SERVICE=service-name	/LOG

PARAMETERS

modify-object

Name of the NTY object to be modified (changed).

port-name

Name of the NTY port device to be modified (changed).

QUALIFIERS

/LOG

Controls whether a log message is generated on successful completion of the command. The default is /LOG.

/LOGICAL=(logical-name-options...)

This is the logical name for the NTY device you want to modify. This qualifier takes one or more of the keyword options specified in Table 7-3. If you specify multiple options, separate them by commas. You must have access to the specified logical name table and sufficient privilege to modify the logical name.

Table 7-3 NTYCP MODIFY PORT /LOGICAL Keyword Options

Keyword	Description
NAME = <i>logical-name</i>	The logical name to be created. You must specify this option if you use /LOGICAL.

Table 7-3 NTYCP MODIFY PORT /LOGICAL Keyword Options (Continued)

Keyword	Description
TABLE = <i>table-name</i>	Specifies the logical name table in which the logical name should be created. This can be the actual name of a table, or one of the keywords PROCESS, GROUP, SYSTEM. The default is TABLE=PROCESS.
MODE = <i>mode-name</i>	Specifies the access mode in which the logical name should be created. The keywords are EXECUTIVE, SUPERVISOR, USER. The default is MODE=SUPERVISOR.

/NODE=node-name-or-address

Specifies the name or numeric IP address of the remote node. You must specify this qualifier.

If you specify a node name, it is translated into an IP address. Only one IP address may be configured per NTY device. If the destination system is a host with multiple IP addresses, and not all addresses are directly reachable from your local system, you should specify the IP address numerically to ensure that a reachable address is configured.

/PORT=port-number

Specifies a TCP port number on the remote node to which the connection will be made. You must specify either the /PORT qualifier or the /SERVICE qualifier with the command.

/SERVICE=service-name

Specifies the name of a TCP service that translates to a port number to which the connection will be made. You may specify any TCP service name present in the local hosts/services table. You must specify either the /PORT qualifier or the /SERVICE qualifier with the command.

Chapter 8

ACCESS-CONFIG Commands

This chapter describes the ACCESS-CONFIG commands you can use to examine, modify, and save configuration files for MultiNet Secure/IP.

To invoke the ACCESS-CONFIG utility:

```
$ MULTINET CONFIGURE /ACCESS
```

At any ACCESS-CONFIG prompt, type ? to list the available commands.

Online help for each ACCESS-CONFIG command is available through the HELP command. For details on configuring MultiNet Secure/IP, refer to Chapter 4 of the *MultiNet for OpenVMS Installation and Administrator's Guide*.

Command Summary

Table 8-1 lists the commands you can use at the ACCESS-CONFIG prompt.

Table 8-1 ACCESS-CONFIG Command Summary

Command	Description
ADD	Allows multiple address parameters to be added as a comma-separated list.
ATTACH	Detaches the terminal from the calling process and reattaches it to another access.
EXIT	Saves the current configuration, if it has been modified, then quits.
GET	Reads in a configuration file. (Functionally equivalent to USE.)
HELP	Displays help information.
NETCONTROL	Transfers control to a configuration manager subsystem that contacts the NETCONTROL server on local or remote hosts.

Table 8-1 ACCESS-CONFIG Command Summary (Continued)

Command	Description
PUSH	Starts a DCL subprocess.
QUIT	Exits and prompts to save the changes if you changed the configuration.
RELOAD	Reloads MultiNet Secure/IP from the MULTINET:START_ACCESS.COM configuration file.
REMOVE	Allows multiple address parameters to be removed.
SAVE	Writes the current configuration file. (Functionally equivalent to WRITE.)
SET	Sets MultiNet Secure/IP global parameters.
SHOW	Displays the current configuration of the local MultiNet Secure/IP software. If only the MultiNet Secure/IP Client is running, the Secure/IP Server information is suppressed.
SPAWN	Executes a single DCL command, or, if entered without options, starts a subprocess with the same effect as PUSH.
STATUS	Displays the version and whether the configuration has been modified.
USE	Reads in a configuration file. (Functionally equivalent to GET.)
VERSION	Displays the version number.
WRITE	Writes the current configuration to a file. (Functionally equivalent to SAVE.)

Most configuration changes rely on the SET command. After setting or changing parameters, ACCESS-CONFIG displays directions for the utilities that must be run as it exits. These directions are summarized in the following table.

If you change this parameter:	Do the following:
DECNET-LOGIN	Restart the Client with @MULTINET:START_ACCESS.
DECTERM-LOGIN	Restart the Client with @MULTINET:START_ACCESS.
DEFAULT-METHOD	Reload the Server with MULTINET NETCONTROL ACCESS RELOAD.
FTP-ENABLED	Restart the Client with @MULTINET:START_ACCESS.
LOCAL-DEVICES	Restart the Client with @MULTINET:START_ACCESS.
LOCAL-NETWORKS	Reload the Server with MULTINET NETCONTROL ACCESS RELOAD.

If you change this parameter:	Do the following:
LOCAL-PASSWORDS	Reload the Server with MULTINET NETCONTROL ACCESS RELOAD.
MULTINET-LOGIN	Restart the Client with @MULTINET:START_ACCESS.
MUTUAL-AUTHENTICATION	Restart the Client with @MULTINET:START_ACCESS.
NETWORK-LOGIN	Restart the Client with @MULTINET:START_ACCESS.
SERVER-ADDRESS	Restart the Client and Server with @MULTINET:START_ACCESS and @MULTINET:START_SERVER.
SERVER-PORT	Restart the Client and Server with @MULTINET:START_ACCESS and @MULTINET:START_SERVER.
TELNET-ENABLED	Restart the Client with @MULTINET:START_ACCESS.
TICKET-LIFETIME	Restart the Client with @MULTINET:START_ACCESS.
USER-SKEY	Reload the Server with MULTINET NETCONTROL ACCESS RELOAD.

Note! After you make changes with ACCESS-CONFIG, you are prompted as to what to do to make the changes take effect.

ADD

Allows multiple address parameters to be added as a comma-separated list. Network parameters require a subnet mask, so use the format IP-NETWORK/NETWORK-MASK. You can use the keyword DEFAULT as the network mask. The mask will be derived from the given ip-network.

FORMAT

```
ADD  [ local-networks ]  
      [ untrusted-hosts ]  
      [ server-addresses ]
```

PARAMETERS

local-networks

Specifies the address of the local network you want to add.

untrusted-hosts

Specifies the address of the untrusted hosts you want to add.

server-address

Specifies the address of the server you want to add.

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS  
MultiNet Access Configuration Utility 4.4(n)  
[Reading in configuration from MULTINET:START_ACCESS.COM]  
ACCESS-CONFIG>ADD LOCAL-NETWORKS 161.44.72.0/255/255/255/0  
ACCESS-CONFIG>ADD UNTRUSTED-HOSTS 161.44.72.3,161.44.72.4  
ACCESS-CONFIG>ADD SERVER-ADDRESS 161.44.72.1  
[Writing configuration to MULTINET:START_ACCESS.COM]  
ACCESS-CONFIG>
```

ATTACH

Detaches the terminal from the calling process and reattaches it to another process. Use the SPAWN SHOW PROCESS /SUBPROCESSES command to list the names of the subprocesses. Use the DCL LOGOUT command to return to the original process. If the MULTINET_DISABLE_SPAWN logical is defined, ATTACH does not work.

FORMAT

ATTACH *process-name*

PARAMETER

process_name

Specifies the name of a process to which you want your terminal attached. Not all subprocesses can be attached; some testing may be required.

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>SPAWN
$ MM
MM>SPAWN SHOW PROCESS /SUBPROCESSES
. . .
There are 3 processes in this job:
  _TWA42:
    PROC_1
    PROC_2 (*)
MM>ATTACH _TWA42:
ACCESS-CONFIG>ATTACH PROC_1
MM>EXIT
$ LOGOUT
ACCESS-CONFIG>
```

This example shows how to create and exit attached subprocesses. The SPAWN command creates a subprocess. Then MM is invoked from that subprocess. Next, the SPAWN SHOW PROCESS /SUBPROCESSES command lists all the active subprocesses: _TWA42: is ACCESS-CONFIG, PROC_1 is MM, and PROC_2 is SHOW PROCESS /SUBPROCESSES.

The ATTACH _TWA42: command hands control to ACCESS-CONFIG. The ATTACH PROC_1 command hands control to MM. When MM is exited, control returns to the first subprocess. Then LOGOUT returns control to ACCESS-CONFIG.

EXIT

Saves the current configuration, if it has been modified, then quits.

FORMAT

EXIT

EXAMPLE

This example shows that when the configuration has not been changed, a message indicates that the configuration file has not been updated.

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>EXIT
[Configuration not modified, so no update needed]
$
```

This example shows that when the configuration has been changed, a message indicates that the configuration file has been updated.

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>command
ACCESS-CONFIG>EXIT
[Writing configuration to MULTINET:START_ACCESS.COM]
$
```


GET

Reads in a configuration file. (Functionally equivalent to USE.) After using GET, you can use other ACCESS-CONFIG commands to display the new configuration.

FORMAT

GET *config_file*

PARAMETER

config_file

Specifies the name of an input configuration file.

EXAMPLE

This example reads in the MULTINET:NEW_CONFIG.CFG file.

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>GET MULTINET:NEW_CONFIG.CFG
[Reading in configuration from MULTINET:NEW_CONFIG.CFG;1]
ACCESS-CONFIG>EXIT
```

HELP

Displays help information.

FORMAT

HELP [*topics*]

PARAMETER

topics

Specifies a space-delimited list of words beginning with a topic, which may be followed by subtopics. The default topic is **HELP**.

EXAMPLE

```
ACCESS-CONFIG>HELP

HELP
    Invokes command help.
    Format
    HELP    [topics]
Additional information available:
ATTACH      Command_Summary      EXIT      GET      HELP
NETCONTROL  PUSH      QUIT      RELOAD   SAVE     SET
SHOW        SPAWN      STATUS    USE       VERSION  WRITE
Topic?
```

NETCONTROL

Transfers control to a configuration manager subsystem that contacts the NETCONTROL server on local or remote hosts. Use NETCONTROL RELOAD to reload the MultiNet Secure/IP Server. After invoking NETCONTROL, issue commands to the NETCONTROL server to affect MULTINET_SERVER operations at the site.

FORMAT

NETCONTROL [*host*]

PARAMETERS

host

Specifies a host name. It defaults to the local host if no host is specified.

restrictions

The NETCONTROL server is normally protected from unauthorized access by a restriction list.

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>NETCONTROL
Connected to NETCONTROL server on "127.0.0.1"
< FLOWERS.COM Network Control 4.4 (nnn) at Mon 17-April-2000 7:42am-PDT
ACCESS>? NETCONTROL command, one of the following:
ATTACH  PUSH      QUIT      QUOTE    SELECT   SPAWN    VERBOSE
or Command, one of the following:
DEBUG   NOOP      RELOAD   VERSION
ACCESS>RELOAD
< ACCESS database reload done
ACCESS>QUIT
ACCESS-CONFIG>
```

This example reloads the ACCESS server. You can run MULTINET NETCONTROL from the DCL command line also:

```
$ MULTINET NETCONTROL
NETCONTROL>SELECT ACCESS
ACCESS>RELOAD
ACCESS>QUIT
```

PUSH

Starts a DCL subprocess. To return control to ACCESS-CONFIG from the DCL command line, use the LOGOUT command. PUSH does not function if the MULTINET_DISABLE_SPAWN logical is defined.

FORMAT

PUSH

EXAMPLE

In this example, PUSH is used to go to the DCL command line to disable broadcasts. The LOGOUT command returns control to ACCESS-CONFIG.

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>PUSH$ SET TERMINAL /NOBROADCAST
$ LOGOUT
ACCESS-CONFIG>
```

QUIT

Exits and prompts to save the changes if the configuration has been modified.

FORMAT

QUIT

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>QUIT
Configuration modified, do you want to save it ? [NO]NO
$
```

RELOAD

Reloads MultiNet Secure/IP from the MULTINET:START_ACCESS.COM configuration file.

FORMAT

RELOAD

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>RELOAD
Connected to NETCONTROL server on "127.0.0.1"
< FNORD.IRIS.COM Network Control 4.4(nnn) at Mon 17-April-2000 7:42am-PDT
< ACCESS database reload done
ACCESS-CONFIG>
```

REMOVE

Allows removal of multiple address entries from a comma-separated list. Network parameters require a subnet mask, so use the format IP-NETWORK/NETWORK-MASK. You can use the keyword DEFAULT as the network mask. The mask will be derived from the given ip-network.

FORMAT

```
REMOVE [ local-networks ]  
          [ untrusted-hosts ]  
          [ server-addresses ]
```

PARAMETERS

local-networks

Specifies the address of the local network you want to remove.

untrusted-hosts

Specifies the address of the untrusted hosts you want to remove.

server-address

Specifies the address of the server you want to remove.

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS  
MultiNet Access Configuration Utility 4.4(n)  
[Reading in configuration from MULTINET:START_ACCESS.COM]  
ACCESS-CONFIG>REMOVE LOCAL-NETWORKS 161.44.72.0/255/255/255/0  
ACCESS-CONFIG>REMOVE UNTRUSTED-HOSTS 161.44.72.3,161.44.72.4  
ACCESS-CONFIG>REMOVE SERVER-ADDRESS 161.44.72.1  
[Writing configuration to MULTINET:START_ACCESS.COM]  
ACCESS-CONFIG>
```

SAVE

Writes the current configuration file. (Functionally equivalent to WRITE.)

FORMAT

SAVE [*config_file*]

PARAMETER

config_file

Specifies the name of the output configuration file. The default is the same file from which the configuration was read.

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>SAVE
[Writing configuration to MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>
```


SET

Sets MultiNet Secure/IP global parameters.

FORMAT

SET *[decnet-login]*
 [decterm-login]
 [default-method]
 [ftp-enabled]
 [kerberos-principal]
 [local-devices]
 [local-networks]
 [local-passwords]
 [multinet-login]
 [mutual-authentication]
 [network-login]
 [server-address]
 [server-port]
 [telnet-enabled]
 [ticket-lifetime]
 [untrusted-host]
 [user-skey]

PARAMETERS

decnet-login

When DECNET-LOGIN is TRUE, plain text passwords (OpenVMS or Kerberos) are allowed when logging in via DECnet SET HOST. When DECNET-LOGIN is FALSE (the default), users must authenticate using their default authentication methods. A DECnet login occurs when a user gets a Username: prompt on an RTcu: device.

decterm-login

When DECTERM-LOGIN is TRUE (the default), plain text passwords are allowed when logging in on pseudo-terminals created with the CREATE /TERMINAL /DETACH /NOLOGGED_IN command. When DECTERM-LOGIN is FALSE, the system forces users to authenticate using their default authentication methods.

default-method

Specifies the default authentication method for non-local logins. This is a system-wide default that can be overridden on a per-user basis by the system manager.

Accepted values are:

- CRYPTOCARD—Assigns CRYPTOCARD as the default for non-local logins.
- COMPAQ-PATHWAYS-SECURENET—Assigns Compaq Pathways SecureNet Key as the

default for non-local logins.

- **PLAINTEXT-PASSWORDS**—Assigns plain text passwords as the default for non-local logins. You can then selectively enable alternate methods for each user who needs stronger authentication.
- **SECURITY-DYNAMICS-SECURID**—Assigns Security Dynamics SecurID Card as the default for non-local logins.
- **BELLCORE-SKEY**—Assigns S/KEY as the default for non-local users.

ftp-enabled

Controls whether the MultiNet FTP server should use MultiNet Secure/IP to authenticate FTP connections that originate outside the trusted local network. By default, the MultiNet FTP server uses MultiNet Secure/IP for all offsite connections. **FTP-ENABLED** is **TRUE** when you install MultiNet Secure/IP.

kerberos-principal

Specifies which service name is used as a principal for Kerberos authentication. The default is **rcmd** (which is also used by the **TELNET** and **RLOGIN** services).

local-devices

Specifies a set of OpenVMS device mnemonics (**ddcu**) that are directly connected to the host computer system and considered part of the TLN. Local device designations are a full set or a subset of OpenVMS device specifications (for example, **FNORD\$TXA1** or **TT**). You may list more than one device. If the device designation contains a node name, this device is only considered local on the specified node. If you do not set **LOCAL-DEVICES**, directly connected devices use the default authentication method for the associated user. Also, if **LOCAL-PASSWORDS** is disabled, **LOCAL-DEVICES** is ignored.

local-networks

Specifies which networks are considered part of the TLN. Identify networks by IP address. When specifying more than one address, separate each address with a comma. For example, **161.44.224.0, 161.44.225.0**. By default, all networks on all known interfaces are considered local. If **LOCAL-NETWORKS** is defined, then only those networks explicitly listed are considered local. This parameter works with **LOCAL-PASSWORDS**. If **LOCAL-PASSWORDS** is disabled, the **LOCAL-NETWORKS** parameter is ignored.

CAUTION! If you define trusted local networks with the **SET LOCAL-NETWORKS** command, you must explicitly add the loopback network, **127.0.0/255.0.0**. It is not implicitly included in your TLN.

local-passwords

When **LOCAL-PASSWORDS** is **TRUE** (the default), plain text passwords are allowed when logging in from a local network or local device. This parameter acts as a global switch that determines whether a trusted local network is in effect (**SET LOCAL-PASSWORDS TRUE**) or not (**SET LOCAL-PASSWORDS FALSE**).

multinet-login

Specifies a command procedure that will run before any others immediately after users authenticate themselves. The specified command procedure runs before SYSLOGIN and LOGIN.COM.

mutual-authentication

When MUTUAL-AUTHENTICATION is TRUE, the MultiNet Secure/IP Client requires Kerberos authentication with the MultiNet Secure/IP Server. Enable this parameter only if Kerberos is configured on the MultiNet Secure/IP Client and Server. Mutual authentication requires that both the client and server systems be properly configured for Kerberos, and that the client system have a valid MULTINET:KERBEROS.SRVTAB file with a host *rcmd* service key.

Because the version of MultiNet Secure/IP prior to V2.0 does not support mutual authentication, MultiNet Secure/IP Client V2.0 does not use mutual authentication when it communicates with earlier versions of Secure/IP Server, even if MUTUAL-AUTHENTICATION is TRUE. The default is FALSE.

network-login

When NETWORK-LOGIN is TRUE (the default), users are granted Kerberos ticket-getting tickets when they log in to the MultiNet Secure/IP Client using Kerberos passwords within the TLN.

server-address

Specifies the IP address(es) of the host(s) running the authentication server; that is, the nodes with the ACCESS service enabled. You can specify more than one IP address for redundancy. Separate multiple addresses with commas. For example, 161.44.224.70, 161.44.224.23. By default, the authentication server address is the loopback IP address 127.0.0.1. It directs each host to use itself when authenticating.

server-port

Specifies the privileged port number on which the authentication server listens. The default is port 702. The port number must be less than 1024.

telnet-enabled

Controls whether the MultiNet TELNET server should use MultiNet Secure/IP to authenticate TELNET connections that originate outside the trusted local network. The default is the TELNET server uses MultiNet Secure/IP for all offsite connections. TELNET-ENABLED is TRUE when you install MultiNet Secure/IP.

ticket-lifetime

Specifies the duration, in minutes, that a Kerberos ticket remains active for a user. This parameter overrides the ticket lifetime defined with the MULTINET KERBEROS DATABASE EDIT command (see the *MultiNet for OpenVMS Administrator's Reference*). The parameter range is 1 to 1275 minutes (21.25 hours). The default duration is eight hours (480 minutes).

untrusted-host

Specifies the IP address of a host to be excluded from the trusted local network. For example, if there is a modem server connected within your trusted local network, you can exclude it with the

UNTRUSTED-HOST parameter to force dial-in users to authenticate themselves via MultiNet Secure/IP.

user-skey

When USER-SKEY is TRUE (the default), users can use S/KEY without a system manager's intervention. You can enable S/KEY by initializing a private S/KEY sequence using the MULTINET SKEY/INITIALIZE command. If disabled, an S/KEY sequence can only be used if a system manager creates a sequence for the user or modifies the user's default method to "SKEY."

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>SET DEFAULT-METHOD BELLCORE-SKEY
```

SHOW

Displays the current configuration of the local MultiNet Secure/IP software. If only the MultiNet Secure/IP Client is running, the MultiNet Secure/IP Server information is suppressed.

FORMAT

SHOW

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>SHOW
Secure/IP Server Parameters
-----
Default Method:                               Compaq Pathways SecureNet Key
Allow Local Passwords:                       TRUE
Local Network(s):                            <default>
Untrusted Host(s):                           <none>
Allow user control of S/KEY                   TRUE
Allow key display (/SHOW):                   TRUE

Secure/IP Client Parameters
-----
Telnet Enabled:                               FALSE
FTP Enabled:                                  TRUE
Server Address(es):                          127.0.0.1
Server Port:                                  702
LOGINOUT Parameters
-----
Require mutual authentication:                FALSE
Local Device(s):                             <none>
Allow plaintext passwords, on:
    Remote DECnet terminals (RT): FALSE
    Pseudo-terminal devices (FT): TRUE
Attempt Network (Kerberos) Login:            TRUE
Kerberos ticket lifetime (minutes):          480
MultiNet Login command procedure: MULTINET:MULTINET-LOGIN.COM
```

SPAWN

Executes a single DCL command, or, if entered without options, starts a subprocess with the same effect as PUSH. To return from DCL, use the LOGOUT command. SPAWN does not work if the MULTINET_DISABLE_SPAWN logical is defined.

FORMAT

SPAWN [*command*]

PARAMETER

command

Specifies a command to execute. If you omit the command, a DCL command line subprocess is created.

QUALIFIERS

/INPUT=file-spec

Specifies an input file for the process you SPAWN.

/LOGICAL_NAMES

/NOLOGICAL_NAMES

Specifies that logical names and logical name tables are not copied to the subprocess.

/SYMBOLS

/NOSYMBOLS

Specifies that global and local symbols are not passed to the subprocess.

/WAIT

/NOWAIT

Specifies that control of the terminal is returned without waiting for the command to complete. Do not use this qualifier with commands that have prompts or screen displays.

/OUTPUT=file-spec

Specifies a file for the output of the command invoked with SPAWN. This qualifier only works when you enter a single command without creating a DCL subprocess.

EXAMPLES

This example displays terminal information, captures the output in a file, and displays the information with the TYPE command.

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
```

```
ACCESS-CONFIG>SPAWN/OUTPUT=FOO. SHOW TERM  
ACCESS-CONFIG>SPAWN TYPE FOO.
```

This example displays help information about ACCESS-CONFIG. Use the LOGOUT command to return control to ACCESS-CONFIG.

```
ACCESS-CONFIG>SPAWN @COMPROC
```

This example invokes a command procedure.

```
ACCESS-CONFIG>SPAWN  
$ HELP MULTINET CONFIGURE /ACCESS  
.  
.  
.  
$ LOGOUT  
ACCESS-CONFIG>
```

STATUS

Displays the version and whether the configuration has been modified.

FORMAT

STATUS

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS  
MultiNet Access Configuration Utility 4.4(n)  
[Reading in configuration from MULTINET:START_ACCESS.COM]  
ACCESS-CONFIG>STATUS  
This is the MultiNet Access configuration program Version 4.4(n)  
The configuration file MULTINET:START_ACCESS.COM has not been modified.  
ACCESS-CONFIG>
```


USE

Reads in a configuration file. (Functionally equivalent to GET.) You can use other ACCESS-CONFIG commands to display the new configuration.

FORMAT

USE *config_file*

PARAMETER

config_file

Specifies the name of the configuration file to read in.

EXAMPLE

This example reads in the MULTINET:NEW_CONFIG.CFG file.

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>USE MULTINET:NEW_CONFIG.CFG
[Reading in configuration from MULTINET:NEW_CONFIG.CFG;1]
ACCESS-CONFIG>EXIT
```

VERSION

Displays the version number.

FORMAT

VERSION

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS  
MultiNet Access Configuration Utility 4.4(n)  
[Reading in configuration from MULTINET:START_ACCESS.COM]  
ACCESS-CONFIG>VERSION
```

This is the MultiNet Access configuration program Version 4.4(n)

WRITE

Writes the current configuration to a file. (Functionally equivalent to SAVE.)

FORMAT

WRITE [*config_file*]

PARAMETER

config_file

Specifies a configuration file name. The default is the same file from which the configuration was read.

EXAMPLE

```
$ MULTINET CONFIGURE /ACCESS
MultiNet Access Configuration Utility 4.4(n)
[Reading in configuration from MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>WRITE
[Writing configuration to MULTINET:START_ACCESS.COM]
ACCESS-CONFIG>
```


Chapter 9

PRINTER-CONFIG Command Reference

This chapter describes the commands you can run from the PRINTER-CONFIG command line. With PRINTER-CONFIG you can examine, modify, and save configuration files for MultiNet remote print queues.

To invoke PRINTER-CONFIG:

```
$ MULTINET CONFIGURE /PRINTERS
```

At the PRINTER-CONFIG prompt, type ? to list the available commands. For online help use the PRINTER-CONFIG HELP command.

To configure print queues, use the MENU-CONFIG "Configure Print Queues" option.

Changes do not take effect until you do one of the following:

- Restart the MultiNet remote printer queues with the @MULTINET:REMOTE-PRINTER-QUEUES.COM command.
- Restart your system.

For details on configuring MultiNet remote printer queues, refer to the *MultiNet for OpenVMS Installation and Administrator's Guide*.

Command Summary

Table 9-1 lists the commands you can run from the PRINTER-CONFIG prompt.

Table 9-1 PRINTER-CONFIG Command Summary

PRINTER-CONFIG Command	Description
ADD	Adds a new VMS print queue to the current configuration.
ATTACH	Switches the terminal to another process.

Table 9-1 PRINTER-CONFIG Command Summary (Continued)

PRINTER-CONFIG Command	Description
CLEAR	Removes all printer queues from the current configuration.
DELETE	Removes a single printer queue from the current configuration.
ERASE	Removes all printer queues from the current configuration (same as CLEAR).
EXIT	Saves the current printer configuration and leaves PRINTER-CONFIG mode.
GET	Reads in a printer configuration file.
HELP	Displays information about one or all commands.
MODIFY	Changes a printer configuration file.
PUSH	Accesses the DCL command line and pauses PRINTER-CONFIG.
QUIT	Exits PRINTER-CONFIG and prompts to save changes.
SAVE	Writes out the current printer configuration file (same as WRITE).
SELECT	Picks the printer that will be modified by subsequent SET commands.
SET ALLOW-USER-SPECIFIED-PRINTER	Controls whether the print queue allows the use of PRINT/ PARAMETER=(...) for specifying the destination address or printer for an LPD job (to override the original queue configuration).
SET BASE-PRIORITY	Specifies the base process priority at which jobs are initiated from a batch execution queue.
SET BLOCK_LIMIT_LOWER	Limits the size of print jobs that can be processed on an output execution queue.
SET BLOCK_LIMIT_UPPER	Limits the size of print jobs that can be processed on an output execution queue.
SET BURST	Controls whether two file flag pages with a burst bar between them are printed preceding output.

Table 9-1 PRINTER-CONFIG Command Summary (Continued)

PRINTER-CONFIG Command	Description
SET CHARACTERISTICS	Specifies one or more characteristics for processing jobs on an execution queue.
SET DEFAULT-FORM	Sets the default form used when submitting a print job to this printer.
SET DESCRIPTION	Specifies a string of up to 255 characters used to provide operator-supplied information about the queue.
SET FLAG	Forces a VMS banner page to print at the beginning of each file, by default, on the print queue.
SET LIBRARY	Sets the device control library for the print queue.
SET NOFEED	Prevents the VMS print symbiont formatting code from inserting a form feed between pages.
SET OWNER	Sets the owner of the print queue.
SET PROTECTION	Sets the protection of the print queue.
SET RETAIN-ON-ERROR	Retains jobs that terminate in an error in the queue.
SET SCHEDULE-NOSIZE	Prints jobs in the order they were submitted, regardless of size.
SET SEPARATE-BURST	Specifies whether two job flag pages with a burst bar between them are printed at the beginning of each job.
SET SEPARATE-FLAG	Specifies whether a job flag page is printed at the beginning of each job.
SET SEPARATE-RESET	Specifies one or more device control library modules that contain the job reset sequence for the queue.
SET SEPARATE-TRAILER	Specifies whether a job flag page is printed at the end of each job.
SET SUPPRESS-REMOTE-BANNER	When set on an LPD queue, the remote LPD is informed not to print a banner page; many LPD servers do not support this option.
SET SUPPRESS-EOJ-FF	When set on a STREAM queue, the VMS print symbiont formatting code does not add a form feed to the end of the job.

Table 9-1 PRINTER-CONFIG Command Summary (Continued)

PRINTER-CONFIG Command	Description
SET SUPPRESS-TELNET	When set on a STREAM queue, MultiNet does not try to use the TELNET protocol to communicate with the printer.
SET TAB-EXPAND	Forces the VMS print symbiont formatting code to expand TAB characters into the correct number of SPACE characters.
SET TRAILER	Controls whether a file trailer page is printed following output.
SET WS-DEFAULT	Defines for a batch job a working set default, the default number of physical pages that the job can use.
SET WS-EXTENT	Defines for the batch job a working set extent, the maximum amount of physical memory that the job can use.
SET WS-QUOTA	Defines for a batch job a working set quota, the amount of physical memory that is guaranteed to the job.
SHOW	Displays the current printer configuration.
SPAWN	Invokes a DCL command in PRINTER-CONFIG, or starts a subprocess.
STATUS	Displays the status of the printer configuration.
USE	Reads in a configuration file (same as GET).
VERSION	Displays the PRINTER-CONFIG version and release information.
WRITE	Writes out the current printer configuration file.

ADD

Adds a new VMS print queue to the current MultiNet configuration, and prompts for queue configuration parameters.

FORMAT

ADD *queue_name*

PARAMETER

queue_name

Specifies the name of the queue to add to the configuration.

EXAMPLES

This example adds a remote printer queue that prints on the queue named "laser" on remote system 192.0.0.15.

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility V4.4(nn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>ADD SYS$LASER
[Adding new configuration entry for queue "SYS$LPTERM"]
Remote Host Name or IP address: 192.0.0.15
Protocol Type: [LPD] LPD
TCP Port Number: [23] 1495
[SYS$LPTERM => 192.0.0.15, TCP port 1495 (no telnet option negotiation)]
PRINTER-CONFIG>
```

This example adds a remote printer queue that prints data by connecting to TCP port 1395 at address 192.0.0.98.

```
PRINTER-CONFIG>ADD SYS$LPTERM
[Adding new configuration entry for queue "SYS$LPTERM"]
Remote Host Name or IP address: 192.0.0.98
Protocol Type: [LPD] STREAM
TCP Port Number: [23] 1395
[SYS$LPTERM => 192.0.0.98, TCP port 1395 (no telnet option negotiation)]
PRINTER-CONFIG>
```

Note! The Remote Queue Name specified may be case-sensitive. In particular, if the server is a UNIX system, you must specify it in the same case as it occurs in the UNIX /etc/printcap file, usually lowercase.

If the server is an Ethernet card in a printer, the name is not arbitrary. Check the Ethernet card documentation for the correct remote queue name.

ATTACH

Detaches the terminal from the calling process and reattaches it to another process. Use the SPAWN SHOW PROCESS /SUBPROCESSES command to list the names of subprocesses. Use the DCL LOGOUT command to return to the original process. ATTACH does not work if the MULTINET_DISABLE_SPAWN logical is enabled.

FORMAT

ATTACH *process-name*

PARAMETER

process-name

Specifies the name of a process to which you want your terminal attached. (Not all subprocesses can be attached; some testing may be required.)

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>SPAWN
$ MM
MM>SPAWN SHOW PROCESS /SUB
...
There are 3 processes in this job:
_TWA42:
  PROC_1
    PROC_2  (*)
MM>ATTACH _TWA42:
PRINTER-CONFIG>ATTACH PROC_1
MM>QUIT
$ LOGOUT
PRINTER-CONFIG>
```

This example shows the use and exit of attached subprocesses.

- 1 The first command uses SPAWN to create a subprocess. MM is invoked from the DCL command line. Next, the SPAWN SHOW PROCESS/SUB command is used to list all the subprocess names. The display shows that three subprocesses are active. (Process _TWA42: is PRINTER-CONFIG, PROC_1 is MM, and PROC_2 is the SPAWN SHOW PROCESS/SUB command.)
- 2 The MM>ATTACH command returns control to the PRINTER-CONFIG process. From this utility, ATTACH returns control to MM. To exit, QUIT is invoked from MM, and LOGOUT is invoked at the original spawned DCL command line; control returns back to PRINTER-CONFIG. (If SPAWN SHOW PROCESS /SUB had been entered, only this command and the configuration processes would be active.)

CLEAR

Removes all remote printer queues from the current MultiNet configuration.

FORMAT

CLEAR

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS  
MultiNet Remote Printer Configuration Utility 4.4 (nnn)  
PRINTER-CONFIG>CLEAR
```

DELETE

Removes the specified remote print queue from the current MultiNet configuration.

FORMAT

DELETE *queue_name*

PARAMETER

queue_name

Specifies the name of the remote print queue to remove.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>DELETE SYS$LASER
```

ERASE

Removes all printer queues from the current MultiNet configuration. (Functionally equivalent to CLEAR; see CLEAR for additional information.)

EXIT

Saves the current configuration, if it has been modified, then quits.

FORMAT

EXIT

EXAMPLES

When the configuration has not changed, a message displays indicating that the configuration file is not updated.

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>EXIT
[Configuration not modified, so no update needed]
$
```

When the configuration has been changed, a message displays indicating that the configuration file is updated.

```
PRINTER-CONFIG>EXIT
[Writing configuration to MULTINET:REMOTE-PRINTER-QUEUES.COM]
$
```

GET

Reads in a MultiNet remote printer configuration file that defaults to MULTINET:REMOTE-PRINTER-QUEUES.COM.

After a GET, you can use the various configuration commands to modify the printer configuration.

FORMAT

GET *config-file*

PARAMETER

config-file

Specifies the name of the configuration file to read in.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>GET
[Reading in configuration from MULTINET_ROOT:[MULTINET]REMOTE-PRINTER-
QUEUES.COM.68]
```

HELP

Invokes the command help.

FORMAT

HELP [*topics*]

PARAMETER

topics

Contains a space-delimited list of topics that begins with a topic followed by subtopics. The default topic is HELP.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>HELP ?
ADD      ATTACH  CLEAR   DELETE   ERASE    EXIT     GET      HELP
MODIFY   PUSH    QUIT    SAVE     SHOW     SPAWN    STATUS   USE
VERSION  WRITE
PRINTER-CONFIG>
```


MODIFY

Changes the parameters of the specified queue in the MultiNet remote printer configuration.

FORMAT

MODIFY *queue_name*

PARAMETER

queue_name

Specifies the name of the queue whose parameters you want to change.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>MODIFY REMOTE_LASER
[Modifying configuration entry for queue "REMOTE_LASER"]
Remote Host Name: [192.0.0.1] 192.0.0.2
Protocol Type: [LPD] RETURN
Remote Queue Name: [LASER] RETURN
[REMOTE_LASER => 192.0.0.2, LASER]
PRINTER-CONFIG>
```

PUSH

Starts and attaches a DCL subprocess. If a parent process exists, attach to it. To return from DCL, use the ATTACH or the LOGOUT command. To switch back from a DCL subprocess, use the ATTACH command.

PUSH does not work if the MULTINET_DISABLE_SPAWN logical is set.

FORMAT

PUSH

QUIT

If the configuration file has been edited, QUIT prompts you to save the file before leaving.

FORMAT

QUIT

SAVE

Functionally equivalent to **WRITE**; see **WRITE** for additional information.

SELECT

Picks the printer that will be modified by any subsequent SET commands.

FORMAT

SELECT *printer*

PARAMETER

printer

Specifies the name of the printer to pick for modification.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>
```

SET ALLOW-USER-SPECIFIED-PRINTER

Controls whether the print queue allows the use of PRINT/PARAMETER=(...) for specifying the destination address and/or printer for an LPD job (to override the original queue configuration).

FORMAT

SET ALLOW-USER-SPECIFIED-PRINTER { *enable* | *disable* }

PARAMETER

{ **enable** | **disable** }

Specifies whether this function is enabled or disabled.

EXAMPLE

This example shows how to enable the use of PRINT/PARAMETER=(...) to override the original queue configuration.

```
$ MULTINET CONFIGURE /PRINTER
MultiNet Remote Printer Configuration Utility V4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SEL HP-PRINT
[The Selected Printer is now HP-PRINT]
PRINTER-CONFIG>SET ALLOW-USER-SPECIFIED-PRINTER ENABLE
```

SET BASE-PRIORITY

Establishes the base priority of the symbiont process when the symbiont process is created.

By default, if you omit this, the symbiont process is initiated at the same priority as the base priority established by DEFPRI at system generation (usually 4).

FORMAT

SET BASE-PRIORITY *priority*

PARAMETER

priority

Specifies the base priority in decimal format, 0 to 15.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET BASE-PRIORITY 4
PRINTER-CONFIG>
```

SET BLOCK-LIMIT-LOWER

Limits the size of print jobs that can be processed on the queue. Allows you to reserve certain printers for certain size jobs. You can set the lower block limit only if the upper block limit is also set (see SET BLOCK-LIMIT-UPPER).

FORMAT

SET BLOCK-LIMIT-LOWER *lowlim*

PARAMETER

lowlim

The lowlim parameter is a decimal number referring to the minimum number of blocks accepted by the queue for a print job. If a print job is submitted that contains fewer blocks than the lowlim value, the job remains pending until the block limit for the queue is changed. After the block limit for the queue is decreased sufficiently, the job is processed.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET BLOCK-LIMIT-LOWER 25
PRINTER-CONFIG>
```


SET BLOCK-LIMIT-UPPER

Limits the size of print jobs that can be processed on the queue. Allows you to reserve certain printers for certain size jobs.

FORMAT

SET BLOCK-LIMIT-UPPER *uplim*

PARAMETER

uplim

The uplim parameter is a decimal number referring to the maximum number of blocks that the queue accepts for a print job. If a print job is submitted that exceeds this value, the job remains pending until the block limit for the queue is changed. After the block limit for the queue is increased sufficiently, the job is processed.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET BLOCK-LIMIT-UPPER 300
PRINTER-CONFIG>
```

SET BURST

Controls whether two file flag pages with a burst bar between them are printed preceding output.

FORMAT

SET BURST *keyword*

PARAMETER

keyword

If you specify the keyword...	Description
ALL (default)	These flag pages are printed before each fill in the job.
ONE	These flag pages are printed once before the first file in the job.
NONE	No flag pages are printed. It is equivalent to NOBURST.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET BURST ONE
PRINTER-CONFIG>
```

SET CHARACTERISTICS

Specifies one or more characteristics for processing print jobs. If a queue does not have all the characteristics that have been specified for a job, the job remains pending. Only the characteristics specified are established for the queue.

FORMAT

SET CHARACTERISTICS *characteristic*,...

PARAMETER

characteristics,...

Queue characteristics are installation specific. The characteristic parameter can be either a value from 0 to 127 or a characteristic name that has been defined by the **DEFINE /CHARACTERISTIC** command.

Parenthesis are not required; they are added automatically.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET CHARACTERISTICS 56
PRINTER-CONFIG>
```

SET DEFAULT-FORM

Specifies the default form used when submitting a print job to the printer.

FORMAT

SET DEFAULT-FORM *formname*

PARAMETER

formname

Specifies the name of a form previously defined on the system with the DEFINE /FORM command.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET DEFAULT-FORM POSTSCRIPT
[Default Form POSTSCRIPT]
PRINTER-CONFIG>
```

SET DESCRIPTION

Specifies a string of up to 255 characters used to provide operator-supplied information about the queue.

FORMAT

SET DESCRIPTION *string*

PARAMETER

string

Sequence of any printable characters, including spaces. Case of input is preserved. The string may optionally be enclosed in quotation marks (" ").

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET DESCRIPTION THIS IS A TEST QUEUE.
PRINTER-CONFIG>
```

SET FLAG

By default, forces a VMS banner page to print at the beginning of each file on the print queue.

FORMAT

SET FLAG *mode*

PARAMETER

mode

If mode is ENABLE, banner pages are printed; if DISABLE, banner pages are not printed.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET FLAG ENABLE
PRINTER-CONFIG>
```

SET LIBRARY

Sets the print queue's device control library.

FORMAT

SET LIBRARY *libraryfile*

PARAMETER

libraryfile

Specifies the name of a text library located in SYSS\$LIBRARY to be used as the device control library for the print queue.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET LIBRARY SYSDEVCTL
[LIBRARY SYSDEVCTL]
PRINTER-CONFIG>
```

SET NOFEED

Prevents the VMS print symbiont formatting code from inserting a form feed between pages.

FORMAT

SET NOFEED *mode*

PARAMETER

mode

If mode is ENABLE, form feeds are not inserted; if DISABLE, they are inserted.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET NOFEED ENABLE
PRINTER-CONFIG>
```


SET OWNER

Sets the owner of the print queue.

FORMAT

SET OWNER *owner*

PARAMETER

owner

Specifies the identifier or UIC of a user on the system.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET OWNER OPERATOR
[OWNER OPERATOR]
PRINTER-CONFIG>
```

SET PROTECTION

Sets the protection of the print queue.

FORMAT

SET PROTECTION *protection_string*

PARAMETER

protection_string

Specifies a VMS queue protection mask.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET PROTECTION (S:RWED,O:REW,G:RE,W:RE)
[PROTECTION (S:RWED,O:REW,G:RE,W:RE) ]
PRINTER-CONFIG>
```

SET RETAIN-ON-ERROR

Retains jobs in the queue that terminate in an error.

FORMAT

SET RETAIN-ON-ERROR *mode*

PARAMETER

mode

If mode is ENABLE, jobs are retained; if DISABLE, jobs are not retained.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET RETAIN-ON-ERROR ENABLE
PRINTER-CONFIG>
```

SET SCHEDULE-NOSIZE

Prints jobs in the order they were submitted, regardless of size.

FORMAT

SET SCHEDULE-NOSIZE *mode*

PARAMETER

mode

If mode is **ENABLE**, jobs will print in the order they are submitted; if mode is **DISABLE**, jobs will print in order by size (shorter prints before longer).

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SCHEDULE-NOSIZE ENABLE
PRINTER-CONFIG>
```

SET SEPARATE-BURST

Specifies whether two job flag pages with a burst bar between them are printed at the beginning of each job.

FORMAT

SET SEPARATE-BURST *mode*

PARAMETER

mode

If mode is ENABLE, prints the flag pages; if is DISABLE, will not print the flag pages.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SEPARATE-BURST ENABLE
PRINTER-CONFIG>
```

SET SEPARATE-FLAG

Specifies whether a job flag page is printed at the beginning of each job.

FORMAT

SET SEPARATE-FLAG *mode*

PARAMETER

mode

If mode is ENABLE, job flag page will print; if it is DISABLE, job flag page will not print.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SEPARATE-FLAG ENABLE
PRINTER-CONFIG>
```

SET SEPARATE-RESET

Specifies one or more device control library modules that contain the job reset sequence for the queue. The specified modules from the queue's device control library (by default SYS\$LIBRARY:SYSDEVCTL) are used to reset the device at the end of each job. The RESET sequence occurs after any file trailer and before any job trailer. Thus, all job separation pages are printed when the device is in its RESET state.

FORMAT

SET SEPARATE-RESET *module*,...

PARAMETER

module

This is the name of the device control library module.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SEPARATE-RESET cosmos
PRINTER-CONFIG>
```

SET SEPARATE-TRAILER

Specifies whether a job flag page is printed at the end of each job.

FORMAT

SET SEPARATE-TRAILER *mode*

PARAMETER

mode

If mode is ENABLE, job flag page will print; if it is DISABLE, job flag page will not print.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SEPARATE-TRAILER ENABLE
PRINTER-CONFIG>
```


SET SUPPRESS-EOJ-FF

When set on a STREAM queue, the VMS print symbiont formatting code does not add a form feed to the end of the job.

FORMAT

SET SUPPRESS-EOJ-FF *mode*

PARAMETER

mode

If mode is ENABLE, a form feed is not inserted at the end of each job; if DISABLE, a form feed is inserted at the end of each job.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SUPPRESS-EOJ-FF ENABLE
PRINTER-CONFIG>
```

SET SUPPRESS-REMOTE-BANNER

When set on an LPD queue, the remote LPD does not print a banner page. (Many LPD servers do not support this option.)

FORMAT

SET SUPPRESS-REMOTE-BANNER *mode*

PARAMETER

mode

If mode is **ENABLE**, banner pages may or may not be generated on the remote system; if **DISABLE**, banner pages are generated on the remote system.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SUPPRESS-REMOTE-BANNER ENABLE
PRINTER-CONFIG>
```

SET SUPPRESS-TELNET

When set on a STREAM queue, MultiNet does not try to use the TELNET protocol to negotiate options with the remote printer. Most terminal servers expect MultiNet to negotiate TELNET options, and most printers that connect directly to an IP network expect MultiNet not to do so.

FORMAT

SET SUPPRESS-TELNET *mode*

PARAMETER

mode

If mode is ENABLE, TELNET options are not negotiated; if DISABLE, TELNET options are negotiated.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET SUPPRESS-TELNET ENABLE
PRINTER-CONFIG>
```

SET TAB-EXPAND

Forces the VMS print symbiont formatting code to expand TAB characters into the correct number of SPACE characters.

FORMAT

SET TAB-EXPAND *mode*

PARAMETER

mode

If mode is ENABLE, tabs are converted to SPACES; if DISABLE, tabs are not changed.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET EXPAND-TAB ENABLE
PRINTER-CONFIG>
```

SET TRAILER

Controls whether a file trailer page is printed following output.

FORMAT

SET TRAILER *keyword*

PARAMETER

keyword

If you specify the keyword...	Description
ALL (default)	These flag pages are printed before each fill in the job.
ONE	These flag pages are printed once before the first file in the job.
NONE	No flag pages are printed. It is equivalent to NOBURST.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET TRAILER ALL
PRINTER-CONFIG>
```

SET WS-DEFAULT

Establishes the working set default of the symbiont process for the queue when the symbiont process is created.

The value set by this command overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

FORMAT

SET WS-DEFAULT *quota*

PARAMETER

quota

Specify the value as a number of 512-byte pagelets on Alpha systems or 512-byte pages on VAX.

Note! OpenVMS rounds this value up to the nearest CPU-specific page so that actual amount of physical memory allowed may be larger than the specified amount on Alpha. For further information, see the *OpenVMS System Manager's Manual*.

If you specify 0 or NONE, the working set default value defaults to the value specified in the UAF or by the SUBMIT command (if it includes a WSDEFAULT value).

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET WS-DEFAULT 27
PRINTER-CONFIG>
```

SET WS-EXTENT

Establishes the working set extent of the symbiont process for the queue when the symbiont process is created.

The value set by this command overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

FORMAT

SET WS-EXTENT *quota*

PARAMETER

quota

Specify the value as a number of 512-byte pagelets on Alpha or and 512-byte pages on VAX.

Note! OpenVMS rounds this value up to the nearest CPU-specific page so that actual amount of physical memory allowed may be larger than the specified amount on Alpha.

If you specify 0 or NONE, the working set extent value defaults to the value specified in the UAF or by the SUBMIT command (if it includes a WSEXTENT value).

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET WS-EXTENT 0
PRINTER-CONFIG>
```

SET WS-QUOTA

Establishes the working set quota of the symbiont process for the queue when the symbiont process is created. The value set by this command overrides the value defined in the user authorization file (UAF) of any user submitting a job to the queue.

FORMAT

SET WS-QUOTA *quota*

PARAMETER

quota

Specify the value as a number of 512-byte pagelets on OpenVMS Alpha or 512-byte pages on OpenVMS VAX. OpenVMS rounds this value up to the nearest CPU-specific page so that actual amount of physical memory allowed may be larger than the specified amount on OpenVMS Alpha. For further information, see the *OpenVMS System Manager's Manual*.

If you specify 0 or NONE, the working set quota value defaults to the value specified in the UAF or by the SUBMIT command (if it includes a WSQUOTA value).

Working set default, working set quota, and working set extent values are included in each user record in the system UAF. You can specify working set values for individual jobs or for all jobs in a given queue. The decision table shows the action taken for different combinations of specifications that involve working set values.

Is the SUBMIT command value specified?	Is the queue value specified?	Action taken
No	No	Use the UAF value.
No	Yes	Use value for the queue.
Yes	Yes	Use smaller of the two values.
Yes	No	Compare specified value with UAF value; use the smaller.

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:REMOTE-PRINTER-QUEUES.COM]
PRINTER-CONFIG>SELECT TEST
[The Selected Printer is now TEST]
PRINTER-CONFIG>SET WS-QUOTA 12
PRINTER-CONFIG>
```


SHOW

Displays the current MultiNet printer configuration.

FORMAT

SHOW

EXAMPLES

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>SHOW
Queue Name          IP Destination      Remote Queue Name
-----
SYS$LASER           192.0.0.15          laser
SYS$LPTERM          192.0.0.98          TCP port 1395
PRINTER-CONFIG>
```

This example shows detailed queue characteristics for a specific printer called HP5.

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>SHOW HP5
Queue Name          IP Destination      Remote Queue Name
-----
HP5                 192.0.0.9           TCP PORT 9100
Device Control Library = HPLF3SI
Queue Owner = [SUPPORT,*]
Default Form = WHITEPAPER
End of Job Form Feed will be suppressed
Telnet Options Processing will be suppressed
PRINTER-CONFIG>
```

SPAWN

Executes a single DCL command, or if entered without options, starts a subprocess with the same effect as PUSH. To return from DCL, use the LOGOUT command. SPAWN does not work if the MULTINET_DISABLE_SPAWN logical is set.

FORMAT

SPAWN [*command*]

PARAMETER

command

Specifies a command to execute. If you omit command, a DCL command line subprocess is created.

QUALIFIERS

/INPUT=file-spec

Specifies an input file to the command you enter with SPAWN.

/LOGICAL_NAMES

/NOLOGICAL_NAMES

Specifies that logical names and logical name tables are not copied to the subprocess.

/SYMBOLS

/NOSYMBOLS

Specifies that global and local names are not passed to the subprocess.

/WAIT

/NOWAIT

Returns control without waiting for the command to complete. Do not use this qualifier with commands that have prompts or screen displays.

/OUTPUT=file-spec

Specifies a file that retains the output of the command invoked with SPAWN. This qualifier only works when a single command is entered without creating a DCL subprocess. In addition, this qualifier is positional; you must enter it immediately after SPAWN or other qualifiers.

EXAMPLES

This example displays terminal information, captures the output in a file, then displays the information with the TYPE command.

```
$ MULTINET CONFIGURE /PRINTERS
```

```
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
```

```
PRINTER-CONFIG>SPAWN/OUTPUT=FOO. SHOW TERM
PRINTER-CONFIG>SPAWN TYPE FOO.
...
```

This example invokes a command procedure.

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>SPAWN @COMPROC
...
```

This example displays help information about the PRINTER-CONFIG utility. Use the LOGOUT command to return control to PRINTER-CONFIG.

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>SPAWN
$ HELP MULTINET CONFIGURE /PRINTERS
...
$ LOGOUT
PRINTER-CONFIG>
```

STATUS

Shows the status of the MultiNet remote printer configuration program.

FORMAT

STATUS

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>STATUS
This is the MultiNet Remote Printer configuration program Version Example

There are 1/1000 queues in the current configuration.
The configuration MULTINET:REMOTE-PRINTER-QUEUES.COM is not modified.
PRINTER-CONFIG>
```

USE

Functionally equivalent to GET; see GET for additional information.

VERSION

Shows the version and release information of the MultiNet remote printer configuration program.

FORMAT

VERSION

EXAMPLE

```
$ MULTINET CONFIGURE /PRINTERS
MultiNet Remote Printer Configuration Utility 4.4 (nnn)
PRINTER-CONFIG>VERSION
This is the MultiNet Remote Printer configuration program Version Example
PRINTER-CONFIG>
```

WRITE

Writes out the current MultiNet remote printer configuration to a MultiNet remote printer configuration file.

FORMAT

WRITE *config_file*

PARAMETER

config_file

Specifies the name of the file to which to write the current MultiNet printer configuration (by default, the same file from which the configuration was read).

Chapter 10

SERVER-CONFIG Command Reference

This chapter describes the commands you can run from the SERVER-CONFIG command line. SERVER-CONFIG lets you examine, modify, and save configuration files for MultiNet services.

To invoke SERVER-CONFIG:

```
$ MULTINET CONFIGURE /SERVERS
```

SERVER-CONFIG commands affect the configuration of the currently selected service. You can select services with the SELECT command. By default, no service is selected.

At any SERVER-CONFIG prompt, type ? to list the available commands. Use the SERVER-CONFIG HELP command to view online help for each SERVER-CONFIG command.

Changes do not take effect until you do one of the following:

- Reload and restart the MultiNet server process with the MULTINET NETCONTROL command (see MULTINET NETCONTROL).
- Restart your system.

For details on configuring MultiNet services, refer to the *MultiNet for OpenVMS Installation and Administrator's Guide*.

Command Summary

Table 10-1 lists the commands you can run from the SERVER-CONFIG prompt.

Table 10-1 SERVER-CONFIG Command Summary

SERVER-CONFIG Command	Description
ADD	Adds a service to the current configuration.
ATTACH	Switches terminal control to another process.
COPY	Copies a service entry to the current configuration.

Table 10-1 SERVER-CONFIG Command Summary (Continued)

SERVER-CONFIG Command	Description
DELETE	Deletes a service from the current configuration.
DISABLE	Disables a service in the current configuration.
ENABLE	Enables a service in the current configuration.
EXIT	Exits from the SERVER-CONFIG session.
GET	Reads a server configuration file; same as GET.
HELP	Displays command information.
NETCONTROL	Contacts the NETCONTROL server at another site.
PUSH	Accesses the DCL command line while pausing SERVER-CONFIG.
QUIT	Exits SERVER-CONFIG and prompts to save changes.
RESTART	Restarts the master server process.
SAVE	Writes out the current server configuration file.
SELECT	Selects a server for SET commands.
SET ACCEPT-HOSTS	Specifies which hosts can access the server.
SET ACCEPT-NETS	Specifies which networks can access the server.
SET BACKLOG	Specifies the server connection queue limits.
SET CONNECTED	Specifies the connection-request-received routine.
SET DISABLED-NODES	Specifies which VMSccluster nodes cannot execute the service.
SET ENABLED-NODES	Specifies which VMSccluster nodes can execute the service.
SET FLAGS	Specifies the flag bit mask for service operation control.
SET INIT	Specifies the initialize-service routine.
SET KEEPALIVE-TIMERS	Sets keepalive timers for a service.
SET LISTEN	Specifies the listen-for-connections routine.
SET LOG-ACCEPTS	Enables/disables successful connections logging.
SET LOG-FILE	Specifies the log message destination.

Table 10-1 SERVER-CONFIG Command Summary (Continued)

SERVER-CONFIG Command	Description
SET LOG-REJECTS	Enables/disables failed connections logging.
SET MAX-SERVERS	Specifies the service process limit.
SET PARAMETERS	Specifies service-dependent parameters.
SET PRIORITY	Specifies a VMS priority for the created processes.
SET PROCESS	Specifies that the service is to run in an auxiliary master server process rather than in the main master server process.
SET PROGRAM	Specifies a VMS file name for run or merged images.
SET REJECT-BY-DEFAULT	Enables/disables conditional connection rejection.
SET RECEIVE-BUFFER-SPACE	Specifies the size of the receive socket buffers.
SET REJECT-HOSTS	Specifies which hosts are not allowed service access.
SET REJECT-MESSAGE	Specifies a rejected connection message.
SET REJECT-NETS	Specifies which networks are not allowed service access.
SET SEND-BUFFER-SPACE	Specifies the size of the send socket buffers.
SET SERVICE	Specifies the perform-service routine.
SET SERVICE-NAME	Changes the service name.
SET SERVICE-TYPE	Sets the service type advertised for a particular service.
SET SOCKET-FAMILY	Specifies the service family address.
SET SOCKET-OPTIONS	Specifies the setsockopt() options.
SET SOCKET-PORT	Specifies the port for connection listening.
SET SOCKET-TYPE	Specifies the socket type.
SET USERNAME	Specifies the user name under which the selected service is started.
SET WORKING-SET-EXTENT	Specifies how much memory the process will be allowed to use if there are free pages available.
SET WORKING-SET-QUOTA	Specifies the maximum amount of memory the process can lock into its working set.

Table 10-1 SERVER-CONFIG Command Summary (Continued)

SERVER-CONFIG Command	Description
SHOW	Shows the current server configuration.
SHUTDOWN	Stops the master server process.
SPAWN	Invokes the DCL command or creates a subprocess.
STATUS	Shows the SERVER-CONFIG service status.
USE	Reads a server configuration file; same as GET.
VERSION	Shows the SERVER-CONFIG version.
WRITE	Writes the current server configuration; same as SAVE.

ADD

Adds a new service to the current server configuration and prompts you for an initial set of parameters for the service.

FORMAT

ADD *service*

PARAMETER

service

Specifies the name of the service to add to the configuration.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>ADD NNTP
[Adding new configuration entry for service "NNTP"]
Protocol: [TCP] TCP
TCP Port number: 119
Program to run: USER$DISK:[NNTP]NNTP_SERVER.EXE
[Added service NNTP to configuration]
[Selected service is now NNTP]
SERVER-CONFIG>
```

ATTACH

Detaches the terminal from the calling process and reattaches it to another process. Use the SPAWN SHOW PROCESS /SUBPROCESSES command to list the name of subprocesses. Use the DCL LOGOUT command to return to the original process. If the MULTINET_DISABLE_SPAWN logical is enabled, ATTACH does not work.

FORMAT

ATTACH *process-name*

PARAMETER

process-name

Specifies the name of a process to which you want your terminal attached. (Not all subprocesses can be attached; some testing may be required.)

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SPAWN
$ MM
MM>SPAWN SHOW PROCESS /SUB
...
There are 3 processes in this job:
_TWA42:
  PROC_1
  PROC_2 (*)
MM>ATTACH _TWA42:
SERVER-CONFIG>ATTACH PROC_1
MM>QUIT
$ LOGOUT
SERVER-CONFIG>
```

This example shows the use and exit of attached subprocesses.

- 1 The first command uses SPAWN to create a subprocess. MM is invoked from the DCL command line. Next, the SPAWN SHOW PROCESS/SUB command is used to list all the subprocess names. The display shows that three subprocesses are active. (Process _TWA42: is SERVER-CONFIG, PROC_1 is MM, and PROC_2 is the SPAWN SHOW PROCESS/SUB command.)
- 2 In the next command, the MM ATTACH command returns control to the SERVER-CONFIG process. From this utility, ATTACH returns control to MM. To exit, QUIT is invoked from MM, and LOGOUT is entered at the original spawned DCL command line; finally control returns to SERVER-CONFIG. (If SPAWN SHOW PROCESS/SUB had been entered, only this command and the configuration processes would be active.)

COPY

Copies a given service entry. When a service is copied, the copy is automatically disabled. Enable the copy after changing any conflicting parameters, such as the port number.

FORMAT

COPY *input-service output-service*

PARAMETERS

input-service

Specifies the name of the service to duplicate.

output-service

Specifies the name of the service to create.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>COPY FINGER LOCALFINGER
[Adding service LOCALFINGER to configuration]
[Disabling service LOCALFINGER]
SERVER-CONFIG>
```

DELETE

Deletes a given service from the current configuration. Once a service is deleted, all information about that service is removed. See the **DISABLE** command for disabling a service.

FORMAT

DELETE *service*

PARAMETER

service

Specifies the name of the service to delete from the configuration.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS  
MultiNet Server Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]  
SERVER-CONFIG>DELETE NNTP  
SERVER-CONFIG>
```


DISABLE

Disables (removes) a given service from the current configuration. Unlike the DELETE command, all information about the service is retained and the service can be re-enabled at any time after a DISABLE.

FORMAT

DISABLE *service*

PARAMETER

service

Specifies the name of the service to disable from the configuration.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>DISABLE NNTP
SERVER-CONFIG>
```

ENABLE

Enables a previously disabled service. (See DISABLE for information on disabling a service.)

FORMAT

ENABLE *service*

PARAMETER

service

Specifies the name of the service to enable in the configuration.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>ENABLE NNTP
SERVER-CONFIG>
```

EXIT

Saves the current configuration, if it has been modified, then quits.

FORMAT

EXIT

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>ENABLE NNTP
SERVER-CONFIG>EXIT
[Writing configuration to MULTINET_COMMON_ROOT:[MULTINET]
SERVICES.MASTER_SERVER]
$
```

GET

Reads in a MultiNet server configuration file. After a GET, you can use the various configuration commands to modify this server configuration. (Functionally equivalent to USE.)

FORMAT

GET *config_file*

PARAMETER

config_file

Specifies the name of the server configuration file to read in.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>GET ST_TMP:FOO.CONFIGURATION
[Reading in configuration from ST_ROO:[TMP]FOO.CONFIGURATION.1]
SERVER-CONFIG>
```

HELP

Invokes command help.

FORMAT

HELP [*topics*]

PARAMETER

topics

Contains a space-delimited list of topics that begins with a topic followed by subtopics. The default topic is HELP.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>HELP ?
ADD          ATTACH    COPY           DELETE         DISABLE        ENABLE
EXIT         GET        HELP           NETCONTROL    PUSH           QUIT
RESTART      SAVE        SELECT        SET            SHOW           SHUTDOWN
SPAWN        STATUS      USE           VERSION        WRITE
SERVER-CONFIG>
```

NETCONTROL

Transfers control to a configuration manager subsystem that contacts the NETCONTROL server at local or remote sites.

After invoking NETCONTROL, you can issue commands to the NETCONTROL server to affect MULTINET_SERVER operations at that site.

FORMAT

NETCONTROL [*host*]

RESTRICTION

The NETCONTROL server is usually protected from unauthorized access by a restriction list.

PARAMETER

host

Specifies the name of the host to which to connect. If not specified, the default is the local host.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>NETCONTROL
Connected to NETCONTROL server on "127.0.0.1"
<FLOWERS.COM Network Control 4.3 (nnn) at Mon 13-Mar-2002 7:42am-EST
NETCONTROL>
```

PUSH

Starts and attaches a DCL subprocess. If a parent process exists, attach to it. To return from DCL, use the ATTACH or the LOGOUT command. To switch back from a DCL subprocess, use the ATTACH command.

If the MULTINET_DISABLE_SPAWN logical is set, PUSH does not work.

FORMAT

PUSH

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>PUSH
$ LOGOUT
Process foobar_1 logged out at 16-Jun-2002 16:36:22.13
SERVER-CONFIG>
```

QUIT

If the configuration file has been edited, QUIT prompts you to save the file before quitting.

FORMAT

QUIT

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS  
MultiNet Server Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]  
SERVER-CONFIG>QUIT  
$
```


RESTART

Kills the old master server (MULTINET_SERVER) process and starts a new one. Any connections in progress are not interrupted. If the configuration has been modified since the last save, RESTART prompts you to save the configuration before restarting.

FORMAT

RESTART

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>RESTART
%RUN-S-PROC_ID, identification of created process is 2060005c
SERVER-CONFIG>
```

SAVE

Writes the current MultiNet server configuration to a server configuration file. (Functionally equivalent to WRITE.)

FORMAT

SAVE *config_file*

PARAMETER

config_file

Specifies the name of the file to which to write the current MultiNet server configuration (by default, the same file from which the configuration was read).

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SAVE
[Writing configuration to
MULTINET_COMMON_ROOT:[MULTINET]SERVICES.MASTER_SERVER.1103]
SERVER-CONFIG>
```

SELECT

Selects which service will be modified by any subsequent SET commands.

FORMAT

SELECT *service*

PARAMETER

service

Specifies the name of the service to select for modification.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT NNTP
[The Selected SERVER entry is not NNTP]
SERVER-CONFIG>
```

SET ACCEPT-HOSTS

Specifies and maintains a list of hosts allowed access to the service.

FORMAT

SET ACCEPT-HOSTS

EXAMPLE

This example shows how to delete host 192.0.0.1 from the accept-hosts list, and add host 192.0.0.4.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET ACCEPT-HOSTS
Delete address "IP-192.0.0.1" ? [NO] Y
[Address "IP-192.0.0.1" deleted from TELNET]
Delete address "IP-192.0.0.2" ? [NO] RETURN
Delete address "IP-192.0.0.3" ? [NO] RETURN
You can now add new addresses for TELNET. An empty line terminates.
Add Address: 192.0.0.4
Add Address: RETURN
SERVER-CONFIG>
```

SET ACCEPT-NETS

Invokes an interactive utility that prompts you for the addresses of networks that are allowed access to the selected service.

Specify each network as follows:

IP_address [subnetmask]

When done, press **RETURN** at the "Add:" prompt.

For more information about restricting access to services, see the *MultiNet for OpenVMS Installation and Administrator's Guide*.

FORMAT

SET ACCEPT-NETS

EXAMPLE

This example shows how to delete network address 192.0.0.0 from the accept-nets list, and add network address 128.1.0.0.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET ACCEPT-NETS
Delete address "IP-192.0.0.0" ? [NO] Y
[Address "IP-192.0.0.0" deleted from TELNET]
Delete address "IP-192.12.19.0" ? [NO] RETURN
You can now add new addresses for TELNET. An empty line terminates.
Add Address: 128.1.0.0
Add Address:
SERVER-CONFIG>
```

SET BACKLOG

Specifies the number of server connections to queue up before refusing to accept additional connections when MAX-SERVERS is reached.

FORMAT

SET BACKLOG *backlog*

PARAMETER

backlog

Specifies the number of connections to queue—but not process—while waiting for connections that are already running to exit.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET BACKLOG 5
[Backlog of TELNET set to 5]
SERVER-CONFIG>
```

SET CONNECTED

Specifies the name of the internal MULTINET_SERVER routine to call when a connection request is received.

FORMAT

```

                                [ none ]
                                [ tcp_connected ]
                                [ udp_chargen ]
                                [ udp_connected ]
SET CONNECTED [ udp_connected_single ]
                                [ udp_daytime ]
                                [ udp_discard ]
                                [ udp_echo ]
                                [ udp_time ]
```

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET CONNECTED UDP_CONNECTED_SINGLE
[Connected action of TELNET set to UDP_Connected_Single]
SERVER-CONFIG>
```

SET DISABLED-NODES

Specifies and maintains a list of VMSccluster nodes that cannot execute the service.

The master server (MULTINET_SERVER) can be tailored to enable or disable services on a per-node basis in a VMSccluster. Use the SET ENABLED-NODES or SET DISABLED-NODES commands to specify a list of VMSccluster nodes on which the service runs or does not run.

Note! The service must also be enabled via the ENABLE command.

Note! When entering the nodes to be disabled, use only the VMSccluster node name or the DECnet node name; do not use the IP address.

FORMAT

SET DISABLED-NODES

EXAMPLE

This example shows how to delete the node FLEET from the disabled-nodes list, and add the node DRAGO.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET DISABLED-NODES
Delete VMSccluster node "FLEET" ? [NO] Y
[Node "FLEET" deleted from TELNET]
Delete VMSccluster node "NINET9" ? [NO] RETURN
You can now add new VMSccluster nodes for TELNET. An empty line terminates.
Add VMSccluster node: DRAGO
Add Address: RETURN
SERVER-CONFIG>
```


SET ENABLED-NODES

Specifies and maintains a list of VMSccluster nodes that can execute the service.

The master server (MULTINET_SERVER) can be tailored to enable or disable services on a per-node basis in a VMSccluster. Use the SET ENABLED-NODES or SET DISABLED-NODES commands to specify a list of VMSccluster nodes on which the service runs or does not run.

Note! The service must also be enabled via the ENABLE command.

Note! When entering the nodes to be enabled, use only the VMSccluster node name or the DECnet node name; do not use the IP address.

FORMAT

SET ENABLED-NODES

EXAMPLE

This example shows how to delete the node DRAGO from the enabled-nodes list, and add the node FLEET.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET ENABLED-NODES
Delete VMSccluster node "DRAGO" ? [NO] Y
[Node "DRAGO" deleted from TELNET]
Delete VMSccluster node "NINET9" ? [NO] RETURN
You can now add new VMSccluster nodes for TELNET. An empty line terminates.
Add VMSccluster node: FLEET
Add Address: RETURN
SERVER-CONFIG>
```

SET FLAGS

Specifies a bit mask of flags that control the operation of the service. If you do not specify a flag for this command, all existing flags are cleared.

FORMAT

SET FLAGS [*flag1* | *flag2*, . . . | *flag3*]

FLAGS

EUNICE_SERVER

Indicates the connection is not closed until the server process exits, instead of when the server process closes the connection. This flag is required for servers compiled under EUNICE, as the EUNICE runtime opens and closes the channel to the connection many times.

EXOS_SERVER

Indicates that the MULTINET_SERVER process passes the connection to a new process using the EXOS conventions.

MANUAL

Indicates that the MULTINET_SERVER process does not accept a CHAOSnet connection; instead, the created process performs the accept in a nonstandard way.

NO_TELNET_NEGOTIATIONS

Indicates that TELNET option negotiations do not take place. This flag is used with services that use the **Internal_Telnet** INIT() routine.

SNMP_MONITORED

Tells the service handling routines to connect to SNMP Agent X and provide information about the state of the service. You need to define **MULTINET_SNMP_AGENTX 1** and add **AGENTX_PEER 127.0.0.1** in the SNMPD.CONF file. The values returned when SNMP_MONITORED flag is set are the Network Services Monitoring MIB (RFC2788). See page 18-11 in the *Installation and Administrator's Guide* for an example of the Network Services Monitoring MIB. The following values are displayed within **enterprises.105.2.service_port**:

- 1 Service name
- 2 Service port number
- 3 Maximum servers allowed
- 4 Number of active servers
- 5 Number of times the service processing code has been called
- 6 Last I/O status value for the service (generally 0 or 1)

START_AUX_SERVER

Causes the main master server to start the auxiliary master server process automatically.

UCX_SERVER

Configures services written for Compaq TCP/IP Services for OpenVMS (formerly UCX) to work with MultiNet.

EXAMPLES

This example sets the EUNICE_SERVER flag.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET FLAGS EUNICE_SERVER
[TELNET flags set to <EUNICE_SERVER>]
SERVER-CONFIG>
```

This example clears all flags that are set on a service.

```
SERVER-CONFIG>SET FLAGS
[TELNET flags set to <NONE>]
SERVER-CONFIG>
```

SET INIT

Specifies the name of the internal MULTINET_SERVER routine to call to initialize a service.

FORMAT

```
[ cluster_alias_init ]  
[ merge_image ]  
[ netcontrol_init ]  
[ none ]  
[ rpc_init ]  
[ rpc_portmap_init ]  
SET INIT [ tcp_init ]  
[ ucxqio_init ]  
[ udp_init ]  
[ viadecnet_init ]  
[ viapsi_init ]
```

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS  
MultiNet Server Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]  
SERVER-CONFIG>SELECT TELNET  
SERVER-CONFIG>SET INIT MERGE_IMAGE  
[Init action of TELNET set to Merge_Image]  
SERVER-CONFIG>
```

SET KEEPALIVE-TIMERS

Sets keepalive timers for a service.

FORMAT

SET KEEPALIVE-TIMERS *idle-time probe-interval probe-count*

PARAMETERS

idle-time

Specifies the amount of time, in seconds, that a connection should be idle before the first keepalive probe is sent.

probe-interval

Specifies the number of seconds between keepalive probes.

probe-count

Specifies the number of probes that can be sent, with no reply from the other side of the connection, before the connection should be destroyed.

DESCRIPTION

Keepalives are useful in situations when other systems that connect to services provided by your system are subject to frequent crashing, resets, or power-offs (as with personal computers).

TCP/IP connections must normally pass through a three-way handshake sequence to be closed and removed from the connection table. However, if a connection is open but idle, and the remote system is shut off, reset, or crashes, the connection cannot be closed down until an attempt to communicate with the remote system is made. If an application or service does not do this, a keepalive probe can be used to ensure that these dormant connections are cleaned up.

If you set the SO_KEEPALIVE socket option for a service, but you do not explicitly set the KEEPALIVE-TIMERS, the default values are:

- *idle-time* 2 hours
- *probe-interval* 75 seconds
- *probe-count* 8

If you do not set the SO_KEEPALIVE socket option for a service, no keepalive probes will be sent for connections to that service.

SET LISTEN

Specifies the name of the internal MULTINET_SERVER routine to call to listen for connections to the service.

FORMAT

```
[ none ]  
SET LISTEN [ tcp_listen ]  
[ udp_listen ]
```

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS  
MultiNet Server Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]  
SERVER-CONFIG>SELECT TELNET  
SERVER-CONFIG>SET LISTEN TCP_LISTEN  
[Listen action of TELNET set to TCP_Listen]  
SERVER-CONFIG>
```

SET LOG-ACCEPTS

Specifies whether to log successful connections to the service.

FORMAT

SET LOG-ACCEPTS *mode*

PARAMETER

mode

If mode is TRUE, accepted connections are logged to OPCOM or to the log file; if it is FALSE, accepted connections are not logged.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET LOG-ACCEPTS TRUE
SERVER-CONFIG>
```

SET LOG-FILE

Specifies the destination of log messages: a VMS file name, or OPCOM to direct messages to the VMS OPCOM process.

FORMAT

```
SET LOG-FILE [ opcom ]  
               [ file_spec ]
```

PARAMETER

file_spec

Specifies the file specification to which to write the audit records; specify OPCOM to write the audit records to OPCOM.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS  
MultiNet Server Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]  
SERVER-CONFIG>SELECT TELNET  
SERVER-CONFIG>SET LOG-FILE OPCOM  
SERVER-CONFIG>
```


SET LOG-REJECTS

Specifies whether to log rejected connections to the service. A connection can be rejected because of the values of the REJECT-HOSTS, REJECT-NETS, and REJECT-BY-DEFAULT parameters.

FORMAT

SET LOG-REJECTS *mode*

PARAMETER

mode

If mode is TRUE, rejected connections are logged to OPCOM or to the log file; if it is FALSE, rejected connections are not logged.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET LOG-REJECTS TRUE
SERVER-CONFIG>
```

SET MAX-SERVERS

Specifies the maximum number of service processes to allow at any one time. If this limit is reached, additional connections up to BACKLOG are accepted but are not processed until one of the previous connections completes.

FORMAT

SET MAX-SERVERS *number*

PARAMETER

number

Specifies the maximum number of server processes to create for this service.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET MAX-SERVERS 4
[Max_Servers of TELNET set to 4]
SERVER-CONFIG>
```

SET PARAMETERS

Specifies service-dependent parameters. These parameters are passed to the initialization routine of built-in services. (This is normally not used for user-written services. The parameters and their arguments differ on a per-service basis.)

FORMAT

SET PARAMETERS

EXAMPLE

This example enables debugging for the Domain Name Service (DNS).

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT DOMAINNAME
SERVER-CONFIG>SET PARAMETERS
Delete parameter "bootfile MULTINET:DOMAIN-NAME-SERVICE.CONFIGURATION"?
[NO]
You can now add new parameters for DOMAINNAME. An empty line terminates.
Add Parameter: debug 3
Add Parameter:
[Service specific parameters for DOMAINNAME changed]
SERVER-CONFIG>
```

SET PRIORITY

Specifies the VMS process priority to assign to created processes.

FORMAT

SET PRIORITY *priority*

PARAMETER

priority

Specifies the VMS process priority to assign to created processes.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT SMTP
SERVER-CONFIG>SET PRIORITY 5
[Priority of SMTP set to 5]
SERVER-CONFIG>
```

SET PROCESS

Specifies that the service is to run in an auxiliary master server process rather than in the main master server process.

The SET PROCESS command should be used in conjunction with the SET FLAGS start_aux_server command, unless the administrator wants to start the auxiliary server manually.

FORMAT

SET PROCESS *process_name*

PARAMETER

process_name

Specifies the name of the process to run in auxiliary master process mode.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET FLAG start_aux_server
SERVER-CONFIG>SET PROCESS MNSERVER_1
SERVER-CONFIG>SELECT RLOGIN
SERVER-CONFIG>SET FLAG start_aux_server
SERVER-CONFIG>SET PROCESS MNSERVER_1
SERVER-CONFIG>SELECT RSHELL
SERVER-CONFIG>SET FLAG start_aux_server
SERVER-CONFIG>SET PROCESS MNSERVER_1
SERVER-CONFIG>
```

SET PROGRAM

Specifies the VMS file name of the image to run or merge.

FORMAT

SET PROGRAM *file_spec*

PARAMETER

file_spec

Specifies the name of the file containing the server image.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT SMTP
SERVER-CONFIG>SET PROGRAM MULTINET:SMTP_SERVER.EXE
[Program to run for SMTP set to MULTINET:SMTP_SERVER.EXE]
SERVER-CONFIG>
```

SET REJECT-BY-DEFAULT

Specifies whether to reject a connection from a host that does not match any of the ACCEPT-HOSTS, ACCEPT-NETS, REJECT-HOSTS, and REJECT-NETS lists.

FORMAT

SET REJECT-BY-DEFAULT *mode*

PARAMETER

mode

If mode is TRUE, the default is to reject connections; if it is FALSE, the default is to accept them.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT SMTP
SERVER-CONFIG>SET REJECT-BY-DEFAULT TRUE
SERVER-CONFIG>
```

SET RECEIVE-BUFFER-SPACE

Specifies the size of the receive socket buffers.

FORMAT

SET RECEIVE-BUFFER-SPACE *size*

PARAMETER

size

Specifies the size of the receive socket buffers for the selected service.

SET REJECT-HOSTS

Specifies and maintains a list of hosts that are not allowed to access the service.

FORMAT

SET REJECT-HOSTS

EXAMPLE

This example shows how to delete host 192.0.0.1 from the reject-hosts list, and add host 192.0.0.4.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET REJECT-HOSTS
Delete address "IP-192.0.0.1" ? [NO] Y
[Address "IP-192.0.0.1" deleted from TELNET]
Delete address "IP-192.0.0.2" ? [NO] RETURN
Delete address "IP-192.0.0.3" ? [NO] RETURN
You can now add new addresses for TELNET. An empty line terminates.
Add Address: 192.0.0.4
Add Address:
SERVER-CONFIG>
```

SET REJECT-MESSAGE

Specifies a text string to send down the network connection when a service is rejected.

FORMAT

SET REJECT-MESSAGE *string*

PARAMETER

string

This parameter is written down the network connection before closing the connection when a request is rejected.

RESTRICTION

This parameter is ignored on UDP services.

EXAMPLE

This example sets the rejection message to "Service refused."

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET REJECT-MESSAGE Service refused
SERVER-CONFIG>
```

SET REJECT-NETS

Specifies and maintains a list of networks or subnetworks that are not allowed to access the service.

FORMAT

SET REJECT-NETS

DESCRIPTION

SET REJECT-NETS invokes an interactive utility that prompts you for the addresses of networks that are not allowed to access the selected service.

Specify each network as follows:

IP_address [subnetmask]

When done, press **RETURN** at the "Add:" prompt.

For more information about restricting access to services, see the *MultiNet for OpenVMS Installation and Administrator's Guide*.

EXAMPLE

This example deletes network address 192.0.0.0 from the reject-nets list, and adds network address 128.1.0.0.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET REJECT-NETS
Delete address "IP-192.0.0.0" ? [NO] Y
[Address "IP-192.0.0.0" deleted from TELNET]
Delete address "IP-192.12.19.0" ? [NO] RETURN
You can now add new addresses for TELNET. An empty line terminates.
Add Address: 128.1.0.0
Add Address:
SERVER-CONFIG>
```

SET SEND-BUFFER-SPACE

Specifies the size of the send socket buffers.

FORMAT

SET RECEIVE-BUFFER-SPACE *size*

PARAMETERS

size

Specifies the size of the send socket buffers for the selected service.

SET SERVICE

Specifies the name of the internal MULTINET_SERVER routine to call to perform the service.

FORMAT

```

[ internal_ftp ]
[ internal_pop2 ]
[ internal_pop3 ]
[ internal_telnet ]
SET SERVICE [ no_service ]
[ none ]
[ run_program ]
[ tcp_daytime ]
[ tcp_time ]
```

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET SERVICE INTERNAL TELNET
[Service action of TELNET set to Internal_Telnet]
SERVER-CONFIG>
```

SET SERVICE-NAME

Changes the name of the service.

FORMAT

SET SERVICE-NAME *name*

PARAMETER

name

Specifies the new service name.

EXAMPLE

This example shows how to rename a service to "FOO."

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET SERVICE-NAME FOO
[Name of selected service changed to FOO]
SERVER-CONFIG>
```

SET SERVICE-TYPE

For Netware (SPX- or IPX-based) servers, sets the service type advertised for the service. This setting is primarily used by third-party NetWare-based services, and is generally not changed by users.

FORMAT

SET SERVICE-TYPE *service-type*

PARAMETER

service-type

Specifies the NetWare service type for SAP advertisements. This value is a decimal number in the range of 1 through 6535.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT servicename
SERVER-CONFIG>SET SERVICE-TYPE n
[servicename service type is n]
SERVER-CONFIG>
```

SET SOCKET-FAMILY

Specifies the address family of the service.

FORMAT

SET SOCKET-FAMILY *family*

PARAMETER

family

Specifies the new protocol family for this service.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET SOCKET-FAMILY AF_INET
[TELNET socket family is AF_INET]
SERVER-CONFIG>
```


SET SOCKET-OPTIONS

Specifies socket options to be set via **setsockopt()**. See the *MultiNet for OpenVMS Programmer's Reference* for more information on socket options.

FORMAT

SET SOCKET-OPTIONS *options*

PARAMETER

options

Specifies a list of socket options separated by a vertical bar (|).

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET SOCKET-OPTIONS SO_DEBUG | SO_KEEPAIVE
[TELNET socket options set to <SO_DEBUG | SO_KEEPAIVE]
SERVER-CONFIG>
```

SET SOCKET-PORT

Specifies the port number on which to listen for connections.

FORMAT

SET SOCKET-PORT *port*

PARAMETER

port

Specifies the name or number of the port on which to listen.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TELNET
SERVER-CONFIG>SET PORT 10
[TELNET socket port is now 10]
SERVER-CONFIG>
```

SET SOCKET-TYPE

Specifies the type of socket; for example, SOCK_STREAM (TCP) or SOCK_DGRAM (UDP).

FORMAT

SET SOCKET-TYPE *type*

PARAMETER

type

Specifies the socket type to listen on, usually SOCK_DGRAM (UDP) or SOCK_STREAM (TCP).

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT TFTP
SERVER-CONFIG>SET SOCKET-TYPE SOCK_DGRAM
[Socket type of TFTP set to SOCK_DGRAM]
SERVER-CONFIG>
```

SET USERNAME

Specifies the user name under which the selected service is started.

FORMAT

SET USERNAME *username*

PARAMETER

username

Specifies the name of the user under which the selected service is started.

SET WORKING-SET-EXTENT

Specifies how much memory the process will be allowed to use if there are free pages available.

FORMAT

SET WORKING-SET-EXTENT

EXAMPLES

```
1 $ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT FTP
SERVER-CONFIG>SET WORKING-SET 2000
[Working_Set of FTP set to 2000]
SERVER-CONFIG>

2 $ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility V4.4(42)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT FTP
[The Selected SERVER entry is now FTP]
SERVER-CONFIG>SET WORKING-SET-QUOTA 4096
[Working Set Quota of FTP set to 4096]
SERVER-CONFIG>SET WORKING-SET-EXTENT 8192
[Working Set Extent of FTP set to 8192]
```

SET WORKING-SET-QUOTA

Specifies the maximum amount of memory the process can lock into its working set.

FORMAT

SET WORKING-SET-QUOTA

EXAMPLES

1 \$ MULTINET CONFIGURE /SERVERS

```
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT FTP
SERVER-CONFIG>SET WORKING-SET 2000
[Working_Set of FTP set to 2000]
SERVER-CONFIG>
```

2 \$ MULTINET CONFIGURE /SERVERS

```
MultiNet Server Configuration Utility V4.4(42)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SELECT FTP
[The Selected SERVER entry is now FTP]
SERVER-CONFIG>SET WORKING-SET-QUOTA 4096
[Working Set Quota of FTP set to 4096]
SERVER-CONFIG>SET WORKING-SET-EXTENT 8192
[Working Set Extent of FTP set to 8192]
```

SHOW

Shows the current server configuration.

FORMAT

SHOW

QUALIFIER

/FULL

Provides a more detailed listing.

EXAMPLE

This example displays detailed information about SMTP.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SHOW/FULL SMTP
Service "SMTP"
TCP socket (AF_INET,SOCK_STREAM), Port 25
Socket Options = SO_KEEPAIVE
INIT() = TCP_Init
LISTEN() = TCP_Listen
CONNECTED() = TCP_Connected
SERVICE() = Run_Program
Program = "MULTINET:SERVER_SMTP.EXE"
SERVER-CONFIG>
```

SHUTDOWN

Stops the master server (MULTINET_SERVER) process. After a SHUTDOWN, any subsequent network service requests are rejected by MultiNet until the RESTART command is executed.

FORMAT

SHUTDOWN

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS  
MultiNet Server Configuration Utility 4.4 (nnn)  
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]  
SERVER-CONFIG>SHUTDOWN  
SERVER-CONFIG>
```


SPAWN

Executes a single DCL command, or if entered without options, starts a subprocess with the same effect as PUSH. To return from DCL, use the LOGOUT command. If the MULTINET_DISABLE_SPAWN logical is set, SPAWN does not work.

FORMAT

SPAWN [*command*]

PARAMETER

command

Specifies a command to execute. If you omit *command*, a DCL command line subprocess is created.

QUALIFIERS

/INPUT=file-spec

Specifies an input file to the command you enter with SPAWN.

/LOGICAL_NAMES

/NOLOGICAL_NAMES

Specifies that logical names and logical name tables are not copied to the subprocess.

/SYMBOLS

/NOSYMBOLS

Specifies that global and local names are not passed to the subprocess.

/WAIT

/NOWAIT

Returns control without waiting for the command to complete. Do not use this qualifier with commands that have prompts or screen displays.

/OUTPUT=file-spec

Specifies a file that retains the output of the command invoked with SPAWN. This qualifier only works when a single command is entered without creating a DCL subprocess. In addition, this qualifier is positional; you must enter it immediately after SPAWN or other qualifiers.

EXAMPLES

This example displays terminal information, captures the output in a file, then displays the information with the TYPE command.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SPAWN/OUTPUT=FOO. SHOW TERM
SERVER-CONFIG>SPAWN TYPE FOO.
...
```

This example invokes a command procedure.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SPAWN @COMPROC
...
```

This example displays help information about the SERVER-CONFIG utility. Use the LOGOUT command to return control to SERVER-CONFIG.

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>SPAWN
$ HELP MULTINET CONFIGURE /SERVER
...
$ LOGOUT
SERVER-CONFIG>
```

STATUS

Shows the status of the MultiNet server configuration program.

FORMAT

STATUS

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>STATUS
This is the MultiNet Server configuration program Version 4.3 (nnn)
There are 73/200 entries in the current server configuration.
There is NO selected SERVER entry.
The configuration MULTINET:SERVICES.MASTER_SERVER is not modified.
SERVER-CONFIG>
```

USE

Reads in a MultiNet server configuration file. After a USE, you can use the various configuration commands to modify the server configuration. (Functionally equivalent to GET.)

FORMAT

USE *config-file*

PARAMETER

config-file

Specifies the name of the server configuration file to read in.

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>USE ST_TMP:FOO.CONFIGURATION
[Reading in configuration from ST_ROOT:[TMP]FOO.CONFIGURATION.1]
SERVER-CONFIG>
```

VERSION

Displays the MultiNet server configuration program version and release information.

FORMAT

VERSION

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>VERSION
This is the MultiNet Server configuration program Version 4.4 (nnn)
SERVER-CONFIG>
```

WRITE

Writes the current server configuration file. (Functionally equivalent to SAVE.)

FORMAT

WRITE *config-file*

PARAMETER

config-file

Specifies the name of the file to which to write the current MultiNet server configuration (by default, the same file from which the configuration was read).

EXAMPLE

```
$ MULTINET CONFIGURE /SERVERS
MultiNet Server Configuration Utility 4.4 (nnn)
[Reading in configuration from MULTINET:SERVICES.MASTER_SERVER]
SERVER-CONFIG>WRITE
[Writing configuration to
MULTINET_COMMON_ROOT:[MULTINET]SERVICES.MASTER_SERVER.1103]
SERVER-CONFIG>
```

Index

A

ACCESS-CONFIG

command

- ADD 8-4
- ATTACH 8-5
- EXIT 8-6
- GET 8-7
- HELP 8-8
- NETCONTROL 8-9
- PUSH 8-10
- QUIT 8-11
- RELOAD 8-12
- REMOVE 8-13
- SAVE 8-14
- SET 8-15
- SHOW 8-19
- SPAWN 8-20
- STATUS 8-22
- USE 8-23
- VERSION 8-24
- WRITE 8-25

C

COMMON LINK 1-111

COMMON_LINK

- SET /INTERFACE qualifier 1-106

CRYPTOCARD

/DISPLAY keyword

- DECIMAL 2-10
- HEXADECIMAL 2-10
- TELEPHONE 2-11
- USERID 2-11

/KEY keyword

- NUMBER 2-11
- OCTAL 2-11
- SPLIT 2-11
- VALUE 2-12

/PIN parameter

- {FEEDBACK | NOFEEDBACK} 2-13
- FIXED 2-13
- LENGTH 2-13
- TRIES 2-13

D

DECNET-CONFIG command

- ADD 3-3
- ATTACH 3-4
- CLEAR 3-5
- DELETE 3-6
- ERASE 3-7
- EXIT 3-8
- GET 3-9
- HELP 3-10
- MODIFY 3-11
- PUSH 3-12
- QUIT 3-13
- SAVE 3-14
- SHOW 3-15
- SPAWN 3-16
- STATUS 3-18
- USE 3-19
- VERSION 3-20
- WRITE 3-21
- DELETE 10-8

E

- electronic mail xx

F

- FAQs xxii
- fax xxi

H

HELP 10-13

I

interfaces and parameters

- dn 5-4
- nsip 5-4
- pd 5-5
- ppp 5-6
- psi 5-6
- rp 5-7
- se 5-7
- sl 5-8

IPP SHOW 1-39

L

logical

- MULTINET_ANONYMOUS_FTP_DIRECTORY 5-29
- MULTINET_CLUSTER_SERVICE_ADDRESS 5-30
- MULTINET_CLUSTER_SERVICE_NAMES 5-31
- MULTINET_DISABLE_SPAWN 3-4, 3-12, 3-16, 4-8, 4-17, 4-46, 5-13, 5-26, 5-51, 6-13, 6-25, 6-54, 8-5, 8-10, 8-20, 9-6, 9-14, 9-46, 10-6, 10-15, 10-57
- MULTINET_HOST_NAME 5-36
- MULTINET_IP_CLUSTER_ALIASES 5-37
- MULTINET_LOCALDOMAIN 5-40
- MULTINET_LPD_DEFAULT_USERNAME 5-41
- MULTINET_NAMESERVER_RETRANS 5-42
- MULTINET_NAMESERVER_RETRY 5-42
- MULTINET_NAMESERVERS 5-34
- MULTINET_RMT_TAPE_DEVICE 5-32
- MULTINET_SMTP_REPLY_TO 4-3, 4-27
- MULTINET_SPOOL 5-43
- MULTINET_TFTP_DEFAULT_DIRECTORY 5-44
- MULTINET_WHOIS_DEFAULT_SERVER 5-47

M

MAIL-CONFIG command

- ADD GATEWAY 4-5
- ADD LOCAL-DOMAIN 4-6
- ADD QUEUE-GROUP 4-7
- ATTACH 4-8
- CLEAR 4-9
- DELETE GATEWAY 4-10
- DELETE LOCAL-DOMAIN 4-11

- DELETE QUEUE-GROUP 4-12
- ERASE 4-13
- EXIT 4-14
- GET 4-15
- HELP 4-16
- PUSH 4-17
- QUIT 4-18
- REMOVE GATEWAY 4-19
- REMOVE QUEUE-GROUP 4-20
- SAVE 4-21
- SET ACCOUNTING-HOST 4-22
- SET ACCOUNTING-PORT 4-23
- SET ALIAS-FILE 4-24
- SET DECNET-DOMAIN 4-25
- SET DELIVERY-RECEIPTS 4-26
- SET DISABLE-PSIMAIL 4-28
- SET DISALLOW-USER-REPLY-TO 4-27
- SET FORWARDER 4-29
- SET FORWARD-LOCAL-MAIL 4-30
- SET FORWARD-REMOTE-MAIL 4-31
- SET HEADER-CONTROL 4-32
- SET HOST-ALIAS-FILE 4-33
- SET LOCAL-MAIL-FORWARDER 4-34
- SET POSTMASTER 4-35
- SET QUEUE-COUNT 4-36
- SET REPLY-CONTROL 4-37
- SET RESENT-HEADERS 4-38
- SET RETRY-INTERVAL 4-39
- SET RETURN-INTERVAL 4-40
- SET RFC2789 4-41
- SET SEND-BROADCAST-CLASS 4-42
- SET SMTP-HOST-NAMES 4-43
- SET START-QUEUE-MANAGER 4-44
- SHOW 4-45
- SPAWN 4-46
- STATUS 4-47
- USE 4-48
- VERSION 4-49
- WRITE 4-50

MOUNT 1-96

MultiNet

- startup 1-110

MULTINET ACCOUNTING 1-6

MULTINET CHECK 1-7

MULTINET CONFIGURE 1-8

MULTINET DIG 1-11

MULTINET DNSKEYGEN 1-17

MULTINET DNSSIGNER 1-20

MULTINET FONT COMPILE 1-27

MULTINET FONT INFO 1-28

MULTINET FONT LIST 1-29

MULTINET FONT MKFONTDIR 1-30

MULTINET FONT SHOW 1-31

MULTINET FONT UNCOMPILE 1-33

MULTINET HOST_TABLE COMPILE 1-34

MULTINET HOST_TABLE GET 1-36

MULTINET HOST_TABLE INSTALL 1-38
 MULTINET IPP SHOW 1-39
 MULTINET IPP SHOW command
 qualifier
 APPEND 1-40
 ATTRIBUTE 1-39
 FORMAT 1-40
 FULL 1-40
 GLOBAL 1-41
 OUTPUT 1-41
 SYMBOL 1-41
 MULTINET KERBEROS DATABASE DUMP 1-45
 MULTINET KERBEROS DATABASE EDIT 1-46
 prompts 1-46
 MULTINET KERBEROS DATABASE INITIALIZE 1-49
 MULTINET KERBEROS DATABASE LOAD 1-50
 MULTINET KERBEROS DATABASE NEW_
 MASTER_KEY 1-51
 MULTINET KERBEROS DATABASE SRVTAB 1-52
 MULTINET KERBEROS DATABASE STASH 1-53
 MULTINET LOAD 1-54
 MULTINET NETCONTROL 1-55
 MULTINET NFSDISMOUNT 1-77
 MULTINET NFSMOUNT 1-78
 MULTINET NSLOOKUP 1-84
 MULTINET PING 1-91
 OpenVMS status code
 SS\$_DATA_LOST 1-91
 SS\$_IVBUFLN 1-91
 SS\$_NOPRIV 1-91
 SS\$_NORMAL 1-91
 SS\$_NOSUCHNODE 1-91
 SS\$_PROTOCOL 1-91
 SS\$_UNREACHABLE 1-91
 MULTINET PROFILE /DELETE 2-3
 MULTINET PROFILE /MODIFY 2-4
 MULTINET PROFILE /SHOW 2-5
 MULTINET PROFILE /SUMMARY 2-6
 MultiNet public mailing list xxii
 MULTINET RDATE 1-93
 MULTINET RMTALLOC 1-94
 MULTINET RMTALLOC BLOCKSIZE 1-96
 MULTINET RMTALLOC BROKEN 1-97
 MULTINET RMTALLOC COMMENT 1-96
 MULTINET RMTALLOC DENSITY 1-96
 MULTINET RMTALLOC LABEL 1-96
 MULTINET RMTALLOC UNIX 1-97
 MULTINET RWALL 1-101
 MULTINET SET /ARP 1-102
 MULTINET SET /DECNET 1-104
 MULTINET SET /INTERFACE 1-106
 MULTINET SET /ROUTE 1-112
 MULTINET SET /TIMEZONE 1-114
 MULTINET SHOW 1-115
 MULTINET SKEY 2-7
 MULTINET TCPDUMP 1-122

MULTINET TCPVIEW 1-126
 MULTINET TCPVIEW MENU
 CAPTURE 1-128
 FILE 1-127
 FILTER 1-128
 HELP 1-130
 OPTIONS 1-129
 MULTINET TOKEN CRYPTOCARD /CLEAR 2-9
 MULTINET TOKEN CRYPTOCARD /LOAD 2-10
 MULTINET TOKEN CRYPTOCARD /TEST 2-18
 MULTINET TOKEN SKEY /CLEAR 2-19
 MULTINET TOKEN SKEY /INITIALIZE 2-20
 MULTINET TOKEN SKEY /SHOW 2-23
 MULTINET TOKEN SKEY /TEST 2-24
 MULTINET TOKEN SNK /CLEAR 2-25
 MULTINET TOKEN SNK /LOAD 2-26
 MULTINET TOKEN SNK /TEST 2-29
 MULTINET TRACEROUTE 1-131
 MULTINET X11DEBUG 1-134

N

NET-CONFIG

interfaces and parameters 5-4
 prompts 5-8
 ACCM mask 5-8
 address and control field compression 5-8
 authentication method 5-8
 baud rate 5-8
 BSD trailer encapsulation 5-9
 hardware device 5-9
 header compression mode 5-9
 ICMP 5-9
 idle timeout 5-9
 IP address 5-9
 IP address of remote system 5-9
 IP broadcast address 5-10
 IP over DECnet peer host's DECnet name 5-10
 IP over PSI local DTE address 5-10
 IP over PSI peer DTE address 5-10
 IP subnet mask 5-10
 link level encapsulation mode 5-10
 maximum receive unit (MRU) size 5-10
 NetWare link level encapsulation 5-10
 NetWare network number 5-11
 point-to-point device IP destination address 5-11
 protocol compression 5-11
 retry count 5-11
 termination retry count 5-11
 timeout 5-11
 VMS device 5-11

NET-CONFIG command

- ADD 5-4
- ATTACH 5-13
- CHECK 5-14
- CLEAR 5-17
- DELETE 5-18
- DISABLE 5-19
- ENABLE 5-20
- ERASE 5-21
- EXIT 5-22
- GET 5-23
- HELP 5-24
- MODIFY 5-25
- PUSH 5-26
- QUIT 5-27
- SAVE 5-28
- SET ANONYMOUS-FTP-DIRECTORY 5-29
- SET CLUSTER-SERVICE-ADDRESS 5-30
- SET CLUSTER-SERVICE-NAMES 5-31
- SET DEFAULT-RMT-TAPE-DEVICE 5-32
- SET DEFAULT-ROUTE 5-33
- SET DOMAIN-NAMESERVERS 5-34
- SET HOST-NAME 5-36
- SET IP-CLUSTER-ALIASES 5-37
- SET LOAD-EXOS-DRIVER 5-38
- SET LOAD-PWIP-DRIVER 5-39
- SET LOCAL-DOMAIN 5-40
- SET LPD-DEFAULT-USERNAME 5-41
- SET NAMESERVER-RETRANSMISSION 5-42
- SET SPOOL-DIRECTORY 5-43
- SET TFTP-DIRECTORY 5-44
- SET TIMEZONE 5-45
- SET TIMEZONE-RULES 5-46
- SET WHOIS-DEFAULT-SERVER 5-47
- SET WINS-COMPATIBILITY 5-48
- SHOW 5-49
- SPAWN 5-51
- STATUS 5-53
- USE 5-54
- VERSION 5-55
- WRITE 5-56

NETCONTROL

"R" Server command

- DEBUG 1-68
- FLUSH-CACHE 1-69
- SHOW-CACHE 1-69

ACCESS command

- DEBUG 1-58
- RELOAD 1-58

BOOTP command

- DEBUG 1-58
- DUMP 1-58
- RELOAD 1-58

BWNFSD command

- DEBUG 1-59

CLUSTERALIAS command

- DEBUG 1-59
- RELEASE 1-59
- SHOW 1-59

command

- LIST 1-57
- NOOP 1-58
- QUIT 1-58
- QUOTE 1-58
- SELECT 1-58
- SERVER-VERSION 1-58
- STATISTICS 1-58
- TIMERS 1-58
- VERBOSE 1-58
- VERSION 1-58

DHCP client command

- DEBUG 1-59
- SHUTDOWN 1-59
- START 1-59
- VERSION 1-59

DHCP command

- DEBUG 1-60
- DHCP-CONTROL-VERSION 1-60
- DUMP 1-60
- NEWLOG 1-60
- PARTNERDOWN 1-60
- RELEASE 1-60
- RELOAD 1-60
- RESTART 1-60
- SHOW ALL 1-61
- SHOW CID 1-61
- SHOW CLIENT 1-61
- SHOW HADDR 1-61
- SHOW LEASES 1-61
- SHOW POOLS 1-61
- SHOW SUBNET 1-61
- SHUTDOWN 1-61
- START 1-62
- STATISTICS 1-62
- UPDATE 1-62

DOMAINNAME command

- DEBUG 1-62
- DUMP 1-62
- MAXIMUM-TTL 1-62
- MINIMUM-TTL 1-62
- QUERYLOG 1-62
- RELOAD 1-62
- RESTART 1-63
- REWRITE-TTL 1-63
- SHOW 1-63
- SHUTDOWN 1-63
- START 1-63
- STATISTICS 1-63
- STOP 1-63
- VERSION 1-63

- EKLOGIN command
 - DEBUG 1-63
 - FLUSH-CACHE 1-63
- FONTSERVER command
 - DEBUG 1-63
 - FLUSH 1-63
 - FS-CONTROL-VERSION 1-64
 - RELOAD 1-64
 - RESET 1-64
 - RESTART 1-64
 - SHUTDOWN 1-64
 - START 1-64
- GATED command
 - DEBUG 1-64
 - DUMP 1-64
 - TRACE 1-64
 - TRACE-FILE 1-65
- IPXRIP command
 - ADVERTISE 1-65
 - DEBUG 1-65
 - FLUSH 1-65
 - SEND 1-65
 - SHOW 1-65
- KERBEROS command
 - DEBUG 1-65
- KLOGIN command
 - DEBUG 1-65
 - FLUSH-CACHE 1-65
- KSHELL command
 - DEBUG 1-66
 - FLUSH-CACHE 1-66
- NETCONTROL command
 - ACCOUNTING 1-66
 - DEBUG 1-66
 - SHUTDOWN 1-66
- NFS command
 - ADD MOUNT-RESTRICTION 1-66
 - AVERAGE-RESPONSE-TIMES 1-66
 - DUMP 1-66
 - FILECACHE-DEBUG 1-66
 - NFS-CONTROL-VERSION 1-67
 - NFSDEBUG 1-67
 - RECORD-RESPONSE-TIMES 1-67
 - RELOAD 1-67
 - RESTART 1-67
 - RPCDEBUG 1-67
 - SHOW-RESPONSE-TIMES 1-67
 - SHUTDOWN 1-67
 - START 1-67
- NOT command
 - DEBUG 1-67
 - RELOAD 1-67
- NTP command
 - ADJUST-FRACTION 1-68
 - DEBUG 1-68
 - LOG-STATISTICS 1-68
 - SHOW 1-68
- PCNFSD command
 - DEBUG 1-68
- RARP command
 - DEBUG 1-68
 - RELOAD 1-68
- RDISC command
 - DEBUG 1-69
 - FLUSH-CACHE 1-69
- RPCBOOTPARAMS command
 - DEBUG 1-69
 - RELOAD 1-69
- RPCLOCKMGR command
 - DEBUG 1-69
 - NOOP 1-69
 - RPCLOCKMGR-CONTROL-VERSION 1-69
 - SHOW 1-69
 - START 1-69
 - STOP 1-69
 - TIMERS 1-70
- RPCMOUNT command
 - CLEAR 1-70
 - DEBUG 1-70
 - DUMP 1-70
 - RELOAD 1-70
 - SHOW 1-70
- RPCPORTMAP command
 - DEBUG 1-70
 - SHOW 1-70
- RPCSTATUS command
 - DEBUG 1-71
 - RELOAD 1-71
 - SHOW 1-71
 - SIMULATE-CRASH 1-71
- SAP command
 - BROADCAST-DEATHS 1-71
 - DEBUG 1-71
 - FLUSH 1-71
 - NEAREST-SERVER-REPLIES 1-71
 - QUERY 1-71
 - REFRESH 1-71
 - SEND 1-71
 - SHOW 1-71
- SNMP command
 - RELOAD 1-71
 - SHUTDOWN 1-72
 - SNMP-CONTROL-VERSION 1-72
 - START 1-72
- SSH command
 - DEBUG 1-72
 - MASTER_RESTART 1-72
 - RESTART 1-72
 - SHOW 1-73
 - SHUTDOWN 1-73
 - START 1-73
- SYSLOG command
 - DEBUG 1-73
 - RELOAD 1-73

- TELNET command
 - DEBUG 1-73
 - TRACE 1-74
- TFTP command
 - DEBUG 1-74
 - RELOAD 1-74
 - SHOW 1-74
 - SHOW-TRANSLATION 1-74
- UCXQIO command
 - DEBUG 1-74
- VIADECNET command
 - DEBUG 1-74
 - RELOAD 1-74
 - SHUTDOWN 1-74
- VIAPSI command
 - DEBUG 1-75
 - DISCONNECT 1-75
 - IDLE 1-75
 - RELOAD 1-75
 - SHUTDOWN 1-75
- XDM command
 - DEBUG 1-75
 - RELOAD 1-75
 - RESTART 1-75
 - SHOW 1-75
 - SHUTDOWN 1-75
 - START 1-75
 - XDM-CONTROL-VERSION 1-75
- XNTP command
 - DEBUG 1-75
 - RELOAD 1-76
 - SHOW 1-76
 - SHUTDOWN 1-76
 - START 1-76
 - VERSION 1-76
 - WAYTOOBIG 1-76
 - XNTP-CONTROL-VERSION 1-76
- NFS-CONFIG command
 - ADD DECSTATION-MOUNT-POINT 6-6
 - ADD EXPORT 6-7
 - ADD MOUNT-RESTRICTION 6-8
 - ADD NFS-GROUP 6-9
 - ADD NFS-PASSWD-FILE 6-10
 - ADD UID-TRANSLATION 6-11
 - APPEND 6-12
 - ATTACH 6-13
 - CURRENT 6-14
 - DELETE DECSTATION-MOUNT-POINT 6-15
 - DELETE EXPORTED-FILE-SYSTEM 6-16
 - DELETE MOUNT-RESTRICTION 6-17
 - DELETE NFS-GROUP 6-18
 - DELETE NFS-PASSWD-FILE 6-19
 - DELETE UID-TRANSLATION 6-20
 - EXIT 6-21
 - GET 6-22
 - HELP 6-23
 - NETCONTROL 6-24
 - PUSH 6-25
 - QUIT 6-26
 - RELOAD 6-27
 - RESTART 6-28
 - SAVE 6-29
 - SELECT 6-30
 - SET APPROXIMATE-TEXT-SIZE-THRESHOLD 6-31
 - SET DIRECTORY-INFO-FLUSH-AGE 6-32
 - SET DIRECTORY-INFO-IDLE-FLUSH-AGE 6-33
 - SET FILE-CACHE-TIMER-INTERVAL 6-34
 - SET FILE-INFO-FLUSH-AGE 6-35
 - SET FILE-INFO-IDLE-FLUSH-AGE 6-36
 - SET MAXIMUM-CACHE-BUFFERS 6-37
 - SET MAXIMUM-CACHE-FILES 6-38
 - SET MAXIMUM-DIRTY-BUFFERS 6-39
 - SET MAXIMUM-FILESYSTEM-BUFFERS 6-40
 - SET MAXIMUM-FILESYSTEM-CHANNELS 6-41
 - SET MAXIMUM-FILESYSTEM-FILES 6-42
 - SET MAXIMUM-OPEN-CHANNELS 6-43
 - SET MAXIMUM-QUEUED-REMOVES 6-44
 - SET MAXIMUM-WRITE-JOBS 6-45
 - SET NUMBER-OF-DUPLICATE-REQUESTS-CACHED 6-46
 - SET NUMBER-OF-RPC-TRANSPORTS 6-47
 - SET READ-ONLY-FLUSH-AGE 6-48
 - SET READ-WRITE-FLUSH-AGE 6-49
 - SET SECONDS-BEFORE-WRITEBACK 6-50
 - SET USE-DIRECTORY-BLOCKING-ASTS 6-51
 - SET USE-FILE-BLOCKING-ASTS 6-52
 - SHOW 6-53
 - SPAWN 6-54
 - STATUS 6-56
 - USE 6-57
 - VERSION 6-58
 - WRITE 6-59
- MULTINET RMTALLOC 1-96
- NSLOOKUP command
 - exit 1-84
 - finger 1-84
 - help 1-84
 - ls name 1-85
 - lserver 1-85
 - name 1-84
 - name server 1-84
 - root 1-85
 - set all 1-84
 - set class 1-84
 - set d2 1-84
 - set debug 1-84
 - set defname 1-84
 - set domain 1-84
 - set port 1-84
 - set query-type 1-84
 - set recurse 1-84

set retry 1-84
 set root 1-84
 set srchlist 1-84
 set timeout 1-84
 set type 1-84
 set vc 1-84
 NSLOOKUP command server 1-84
 NSLOOKUP/TYPE qualifier 1-86
 NTYCP command
 CREATE PORT 7-3
 DELETE PORT 7-5
 EXIT 7-6
 HELP 7-7
 MODIFY PORT 7-8
 NTYCP CREATE PORT /LOGICAL keyword option
 MODE 7-4, 7-9
 NAME 7-4, 7-8
 TABLE 7-4, 7-9

O

online help xxi

P

parameters
 DNSKEYGEN -n 1-17
 PRINTER-CONFIG command
 ADD 9-5
 ATTACH 9-6
 CLEAR 9-7
 DELETE 9-8
 ERASE 9-9
 EXIT 9-10
 GET 9-11
 HELP 9-12
 MODIFY 9-13
 PUSH 9-14
 QUIT 9-15
 SAVE 9-16
 SELECT 9-17
 SET ALLOW-USER-SPECIFIED-PRINTER 9-18
 SET BASE-PRIORITY 9-19
 SET BLOCK-LIMIT-LOWER 9-20
 SET BLOCK-LIMIT-UPPER 9-21
 SET BURST 9-22
 SET CHARACTERISTICS 9-23
 SET DEFAULT-FORM 9-24
 SET DESCRIPTION 9-25
 SET FLAG 9-26
 SET LIBRARY 9-27
 SET NOFEED 9-28
 SET OWNER 9-29

SET PROTECTION 9-30
 SET RETAIN-ON-ERROR 9-31
 SET SCHEDULE-NOSIZE 9-32
 SET SEPARATE-BURST 9-33
 SET SEPARATE-FLAG 9-34
 SET SEPARATE-RESET 9-35
 SET SEPARATE-TRAILER 9-36
 SET SUPPRESS-EOJ-FF 9-37
 SET SUPPRESS-REMOTE-BANNER 9-38
 SET SUPPRESS-TELNET 9-39
 SET TAB-EXPAND 9-40
 SET TRAILER 9-41
 SET WS-DEFAULT 9-42
 SET WS-EXTENT 9-43
 SET WS-QUOTA 9-44
 SHOW 9-45
 SPAWN 9-46
 STATUS 9-48
 VERSION 9-50
 WRITE 9-51

Process Software World Wide Web server xxii
 PUSH 10-15

Q

qualifiers
 ADD MOUNT-RESTRICTION
 -ro 6-8
 CHECK
 IGNORE_ERRORS 1-7
 OUTPUT 1-7
 VERBOSE 1-7
 CONFIGURE
 ACCESS 1-8
 CONFIGURATION_FILE 1-10
 DECNET 1-8
 INTERFACES 1-8
 MAIL 1-8
 MENU 1-8
 NETWARE 1-9
 NETWORK 1-9
 NFS 1-9
 NOBOLD 1-10
 NOT 1-9
 PRINTERS 1-9
 SERVER_IMAGE 1-10
 SERVERS 1-10
 CREATE PORT
 LOG 7-3
 LOGICAL 7-3
 NODE 7-4
 PORT 7-4
 SERVICE 7-4
 DELETE PORT
 LOG 7-5

DIG

ADDITIONAL 1-11
ADDRESS 1-11
ANSWER 1-11
AUTHORITY 1-12
CLASS 1-12
CMD 1-12
DEBUG 1-12
DEBUG2 1-12
ENVSAVE 1-12
ENVSET 1-12
FILE 1-13
HEADER 1-13
HFLAGS 1-13
IGNORE 1-13
KEEPOPEN 1-13
KEY 1-13
NOADDITIONAL 1-11
NOANSWER 1-11
NOAUTHORITY 1-12
NOCMD 1-12
NODEBUG 1-12
NODEBUG2 1-12
NOHEADER 1-13
NOHFLAGS 1-13
NOIGNORE 1-13
NOKEEPOPEN 1-13
NOPFDEF 1-13
NOPFMIN 1-14
NOQUERY 1-14
NOQUESTION 1-14
NORECURSE 1-14
NOREPLY 1-14
NOSTATS 1-15
NOSTICKY 1-15
NOVC 1-15
PFAND 1-13
PFDEF 1-13
PFMIN 1-14
PFOR 1-14
PFSET 1-14
PING 1-14
PORT 1-14
QUERY 1-14
QUESTION 1-14
RECURSE 1-14
REPLY 1-14
RETRY 1-14
SERVER 1-15
STATS 1-15
STICKY 1-15
TIMEOUT 1-15
TIMEWAIT 1-15
TYPE 1-15
VC 1-15

DNSKEYGEN

-a 1-18
-c 1-18
-D 1-17
DSA_DSS 1-17
-F 1-18
-h 1-18
HOST_KEY 1-18
LARGE_EXPONENT 1-18
NOAUTHENTICATION 1-18
NOENCRYPTION 1-18
-p 1-18
PROTOCOL 1-18
-R 1-17
RSA 1-17
-s 1-18
STRENGTH 1-18
-u 1-18
USER_KEY 1-18
-z 1-18
ZONE_KEY 1-18

DNSSIGNER

BIND 1-21
-bind 1-21
DEBUG 1-22
-dur 1-24
DURATION 1-24
-ess 1-24
-k1 1-25
KEY 1-25
-ks 1-24
-l 1-22
-n 1-22
NXT 1-22
-or 1-22
ORIGIN 1-22
PARENT 1-22
POLICY 1-23
-pt 1-25
PURGE_PERIOD 1-25
SELF_SIGN 1-24
SIG 1-24
-st 1-25
STATISTICS 1-25
ZONE 1-25

FONT_COMPILE

BIT_ORDER 1-27
BYTE_ORDER 1-27
OUTPUT 1-27
PADDING 1-27
SCANLINE 1-27
SERVER 1-27

FONT_INFO

OUTPUT 1-28
SERVER 1-28

- FONT LIST
 - BOUNDS 1-29
 - COLUMNS 1-29
 - LISTING_TYPE 1-29
 - NOSORT 1-29
 - OUTPUT 1-29
 - SERVER 1-29
 - WIDTH 1-29
- FONT SHOW
 - BIT_ORDER 1-31
 - BITMAP_PADDING 1-31
 - BYTE_ORDER 1-31
 - END 1-31
 - EXTENTS 1-31
 - OUTPUT 1-31
 - PADDING 1-31
 - SCANLINE 1-32
 - SERVER 1-32
 - START 1-32
- FONT UNCOMPILE
 - OUTPUT 1-33
 - SERVER 1-33
- HOST_TABLE COMPILE
 - HOST_TABLE_FILE 1-34
 - SILENTLY 1-34
 - STARTING_HASH_VALUE 1-34
 - TBLUK_FILE 1-34
 - UNIX_HOST_FILE 1-35
- HOST_TABLE GET
 - HOST 1-36
 - OUTPUT_FILE 1-36
 - QUERY 1-36
 - SILENTLY 1-36
 - VERSION 1-36
- KERBEROS DATABASE DUMP
 - DATABASE_FILE 1-45
- KERBEROS DATABASE EDIT
 - DATABASE_FILE 1-46
 - PROMPT_FOR_KEY 1-46
- KERBEROS DATABASE INITIALIZE
 - DATABASE_FILE 1-49
 - REALM 1-49
- KERBEROS DATABASE LOAD
 - DATABASE_FILE 1-50
- KERBEROS DATABASE SRVTAB
 - PROMPT 1-52
 - REALM 1-52
- MODIFY PORT
 - LOG 7-8
 - LOGICAL 7-8
 - NODE 7-9
 - PORT 7-9
 - SERVICE 7-9
- NETCONTROL
 - HOST 1-55
 - VERBOSE 1-55
- NFSDISMOUNT
 - ALL 1-77
 - LOG 1-77
- NFSMOUNT
 - FID_CACHE 1-78
 - LOCKING 1-78
 - PAGEFILE 1-78
 - PORT 1-79
 - PRIORITY 1-79
 - PROCESSOR 1-79
 - READ_SIZE 1-79
 - RELOAD 1-79
 - SEMANTICS 1-79
 - SOFT 1-82
 - TIMEOUT 1-82
 - TRANSPORT 1-82
 - UNIQUE_FILENO 1-82
 - VMS_SERVER 1-82
 - VOLUME 1-82
 - WRITE 1-82
 - WRITE_SIZE 1-82
 - WSEXTENT 1-82
 - WSQUOTA 1-83
- NSLOOKUP
 - CLASS 1-85
 - DEBUG 1-85
 - DEBUG2 1-85
 - DEFNAMES 1-85
 - DNSRCH 1-86
 - DOMAIN 1-86
 - IGNTC 1-86
 - NODEBUG 1-85
 - NODEBUG2 1-85
 - NODEFNAMES 1-85
 - NODNSRCH 1-86
 - NOIGNTC 1-86
 - NORECURSE 1-86
 - NOVC 1-87
 - PORT 1-86
 - RECURSE 1-86
 - RETRY 1-86
 - ROOT_SERVER 1-86
 - TIMEOUT 1-86
 - TYPE 1-86
 - VC 1-87
- NSLOOKUP/TYPE
 - A 1-86
 - ANY 1-86
 - AXFR 1-86
 - CNAME 1-87
 - GID 1-87
 - HINFO 1-87
 - MAILB 1-87
 - MB 1-87
 - MG 1-87
 - MINFO 1-87

- MR 1-86
- MX 1-86
- NS 1-86
- PTR 1-87
- SOA 1-87
- TXT 1-87
- UID 1-87
- UINFO 1-87
- WKS 1-87
- NSUPDATE
 - d 1-89
 - DEBUG 1-89
 - K 1-89
 - KEY 1-89
 - NODEBUG 1-89
 - NOVC 1-89
 - V 1-89
 - VC 1-89
- PING
 - DATA_LENGTH 1-91
 - DEBUG 1-91
 - FLOOD 1-91
 - NUMBER_OF_PACKETS 1-92
 - PRELOAD 1-92
 - QUIET 1-92
 - RECORD_ROUTE 1-92
 - ROUTE 1-92
 - VERBOSE 1-92
- PROFILE/DELETE
 - CONFIRM 2-3
 - LOG 2-3
- PROFILE/MODIFY
 - CONFIRM 2-4
 - LOG 2-4
- PROFILE/SHOW
 - FULL 2-5
- RDATE
 - DELTA 1-93
 - LOG 1-93
 - SET 1-93
- RMTALLOC
 - CD 1-94
 - HEADER 1-101
 - HOST 1-101
 - LOG 1-94
 - PASSWORD 1-95
 - SEMANTICS 1-95
 - TRUNCATE_USERNAME 1-97
 - UNIX_SERVER 1-97
 - USERNAME 1-97
 - VMS_ATTRIBUTES 1-97
 - WRITE 1-97
- SAVE
 - STARTUP 5-28
- SET
 - APPROXIMATE_TEXT_SIZE 6-31
- SET /ARP
 - ADD 1-102
 - COMMUNITY_NAME 1-102
 - DELETE 1-102
 - FLUSH 1-102
 - PERMANENT 1-102
 - PROXY 1-102
 - PUBLISH 1-102
 - SNMP_HOST 1-102
- SET /DECNET
 - BUFFERS 1-104
 - CLOSE 1-104
 - CONNECT 1-104
 - DEVICE 1-104
 - FILTER_OUT_OF_ORDER 1-104
 - LOGDATA 1-104
 - LOGERRORS 1-104
 - PORT 1-104
 - REMOTE_ADDRESS 1-104
 - TCP 1-105
- SET /INTERFACE
 - ADDRESS 1-106
 - ARP 1-106
 - COMMON_LINK 1-106
 - COMMUNITY_NAME 1-107
 - D1 1-107
 - D2 1-107
 - D3 1-107
 - DEBUG 1-107
 - DECNET_ETHERNET_ADDRESS 1-107
 - DOWN 1-107
 - DYNAMIC 1-107
 - FFI_BUFFERS 1-108
 - FILTER 1-108
 - HARDWARE_DEVICE 1-108
 - IP_BROADCAST 1-108
 - IP_SUBNET_MASK 1-108
 - LINK_LEVEL 1-108
 - LOCAL 1-109
 - MTU 1-109
 - MULTICAST 1-109
 - PEER 1-109
 - POINT_TO_POINT_DESTINATION 1-109
 - PPP_NOICMP 1-109
 - PPP_OPTIONS 1-109
 - PROTOCOL 1-109
 - RARP 1-110
 - SNMP_HOST 1-110
 - TRAILERS 1-110
 - UP 1-110
 - VMS_DEVICE 1-110
- SET /ROUTE
 - ADD 1-112
 - COMMUNITY_NAME 1-112
 - DELETE 1-112
 - FLUSH 1-112

- FORCE_HOST 1-112
- FORCE_NETWORK 1-112
- NETWORK_IMAGE 1-112
- SNMP_HOST 1-113
- SET /TIMEZONE
 - FILES 1-114
 - LOG 1-114
 - SELECT 1-114
- SHOW
 - ALL 1-115
 - ARP 1-115
 - BUFFERS 1-115
 - COMMUNITY_NAME 1-115
 - CONFIGURATION 1-115
 - CONNECTIONS 1-115
 - CONTINUOUS 1-116
 - FULL 1-116, 6-53, 10-55
 - HOSTS 1-116
 - INTERFACE 1-116
 - IP 1-116
 - LICENSE 1-116
 - MIB_VAR 1-116
 - NFSMOUNT 1-116
 - OUTPUT 1-117
 - PROTOCOLS 1-117
 - QUEUE 1-117
 - REMOTE_HOST 1-117
 - ROUTE 1-117
 - RPC_PORTMAP 1-118
 - SNMP_HOST 1-118
 - STATISTICS 1-118
 - SYMBOLIC_ADDRESSES 1-118
 - TCP 1-119
 - VERSION 1-119
 - WIDTH 1-119
- SKEY
 - COUNT 2-7
 - DELETE 2-7
 - OUTPUT 2-7
 - PRINT 2-7
 - QUEUE 2-7
 - SYMBOL 2-7
- SPAWN
 - INPUT 3-16, 4-46, 5-51, 6-54, 8-20, 9-46, 10-57
 - LOGICAL_NAMES 3-16, 4-46, 5-51, 6-54, 8-20, 9-46, 10-57
 - OUTPUT 3-16, 4-46, 5-51, 6-54, 8-20, 9-46, 10-57
 - SYMBOLS 3-16, 4-46, 5-51, 6-54, 8-20, 9-46, 10-57
 - WAIT 3-16, 4-46, 5-51, 6-54, 8-20, 9-46, 10-57
- TCPDUMP
 - AFTER 1-123
 - BEFORE 1-123
- COUNT 1-123
- DEBUG 1-123
- DEVICE 1-123
- DOMAINS 1-123
- EBCDIC 1-123
- ETHERNET_HEADER 1-123
- FILE_FORMAT=SNIFFER 1-123
- FOREIGN_NUMERICALLY 1-123
- HEXADECIMAL_DUMP 1-123
- INTERFACE 1-123
- NUMERICALLY 1-124
- OUTPUT 1-124
- QUIET 1-124
- READ_BINARY 1-124
- RPC 1-124
- SNAPSHOT_SIZE 1-124
- TIMESTAMPS 1-124
- VERBOSE 1-124
- WRITE_BINARY 1-124
- TCPVIEW
 - COUNT 1-126
 - DEVICE 1-126
 - DOMAINS 1-126
 - ETHERNET_HEADER 1-126
 - FILE_FORMAT 1-126
 - INTERFACE 1-126
 - PROMISCUOUS 1-126
 - SNAPSHOT_SIZE 1-127
 - TIMESTAMPS 1-127
 - VERBOSE 1-127
- TOKEN CRYPTOCARD/CLEAR
 - LOG 2-9
- TOKEN CRYPTOCARD/LOAD
 - CHALLENGE 2-10
 - CONFIRM 2-10
 - DISPLAY 2-10
 - KEY 2-11
 - LANGUAGE 2-12
 - LOG 2-12
 - PIN 2-12
 - TIMEOUT 2-13
 - VERBOSE 2-13
- TOKEN SKEY/CLEAR
 - LOG 2-19
- TOKEN SKEY/INITIALIZE
 - LOG 2-20
 - PASSWORD 2-20
 - SEED 2-21
 - SEQUENCE 2-21
 - VERBOSE 2-21
- TOKEN SNK/CLEAR
 - LOG 2-25
- TOKEN SNK/LOAD
 - CONFIRM 2-26
 - KEY 2-26
 - LOG 2-26

- MODE 2-26
- VERBOSE 2-27
- TRACEROUTE
 - DEBUG 1-132
 - MAXIMUM_TTL 1-132
 - MINIMUM_TTL 1-132
 - NUMBER_OF_PROBES 1-132
 - OUTPUT 1-132
 - PORT 1-132
 - ROUTE 1-132
 - SOURCE 1-132
 - SYMBOLIC_ADDRESSES 1-132
 - TYPE_OF_SERVICE 1-132
 - VERBOSE 1-132
 - WAIT_TIME 1-133
- X11DEBUG
 - LOG 1-134

R

REWIND 1-96

RFCs (Requests for Comment) xxiii

S

SELECT 10-19

SERVER-CONFIG command

- ADD 10-5
- ATTACH 10-6
- COPY 10-7
- DISABLE 10-9
- ENABLE 10-10
- EXIT 10-11
- GET 10-12
- NETCONTROL 10-14
- QUIT 10-16
- RESTART 10-17
- SAVE 10-18
- SET ACCEPT-HOSTS 10-20
- SET ACCEPT-NETS 10-21
- SET BACKLOG 10-22
- SET CONNECTED 10-23
- SET DISABLED-NODES 10-24
- SET ENABLED-NODES 10-25
- SET FLAGS 10-26
- SET INIT 10-28
- SET KEEPALIVE-TIMERS 10-29
- SET LISTEN 10-30
- SET LOG-ACCEPTS 10-31
- SET LOG-FILE 10-32
- SET LOG-REJECTS 10-33
- SET MAX-SERVERS 10-34
- SET PARAMETERS 10-35

- SET PRIORITY 10-36
- SET PROCESS 10-37
- SET PROGRAM 10-38
- SET RECEIVE-BUFFER-SPACE 10-40
- SET REJECT-BY-DEFAULT 10-39
- SET REJECT-HOSTS 10-41
- SET REJECT-MESSAGE 10-42
- SET REJECT-NETS 10-43
- SET SEND-BUFFER-SPACE 10-44
- SET SERVICE 10-45
- SET SERVICE-NAME 10-46
- SET SERVICE-TYPE 10-47
- SET SOCKET-FAMILY 10-48
- SET SOCKET-OPTIONS 10-49
- SET SOCKET-PORT 10-50
- SET SOCKET-TYPE 10-51
- SET USERNAME 10-52
- SET WORKING-SET 10-53
- SET WORKING-SET-QUOTA 10-54
- SHOW 10-55
- SHUTDOWN 10-56
- SPAWN 10-57
- STATUS 10-59
- USE 10-60
- VERSION 10-61
- WRITE 10-62

software patches xxii

startup

- MultiNet 1-110

T

TCPDUMP 1-122, 1-126

TCPVIEW 1-126

typographical conventions xxiv

U

UNLOAD 1-96

USE 9-49

W

WHOIS 5-47

Reader's Comments

MultiNet for OpenVMS Administrator's Reference Guide, v4.4 Part Number: N-5011-44-NN-A

Your comments and suggestions will help us to improve the quality of our future documentation. Please note that this form is for comments on documentation only.

I rate this guide's:	Excellent	Good	Fair	Poor
Accuracy	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Completeness (enough information)	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Clarity (easy to understand)	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Organization (structure of subject matter)	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Figures (useful)	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Index (ability to find topic)	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Ease of use	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>

1. I would like to see more/less: _____
2. Does this guide provide the information you need to perform daily tasks? _____
3. What I like best about this guide: _____
4. What I like least about this guide: _____
5. Do you like this guide's binding? If not, what would you prefer? _____

My additional comments or suggestions for improving this guide:

I found the following errors in this guide:

Page	Description
------	-------------

_____	_____
_____	_____

Please indicate the type of user/reader that you most nearly represent:

System Manager	<input type="radio"/>	Educator/Trainer	<input type="radio"/>
Experienced Programmer	<input type="radio"/>	Sales	<input type="radio"/>
Novice Programmer	<input type="radio"/>	Scientist/Engineer	<input type="radio"/>
Computer Operator	<input type="radio"/>	Software Support	<input type="radio"/>
Administrative Support	<input type="radio"/>	Other (please specify)	<input type="radio"/> _____

Name: _____ Dept. _____
Company: _____ Date _____
Mailing Address: _____

After filling out this form, FAX or mail it to:

Process Software, 959 Concord Street, Framingham, MA 01701-4682
Attention: Marketing Manager FAX 508-879-0042 e-mail: techpubs@process.com

